Administrators Guide

Copyright (c) 2015-2022 The OpenNMS Group, Inc.

OpenNMS Meridian 2020.1.22, Last updated 2022-04-12 14:59:08 UTC

Table of Contents

1. About This Guide	1
1.1. Audience	1
1.2. Related Documentation	1
1.3. Typographical Conventions	1
1.4. Need Help?	2
2. Data Choices.	3
3. User Management	4
3.1. Users	4
3.2. Security Roles	5
3.3. Web UI Pre-Authentication	8
3.3.1. Enabling Pre-Authentication	8
3.3.2. Configuring Pre-Authentication	8
4. Administrative Webinterface	9
4.1. Surveillance View	9
4.1.1. Default Surveillance View Configuration	9
4.1.2. Configuring Surveillance Views	
4.1.3. Categorizing Nodes	11
4.1.4. Creating Views for Users and Groups	11
4.2. Dashboard	
4.2.1. Components	
4.2.2. Advanced configuration	15
4.3. Grafana Dashboard Box	
4.4. Operator Board	
4.4.1. Configuration	25
4.4.2. Dashlets	
4.4.3. Boosting <i>Dashlet</i>	31
4.4.4. Criteria Builder	31
4.5. JMX Configuration Generator	33
4.5.1. Web based utility	33
4.5.2. CLI based utility	
4.6. Heatmap	
4.7. Trend	
5. Service Assurance	
5.1. Pollerd Configuration	
5.1.1. Meta-Data-DSL	51
5.2. Critical Service	52
5.3. Downtime Model	53
5.4. Path Outages	54

5.5. Poller Packages	
5.5.1. Response Time Configuration	
5.5.2. Overlapping Services	
5.5.3. Service Patterns	59
5.5.4. Test Services on manually	
5.5.5. Test filters on Karaf Shell	
5.6. Service monitors	63
5.6.1. Common Configuration Parameters	
5.6.2. Using Placeholders in Parameters	
5.6.3. ActiveMQMonitor	
5.6.4. AvailabilityMonitor	
5.6.5. BgpSessionMonitor	
5.6.6. BSFMonitor	
5.6.7. CiscoIpSlaMonitor	
5.6.8. CiscoPingMibMonitor	
5.6.9. CitrixMonitor	
5.6.10. DhcpMonitor	85
5.6.11. DiskUsageMonitor	
5.6.12. DnsMonitor	
5.6.13. DNSResolutionMonitor	
5.6.14. FtpMonitor	
5.6.15. HostResourceSwRunMonitor	
5.6.16. HttpMonitor	
5.6.17. HttpPostMonitor	
5.6.18. HttpsMonitor	105
5.6.19. IcmpMonitor	106
5.6.20. ImapMonitor	
5.6.21. ImapsMonitor	109
5.6.22. JCifsMonitor	109
5.6.23. JDBCMonitor	
5.6.24. JDBCStoredProcedureMonitor	
5.6.25. JDBCQueryMonitor	
5.6.26. JmxMonitor	
5.6.27. JolokiaBeanMonitor	
5.6.28. LdapMonitor	
5.6.29. LdapsMonitor	
5.6.30. MemcachedMonitor	
5.6.31. NetScalerGroupHealthMonitor	
5.6.32. NrpeMonitor	
5.6.33. NtpMonitor	
5.6.34. OmsaStorageMonitor	

5.6.35. OpenManageChassisMonitor	132
5.6.36. PageSequenceMonitor	
5.6.37. PercMonitor	
5.6.38. Pop3Monitor	
5.6.39. PrTableMonitor	
5.6.40. RadiusAuthMonitor	
5.6.41. SmbMonitor	
5.6.42. SmtpMonitor	
5.6.43. SnmpMonitor	
5.6.44. SshMonitor	158
5.6.45. SSLCertMonitor	159
5.6.46. StrafePingMonitor	
5.6.47. TcpMonitor	165
5.6.48. SystemExecuteMonitor	166
5.6.49. VmwareCimMonitor	169
5.6.50. VmwareMonitor	170
5.6.51. WebMonitor	
5.6.52. Win32ServiceMonitor	
5.6.53. WsManMonitor	
5.6.54. XmpMonitor	
6. Performance Management	
6.1. Configuring <i>Collectd</i>	
6.1.1. Setting the Thread Pool	
6.1.2. Configuring Collector Packages	
6.1.3. Guidelines for Collector Packages	
6.2. Configuring Collectors	182
6.2.1. SnmpCollector	182
6.2.2. JmxCollector	
6.2.3. HttpCollector	
6.2.4. JdbcCollector	
6.2.5. NSClientCollector	
6.2.6. PrometheusCollector	192
6.2.7. TcaCollector	
6.2.8. VmwareCimCollector	195
6.2.9. VmwareCollector	195
6.2.10. WmiCollector	196
6.2.11. WsManCollector	196
6.2.12. XmlCollector	203
6.2.13. XmpCollector	205
6.3. Resource Types	206
6.4. SNMP Property Extenders	209

6.4.1. Cisco CBQoS Property Extender	211
6.4.2. Enum Lookup Property Extender	211
6.4.3. Index Split Property Extender	213
6.4.4. Regex Property Extender	214
6.4.5. Pointer-Like Index Property Extender	216
6.4.6. SNMP Interface Property Extender	220
6.5. Administration and Troubleshooting	223
6.5.1. Collectd Administration	223
6.5.2. Shell Commands	223
7. Thresholding	229
7.1. How Thresholding Works in OpenNMS Meridian	229
7.2. What Triggers a Thresholding Event?	229
7.3. Basic Walk-through – Thresholding	230
7.3.1. Determine You are Collecting Metric	230
7.3.2. Create a Threshold	230
7.3.3. Testing the Threshold	232
7.3.4. Creating a Threshold for CPU Usage	232
7.3.5. Determining the Datasource	233
7.3.6. Create a Threshold Group	
7.3.7. Create a Notification on a Threshold Event	
7.4. Thresholding Service	235
7.4.1. Distributed Thresholding with Sentinel	236
7.5. Shell Commands	236
8. Events	238
8.1. Anatomy of an Event	238
8.2. Sources of Events	238
8.2.1. SNMP Traps	239
8.2.2. Syslog Messages.	239
8.2.3. ReST	241
8.2.4. XML-TCP	241
8.2.5. Receiving IBM Tivoli Event Integration Facility Events	242
8.2.6. TL1 Autonomous Messages	243
8.2.7. Sink	243
8.3. The Event Bus	243
8.3.1. Associate an Event to a given node	243
8.4. Event Configuration	
8.4.1. The eventd-configuration.xml file	244
8.4.2. The eventconf.xml file and its tributaries	244
8.4.3. Reloading the event configuration	249
8.5. Debugging	
8.5.1. Karaf Shell	

9. Alarms	251
9.1. Single Alarm Tracking Problem States	251
9.2. Alarm Service Daemon	252
9.3. Configuring Alarms	253
9.4. Alarm Notes	257
9.5. Alarm Sounds	258
9.6. Flashing Unacknowledged Alarms	259
9.7. Configuring Alarm Sounds and Flashing	259
9.8. Alarm History	260
9.8.1. Requirements	261
9.8.2. Setup	261
9.8.3. Alarm indexing	261
9.8.4. Options	262
10. Notifications	264
10.1. Introduction	264
10.2. Getting Started	264
10.2.1. Enabling Notifications	264
10.2.2. Configuring Destination Paths	264
10.2.3. Configuring Event Notifications	265
10.3. Concepts	265
10.3.1. Events and UEIs	266
10.3.2. Users, Groups, and On-Call Roles	266
10.3.3. Duty Schedules	267
10.3.4. Destination Paths	267
10.3.5. Notification Commands	268
10.4. Bonus Notification Methods	269
10.4.1. Mattermost	269
10.4.2. Slack Notifications	271
11. Provisioning	273
11.1. Introduction	273
11.2. Concepts	273
11.2.1. Terminology	274
11.2.2. Addressing Scalability	275
11.3. Getting Started	
11.3.1. Provisioning the SNMP Configuration	278
11.3.2. Automatic Discovery	280
11.3.3. Enhanced Directed Discovery	281
11.4. Import Handlers	283
11.4.1. Generic Handler	283
11.4.2. File Handler	284
11.4.3. HTTP Handler	284

11.4.4. DNS Handler	284
11.5. Provisioning Examples	286
11.5.1. Basic Provisioning	
11.5.2. Advanced Provisioning Example	292
11.6. Adapters	303
11.6.1. DDNS Adapter	304
11.6.2. RANCID Adapter	304
11.7. Meta-Data assigned to Nodes	304
11.7.1. User defined contexts	304
11.8. Integrating with Provisiond	304
11.8.1. Provisioning Groups of Nodes	305
11.8.2. Example	305
11.9. Provisioning Single Nodes (Quick Add Node)	307
11.10. Fine Grained Provisioning Using <i>provision.pl</i>	307
11.10.1. Create a new requisition	308
11.11. Yet Other API Examples	309
11.12. SNMP Profiles	310
11.13. Auto Discovery with Detectors	312
11.14. Service Detectors	313
11.14.1. Meta-Data-DSL	314
11.14.2. HTTP Detector	314
11.14.3. HTTPS Detector	315
11.14.4. SNMP Detector	315
11.14.5. WS-Man Detector	317
11.14.6. WS-Man WQL Detector	319
11.14.7. Reverse-DNS-Lookup Detector	321
12. Business Service Monitoring	323
12.1. Business Service Hierarchy	324
12.2. Operational status	325
12.3. Root Cause and Impact Analysis	326
12.4. Simulation Mode	328
12.5. Share View	329
12.6. Change Icons	330
12.7. Business Service Definition	330
12.8. Edges	331
12.8.1. Child Services	332
12.8.2. IP Services	332
12.8.3. Custom Reduction Key	333
12.8.4. Application	333
12.9. Map Functions	333
12.10. Reduce Functions	

12.11. Business Service Daemon	
13. Topology Map	
13.1. Properties	
13.2. Edge Status	
13.2.1. Linkd Topology Provider	
13.3. Icons	
13.3.1. Icon resolution	
13.3.2. Change existing icon mappings	
13.3.3. Add new icons	
14. Asset Topology Provider. 343	
14.1. Overview	
14.2. Asset layers	
14.3. Node filtering	
14.4. Configuration	
14.5. Creating Asset Based Topologies From Karaf Consol	
14.6. Creating Asset Based Topologies Using <i>OpenNMS Meridian</i> events	
14.7. Viewing the topology	
14.8. Additional notes	
15. Database Reports	
15.1. Overview	
15.2. Modify existing reports	
15.3. Add a custom report	
15.4. Usage of Jaspersoft Studio	
15.4.1. Connect to the OpenNMS Meridian Database	
15.4.2. Use Measurements Datasource and Helpers	
15.5. Accessing Performance Data	
15.5.1. Fields	
15.5.2. Parameters	
15.6. Disable Scheduler	
15.7. Helper methods	
15.7.1. Usage of the node source descriptor	
15.7.2. Usage of the interface descriptor	
15.7.3. Use HTTPS	
15.8. Limitations	
15.9. Creating PDF Reports from Grafana Dashboards Using OpenNMS Meridian	
15.9.1. Before You Begin	
15.9.2. Configure the Grafana Endpoint	
15.9.3. Creating a PDF of a Grafana Dashboard	
16. Enhanced Linkd	
16.1. Enlinkd Daemon	
16.2. Layer 2 Link Discovery	

16.2.1. LLDP Discovery	
16.2.2. CDP Discovery	
16.2.3. Transparent Bridge Discovery	373
16.3. Layer 3 Link Discovery	
16.3.1. OSPF Discovery	
16.3.2. IS-IS Discovery	
17. OpenTracing	
17.1. Introduction	
17.1.1. Enabling Tracing on <i>OpenNMS Meridian</i>	
17.1.2. Enabling Tracing on <i>Minion</i>	
17.1.3. Enabling Tracing on <i>Sentinel</i>	
18. Operation	
18.1. HTTPS / SSL	
18.1.1. Standalone HTTPS with Jetty	
18.1.2. OpenNMS Meridian as HTTPS client	
18.1.3. Differences between Java Trust Store and Java Key Store	
18.1.4. Debugging / Properties	
18.2. Request Logging	
18.3. Geocoder Service	390
18.3.1. Google	390
18.3.2. Mapquest	
18.3.3. Nominatim	
18.4. newts-repository-converter: Rrd/Jrb to Newts migration utility	
18.4.1. Migration	392
18.4.2. Usage	
18.4.3. Example 1: convert Rrd-based data with storeByGroup enabled	
18.4.4. Example 2: convert JRobin-based data with storeByGroup disabled	
18.5. Configuration Tester	394
18.6. Newts	
18.6.1. Configuration	
18.6.2. Cassandra Monitoring	
18.6.3. Newts Monitoring	402
18.7. Timeseries Integration Layer	405
18.7.1. Configuration	405
18.8. Daemon Configuration Files	408
18.8.1. Eventd	408
18.8.2. Notifd	409
18.8.3. Pollerd	409
18.8.4. Syslogd	
18.8.5. Trapd	
19. System Properties	411

19.1. Configuring system proxies	411
20. Ticketing	413
20.1. JIRA Ticketing Plugin	413
20.1.1. Setup	413
20.1.2. Jira Commands	
20.1.3. Custom fields	415
20.1.4. Troubleshooting	419
20.2. Remedy Ticketing Plugin	419
20.2.1. Remedy Product Overview	419
20.2.2. Supported Remedy Product Versions	419
20.2.3. Setup	419
20.3. TSRM Ticketing Plugin	422
20.3.1. Setup	422
20.3.2. Mapping OpenNMS Ticket with TSRM Incident	423
21. Enabling RMI	
21.1. Enabling RMI	
21.2. Enabling SSL	425
21.3. Connecting to RMI over SSL	425
22. Minion	427
22.1. Using JMS	427
22.1.1. Tuning the ActiveMQ broker	427
22.1.2. Monitoring the ActiveMQ broker using the Karaf shell	427
22.1.3. Authentication and authorization with ActiveMQ	427
22.1.4. Multi-tenancy with <i>OpenNMS Meridian</i> and ActiveMQ	428
22.1.5. Tuning the RPC client in OpenNMS	428
22.1.6. Diagnosing RPC failures	428
22.2. Using AWS SQS	429
22.2.1. OpenNMS Meridian Configuration	429
22.2.2. Minion Configuration	431
22.2.3. SQS Configuration Settings	431
22.2.4. Managing Multiple Environments	433
22.2.5. AWS Credentials	
22.2.6. Limitations	434
22.3. Using Off-heap Storage for Sink Messages	435
22.3.1. Configuring Off-heap Storage	435
22.4. Installing JDBC drivers in Minion	436
22.5. Time to Live (TTL) for RPCs	436
22.5.1. TTLs in Pollerd & Collectd	437
22.5.2. TTLs for the SNMP Collector	437
22.5.3. TTLs for the other SNMP communication	437
22.5.4. TTLs for Provisiond Detectors	

22.5.5. Global TTL	
22.5.6. Using meta-data for TTLs	
23. Sentinel	
23.1. Limitations	
23.2. Installation	
23.3. Clean Start	
23.4. Configuration	
23.4.1. Configure the datasource	
23.4.2. Configure the controller	
23.4.3. Configure Connectivity	
23.4.4. Available features	
23.4.5. Auto install	
23.4.6. Auto Start	
23.4.7. Health Check / Troubleshooting	
23.5. Flow Processing	
23.5.1. Configure Sentinel	
23.5.2. Configure Minion	
23.5.3. Configure OpenNMS	
23.5.4. Auto configure flow processing for Sentinel	
23.6. Persisting Collection Sets to Newts	
23.6.1. Adapters	
23.6.2. Configure Newts	
24. Special Cases and Workarounds	
24.1. Overriding SNMP Client Behavior	
25. IFTTT Integration	
25.1. IFTTT Configuration	
25.2. OpenNMS Configuration	
25.3. Example	
26. DNS Resolver	
26.1. Modules that use DNS Resolution	
26.2. Configuring DNS Resolution	
26.3. Configuring Circuit Breaker	
26.4. Configuring Bulkhead	
27. Telemetry Daemon	
27.1. Listeners and Parsers	
27.2. Adapters	
27.2.1. Working with Minions	
27.3. Queues	
27.3.1. Configuring <i>Queues</i>	
27.4. Push Sensor Data through Minion	
27.5. Reverse hostname resolution	

27.6. Listener Reference	
27.6.1. TCP Listener	
27.6.2. UDP Listener	
27.7. Protocol Reference	
27.7.1. BGP Monitoring Protocol	
27.7.2. IPFIX	
27.7.3. Junos Telemetry Interface	
27.7.4. NetFlow v5	
27.7.5. NetFlow v9	
27.7.6. Cisco NX-OS Telemetry	
27.7.7. sFlow	
27.7.8. Graphite Telemetry	479
28. Elasticsearch Integration	
28.1. Configuration	483
28.2. Credentials	485
28.3. Features	485
28.3.1. Feature Matrix	485
28.3.2. Event Forwarder	485
28.3.3. Flow Support	491
28.3.4. Situation Feedback	491
28.3.5. Alarm History	492
29. Flow Support	493
29.1. Introduction	493
29.1.1. How it works	493
29.2. Setup	493
29.2.1. Configuration Elasticsearch persistence	493
29.2.2. Enabling a protocol	
29.2.3. Linking to OpenNMS Helm in the Web UI	
29.2.4. Node cache configuration (Optional)	496
29.2.5. Classification Exporter Filter cache configuration (Optional)	
29.2.6. Configure Kafka forwarder	
29.3. Classification Engine	
29.3.1. Rule definition	
29.3.2. Omnidirectional Rules	
29.3.3. Rule Groups	
29.3.4. Order of evaluation	
29.3.5. Verification	
29.3.6. Example	500
29.4. Aggregation	501
30. Kafka Producer	502
30.1. Overview	

30.1.1. Events	
30.1.2. Alarms	
30.1.3. Nodes	502
30.1.4. Topologies	503
30.1.5. Metrics	503
30.2. Enabling the Kafka Producer	503
30.3. Configuring the Kafka Producer	
30.3.1. Configuring Filtering	505
30.3.2. Enabling Metric Forwarding	506
30.3.3. Configuring Topic Names	
30.4. Shell Commands	
30.4.1. opennms:kafka-list-alarms	
30.4.2. kafka-producer:sync-alarms	
30.4.3. opennms:kafka-evaluate-filter	
31. Alarm Correlation	509
31.1. Situation Feedback	509
31.1.1. Introduction	509
31.1.2. Installation	509
31.1.3. Requirements	509
32. Meta-Data	
32.1. Contexts	
32.1.1. Node context	
32.1.2. Interface context	
32.1.3. Service context	
32.2. Adding Metadata through the Web UI	
32.3. The Metadata DSL	
32.3.1. Testing an expression	
32.3.2. Uses	
33. OpenNMS Meridian Administration	
33.1. Shutdown	
33.2. Restart	

Chapter 1. About This Guide

Welcome to the OpenNMS Meridian *Administrators Guide*. This documentation provides information and procedures on setup, configuration, and use of the OpenNMS Meridian platform. Using a task-based approach, chapters appear in a recommended order for working with OpenNMS Meridian:

- 1. Opt in or out of usage statistics collection (requirement during first login).
- 2. Setup the admin user.
- 3. Create users and security roles.
- 4. Provision your system.

1.1. Audience

This guide is suitable for administrative users and those who will use OpenNMS Meridian to monitor their network.

1.2. Related Documentation

Installation Guide: how to install OpenNMS Meridian

Developers Guide: information and procedures on developing for the OpenNMS Meridian project

OpenNMS 101: a series of video training tutorials that build on each other to get you up and running with OpenNMS Meridian

OpenNMS 102: a series of stand-alone video tutorials on OpenNMS features

OpenNMS Helm: a guide to OpenNMS Helm, an application for creating flexible dashboards to interact with data stored by OpenNMS

Architecture for Learning Enabled Correlation (ALEC): guide to this framework for logically grouping related faults (alarms) into higher level objects (situations) with OpenNMS.

1.3. Typographical Conventions

Convention	Meaning
bold	Indicates UI elements to click or select in a procedure, and the names of UI elements like dialogs or icons.
italics	Introduces a defined or special word. Also used for the titles of publications.

This guide uses the following typographical conventions:

1.4. Need Help?


code

- join the OpenNMS Discussion chat
- join our community on Discourse
- contact sales@opennms.com to purchase customer support

Chapter 2. Data Choices

The first time a user with the Admin role logs into the system, a prompt appears for permission to allow the Data Choices module to collect and publish anonymous usage statistics to https://stats.opennms.org.

The OpenNMS Group uses this information to help determine product usage, and improve the OpenNMS Meridian software.



Click **Show me what is being sent** to see what information is being collected. Statisitcs collection and publication happen only once an admin user opts-in.

When enabled, the following anonymous statistics are collected and published on system startup and every 24 hours after:

- System ID (a randomly generated UUID)
- OpenNMS Meridian Release
- OpenNMS Meridian Version
- OS Architecture
- OS Name
- OS Version
- Number of alarms in the alarms table
- Number of events in the events table
- Number of IP interfaces in the ipinterface table
- Number of nodes in the node table
- Number of nodes, grouped by System OID



You can enable or disable usage statistics collection at any time by choosing admin>Configure OpenNMS>Additional Tools>Data Choices and choosing Optin or Opt-out in the UI.

Chapter 3. User Management

Users are entities with login accounts in the *OpenNMS Meridian* system. Ideally each user corresponds to a person. An *OpenNMS Meridian User* represents an actor which may be granted permissions in the system by associating *Security Roles. OpenNMS Meridian* stores by default *User* information and credentials in a local embedded file based storage. Credentials and user details, e.g. contact information, descriptions or *Security Roles* can be managed through the *Admin Section* in the Web User Interface.

Beside local *Users*, external authentication services including LDAP / LDAPS, RADIUS, and SSO can be configured. Configuration specifics for these services are outside the scope of this section.

The following paragraphs describe how to manage the embedded *User* and *Security Roles* in *OpenNMS Meridian*.

3.1. Users

Managing *Users* is done through the *Web User Interface* and requires to login as a *User* with administrative permissions. By default the *admin* user is used to initially create and modify *Users*. The *User*, *Password* and other detail descriptions are persisted in users.xml file. It is not required to restart *OpenNMS Meridian* when *User* attributes are changed.

In case administrative tasks should be delegated to an *User* the *Security Role* named *ROLE_ADMIN* can be assigned.



Don't delete the *admin* and *rtc* user. The *RTC* user is used for the communication of the Real-Time Console on the start page to calculate the node and service availability.



Change the default *admin* password to a secure password.

How to set a new password for any user

- 1. Login as a **User** with administrative permissions
- 2. Choose **Configure OpenNMS** from the user specific main navigation which is named as your login user name
- 3. Choose Configure Users, Groups and On-Call roles and select Configure Users
- 4. Click the Modify icon next to an existing User and select Reset Password
- 5. Set a new Password, Confirm Password and click OK
- 6. Click **Finish** to persist and apply the changes

How users can change their own password

- 1. Login with user name and old password
- 2. Choose **Change Password** from the user specific main navigation which is named as your login user name

- 3. Select Change Password
- 4. Identify yourself with the old password and set the new password and confirm
- 5. Click Submit
- 6. Logout and login with your new password

How to create or modify user

- 1. Login as a **User** with administrative permissions
- 2. Choose **Configure OpenNMS** from the user specific main navigation which is named as your login user name
- 3. Choose Configure Users, Groups and On-Call roles and select Configure Users
- 4. Use **Add new user** and type in a **login name** as *User ID* and a **Password** with confirmation or click **Modify** next to an existing *User*
- 5. *Optional*: Fill in detailed *User Information* to provide more context information around the new user in the system
- 6. Optional: Assign Security Roles to give or remove permissions in the system
- 7. *Optional*: Provide *Notification Information* which are used in *Notification* targets to send messages to the *User*
- 8. Optional: Set a schedule when a User should receive Notifications
- 9. Click Finish to persist and apply the changes



Please note that angle brackets (<>), single (') and double quotation marks ("), and the ampersand symbol (&) are not allowed to be used in the user ID.



By default a new *User* has the *Security Role* similar to *ROLE_USER* assigned. Acknowledgment and working with *Alarms* and *Notifications* is possible. The *Configure OpenNMS* administration menu is not available.

How to delete existing user

- 1. Login as a **User** with administrative permissions
- 2. Choose **Configure OpenNMS** from the user specific main navigation which is named as your login user name
- 3. Choose Configure Users, Groups and On-Call roles and select Configure Users
- 4. Use the trash bin icon next to the User to delete
- 5. Confirm delete request with **OK**

3.2. Security Roles

A *Security Roles* is a set of permissions and can be assigned to an *User*. They regulate access to the Web User Interface and the *ReST API* to exchange monitoring and inventory information. In case of a distributed installation, the *Remote Poller* instances interact with *OpenNMS Meridian* and require specific permissions which are defined in the *Security Role ROLE_REMOTING*. The following

Table 1. Functions	and existing system roles in OpenNMS Meridian	

Security Role Name	Description
anyone	In case the opennms-webapp-remoting package is installed, any user can download the <i>Java Webstart</i> installation package for the remote poller from http://opennms.server:8980/opennms-remoting/webstart/app.jnlp.
ROLE_ANONYMO US	Allows <i>HTTP OPTIONS</i> request to show allowed HTTP methods on a ReST resources and the login and logout page of the Web User Interface.
ROLE_ADMIN	Permissions to create, read, update and delete in the Web User Interface and the <i>ReST API</i> .
ROLE_ASSET_EDI TOR	Permissions to just update the asset records from nodes.
ROLE_DASHBOA RD	Allow users to just have access to the <i>Dashboard</i> .
ROLE_DELEGATE	Allows actions (such as acknowledging an alarm) to be performed on behalf of another user.
ROLE_JMX	Allows retrieving JMX metrics but does not allow executing MBeans of the <i>OpenNMS Meridian</i> JVM, even if they just return simple values.
ROLE_MOBILE	Allow user to use <i>OpenNMS COMPASS</i> mobile application to acknowledge <i>Alarms</i> and <i>Notifications</i> via the ReST API.
ROLE_PROVISIO N	Allow user to use the <i>Provisioning System</i> and configure <i>SNMP</i> in <i>OpenNMS Meridian</i> to access management information from devices.
ROLE_READONL Y	Limited to just read information in the Web User Interface and are no possibility to change <i>Alarm</i> states or <i>Notifications</i> .
ROLE_REMOTIN G	Permissions to allow access from a <i>Remote Poller</i> instance to exchange monitoring information.
ROLE_REST	Allow users interact with the whole ReST API of OpenNMS Meridian
ROLE_RTC	Exchange information with the <i>OpenNMS Meridian Real-Time Console</i> for availability calculations.
ROLE_USER	Default permissions of a new created user to interact with the Web User Interface which allow to escalate and acknowledge <i>Alarms</i> and <i>Notifications</i> .

How to manage Security Roles for Users:

- 1. Login as a **User** with administrative permissions
- 2. Choose **Configure OpenNMS** from the user specific main navigation which is named as your login user name

- 3. Choose Configure Users, Groups and On-Call roles and select Configure Users
- 4. Modify an existing **User** by clicking the modify icon next to the **User**
- 5. Select the Role from Available Roles in the Security Roles section
- 6. Use Add and Remove to assign or remove the Security Role from the User
- 7. Click **Finish** to persist and apply the Changes
- 8. Logout and Login to apply the new Security Role settings

How to add custom roles

- Create a file called \$OPENNMS_HOME/etc/security-roles.properties.
- Add a property called roles, and for its value, a comma separated list of the custom roles, for example:

roles=operator,stage

• After following the procedure to associate the security roles with users, the new custom roles will be available as shown on the following image:

Modify User: operator		
User Passwo	rd	
	Reset Password	
User Information	tion	
Full Name:	operator	
Comments:	An operator user	
		<i>h</i>
Security Roles:	Available Roles	Currently in User
	» Add	« Remove

:imagesdir: ../../images

3.3. Web UI Pre-Authentication

It is possible to configure *OpenNMS Meridian* to run behind a proxy that provides authentication, and then pass the pre-authenticated user to the *OpenNMS Meridian* webapp using a header.

The pre-authentication configuration is defined in **\$OPENNMS_HOME/jetty-webapps/opennms/WEB-INF/spring-security.d/header-preauth.xml**. This file is automatically included in the Spring Security context, but is not enabled by default.



DO NOT configure *OpenNMS Meridian* in this manner unless you are certain the web UI is only accessible to the proxy and not to end-users. Otherwise, malicious attackers can craft queries that include the pre-authentication header and get full control of the web UI and ReST APIs.

3.3.1. Enabling Pre-Authentication

Edit the header-preauth.xml file, and set the enabled property:

```
<beans:property name="enabled" value="true" />
```

3.3.2. Configuring Pre-Authentication

There are a number of other properties that can be set to change the behavior of the preauthentication plugin.

Property	Description	Default
enabled	Whether the pre-authentication plugin is active.	false
failOnError	If true, disallow login if the header is not set or the user does not exist. If false, fall through to other mechanisms (basic auth, form login, etc.)	false
userHeader	The HTTP header that will specify the user to authenticate as.	X-Remote-User
credentialsHeader	A comma-separated list of additional credentials (roles) the user should have.	

Chapter 4. Administrative Webinterface

4.1. Surveillance View

When networks are larger and contain devices of different priority, it becomes interesting to show at a glance how the "whole system" is working. The surveillance view aims to do that. By using categories, you can define a matrix which allows to aggregate monitoring results. Imagine you have 10 servers with 10 internet connections and some 5 PCs with DSL lines:

	Server s	Internet Connections
Super important	1 of 10	0 of 10
Slightly important	0 of 10	0 of 10
Vanity	4 of 10	0 of 10

The whole idea is to give somebody at a glance a hint on where the trouble is. The matrix-type of display allows a significantly higher aggregation than the simple list. In addition, the surveillance view shows nodes rather than services - an important tidbit of information when you look at categories. At a glance, you want to know how many of my servers have an issue rather than how many services in this category have an issue.

Home / Surveillance				
Surveillance view: default default				
default	PROD	TEST	DEV	
Routers	0 of 8	0 of 0	0 of 0	
Switches	0 of 1	0 of 0	0 of 0	
Servers	1 of 17	0 of 0	0 of 0	

Figure 1. Example of a configured Surveillance View

The visual indication for outages in the surveillance view cells is defined as the following:

- No services down: green as normal
- One (1) service down: yellow as warning
- More than one (1) services down: red as critical

This Surveillance View model also builds the foundation of the Dashboard View.

4.1.1. Default Surveillance View Configuration

Surveillance Views are defined in the surveillance-views.xml file. This file resides in the OpenNMS Meridian etc directory.



This file can be modified in a text editor and is reread every time the *Surveillance View* page is loaded. Thus, changes to this file do not require *OpenNMS Meridian* to be restarted.

The default configuration looks like this:

```
<?xml version="1.0" encoding="UTF-8"?>
<surveillance-view-configuration
 xmlns:this="http://www.opennms.org/xsd/config/surveillance-views"
 xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance"
 xsi:schemaLocation="http://www.opennms.org/xsd/config/surveillance-views
http://www.opennms.org/xsd/config/surveillance-views.xsd"
 default-view="default" >
 <views >
    <view name="default" refresh-seconds="300" >
     <rows>
        <row-def label="Routers" >
         <category name="Routers"/>
        </row-def>
        <row-def label="Switches" >
          <category name="Switches" />
        </row-def>
        <row-def label="Servers" >
          <category name="Servers" />
        </row-def>
     </rows>
     <columns>
        <column-def label="PROD" >
          <category name="Production" />
        </column-def>
        <column-def label="TEST" >
          <category name="Test" />
        </column-def>
        <column-def label="DEV" >
          <category name="Development" />
        </column-def>
     </columns>
    </view>
 </views>
</surveillance-view-configuration>
```

Please note, that the old report-category attribute is deprecated and is no longer supported.

4.1.2. Configuring Surveillance Views

The *Surveillance View* configuration can also be modified using the *Surveillance View Configurations* editor on the *OpenNMS Meridian Admin* page.

ME	EDIT	REMOVE	PREVIEW	DEFAULT
shboard-user	Edit	Remove	Preview	0
fault	Edit	Remove	Preview	
c-group	Edit	Remove	Preview	0

Figure 2. The Surveillance View Configurations UI

This page gives an overview of the configured *Surveillance Views* and allows the user to edit, remove or even preview the defined *Surveillance View*. Furthermore, the default *Surveillance View* can be selected using the checkbox in the *DEFAULT* column.

When editing a *Surveillance View* the user has to define the view's title and the time in seconds between successive refreshes. On the left side of this dialog the defined rows, on the right side the defined columns are listed. Beside adding new entries an user can modify or delete existing entries. Furthermore, the position of an entry can be modified using the up/down buttons.

Title default		
Refresh seconds 300		
rows	COLUMNS	
Routers	Add PROD	Add
witches	Edit	Edit
Servers	Remove DEV	Remove
SXi Servers		
OpenStack Infrastructure		
torage Devices		
Power Devices		

Figure 3. Editing a Surveillance View

Editing row or column definitions require to choose an unique label for this entry and at least one *OpenNMS Meridian* category. When finished you can hit the *Save* button to persist your modified configuration or *Cancel* to close this dialog.

4.1.3. Categorizing Nodes

In order to categorize nodes in the Surveillance View, choose a node and click *Edit* beside *Surveillance Category Memberships*. Recalling from your *Surveillance View*, choose two categories that represent a column and a row, for example, *Servers* and *Test*, then click *Add*.

4.1.4. Creating Views for Users and Groups

You can use user and group names for *Surveillance Views*. When the *Surveillance View* page is invoked the following criteria selects the proper *Surveillance View* to be displayed. The first

matching item wins:

- 1. Surveillance View name equal to the user name they used when logging into OpenNMS Meridian.
- 2. Surveillance View name equal to the user's assigned OpenNMS Meridian group name
- 3. Surveillance View name equal to the default-view attribute in the surveillance-views.xml configuration file.

4.2. Dashboard

In Network Operation Centers *NOC* an overview about issues in the network is important and often described as *Dashboards*. Large networks have people (Operator) with different responsibilities and the *Dashboard* should show only information for a given *monitoring context*. Network or Server operator have a need to customize or filter information on the *Dashboard*. A *Dashboard* as an At-a-glance overview is also often used to give an entry point for more detailed diagnosis through the information provided by the monitoring system. The *Surveillance View* allows to reduce the visible information by selecting rows, columns and cells to quickly limit the amount of information to navigate through.

4.2.1. Components

The *Dashboard* is built with five components:

- Surveillance View: Allows to model a monitoring context for the Dashboard.
- *Alarms*: Shows unacknowledged *Alarms* which should be escalated by an *Operator*.
- Notifications: Shows outstanding and unacknowledged notifications sent to Engineers.
- Node Status: Shows all ongoing network Outages.
- Resource Graph Viewer: Shows performance time series reports for performance diagnosis.

The following screenshot shows a configured *Dashboard* and which information are displayed in the components.

Figure 4. Dashboard with configured surveillance view and current outage

The following section describe the information shown in each component. All other components display information based on the *Surveillance View*.

Surveillance View

The Surveillance View has multiple functions.

- Allows to model the *monitoring context* and shows service and node *Outages* in compact matrix view.
- Allows to limit the number of information in the *Dashboard* by selecting rows, columns and cells.

You can select columns, rows, single cells and of course all entries in a *Surveillance View*. Please refer to the <u>Surveillance View Section</u> for details on how to configure *Surveillance Views*.

Surveillance view: default	Surveillance view: default			
default	PROD	TEST	DEV	
Routers	0 of 8	0 of 0	0 of 0	
Switches	0 of 1	0 of 0	0 of 0	
Servers	1 of 17	0 of 0	0 of 0	

Figure 5. The Surveillance View forms the basis for the Dashboard page.

Alarms

The *Alarms* component gives an overview about all unacknowledged *Alarms* with a severity higher than *Normal(1)*. Acknowledged *Alarms* will be removed from the responsibility of the *Operator*. The following information are shown in:

Alarms					
Node	Severity	UEI	Count	Last Time	Log Msg
▲ twc-rr-nc-2-la-ca	Minor	uei.opennms.org/nodes/interfaceDown	1	Apr 16, 2016 4:35:05 PM	Interface 24.43.181.105 is down.
▲ twc-rr-nc-2-la-ca	Minor	uei.opennms.org/nodes/interfaceDown	1	Apr 16, 2016 4:35:05 PM	Interface 24.93.73.62 is down.
A cartman.internal.opennms.com	Warning	uei.opennms.org/threshold/highThresholdExceeded	8	Apr 15, 2016 1:42:25 PM	High threshold exceeded for SNMP datasource ns-dskPercent on interface 172.20.110, parms: label="/home" ds="ns-dskPercent" description="Trigge ra nalert when the percentage of disk space used on any disk reaches or g oes above 90% full for two consecutive measurement intervals" value="94" instance="3" instance.label="/mome" resourceld="mode[9].dskIndex[home]" t hreshold="90.0" trigger="2" rearm="75.0"

Figure 6. Information displayed in the Alarms component

- 1. *Node*: Node label of the node the *Alarm* is associated
- 2. Severity: Severity of the Alarm
- 3. UEI: Shows the UEI of the Alarm
- 4. Count: Number of Alarms deduplicated by the reduction key of the Alarm
- 5. Last Time: Time for the last occurrence of the Alarm
- 6. *Log Msg*: The log message from the *Event* which is the source for this *Alarm*. It is specified in the event configuration file in <logmsg />

The *Alarms* component shows the most recent *Alarms* and allows the user to scroll through the last 100 *Alarms*.

Notifications

To inform people on a duty schedule notifications are used and force action to fix or reconfigure systems immediately. In *OpenNMS Meridian* it is possible to acknowledge notifications to see who is working on a specific issue. The *Dashboard* should show outstanding notifications in the *NOC* to provide an overview and give the possibility for intervention.

Notifications						
Node	Service	Message	Sent Time 🔻	Responder	Respond Time	
192.168.31.202	VMwareCim-Host System	The VMwareCim-HostSystem service poll on interface 192.168.31.202 (192. 168.31.202) on node 192.168.31.202 failed at Sunday, April 17, 2016 5:28: 00 PM CEST.	Apr 17, 2016 5:28:01 PM	auto-acknowledge d	Apr 17, 2016 5:28:33 PM	
gitlab.informatik.hs-fulda.de (193. 29.49)	SSH	The SSH service poll on interface 2001:638:301:11a1:250:56ff:feb3:92df (20 01:0638:0301:11a1:0250:56ff:feb3:92df) on node gitlab.informatik.hs-fulda. de (193.174.29.49) failed at Sunday, April 17, 2016 5:04:10 PM CEST.	Apr 17, 2016 5:04:12 PM	auto-acknowledge d	Apr 17, 2016 5:04:40 PM	
gitlab.informatik.hs-fulda.de (193. 29.49)	SSH	The SSH service poll on interface gitlab.informatik.hs-fulda.de (193.174.29.4 9) on node gitlab.informatik.hs-fulda.de (193.174.29.49) failed at Sunday, A pril 17, 2016 4:03:46 PM CEST.		auto-acknowledge d	Apr 17, 2016 4:04:16 PM	

Figure 7. Information displayed in the Notifications component

- 1. Node: Label of the monitored node the notification is associated with
- 2. Service: Name of the service the notification is associated with
- 3. Message: Message of the notification
- 4. Sent Time: Time when the notification was sent
- 5. *Responder*: User name who acknowledged the notification
- 6. *Response Time*: Time when the user acknowledged the notification

The *Notifications* component shows the most recent unacknowledged notifications and allows the user to scroll through the last 100 *Notifications*.

Node Status

An acknowledged *Alarm* doesn't mean necessarily the outage is solved. To give an overview information about ongoing *Outages* in the network, the *Dashboard* shows an outage list in the *Node Status* component.

Outages				
Node	Current Outages	24 Hour Availability		
barbrady.internal.opennms.com	0 of 11	100.000%		
biggayal.internal.opennms.com	0 of 3	100.000%		
butters.internal.opennms.com	0 of 5	100.000%		
cartman.internal.opennms.com	0 of 20	100.000%		
connect.opennms.com	0 of 7	100.000%		

Figure 8. Information displayed in the Node Status component

- 1. *Node*: Label of the monitored node with ongoing outages.
- 2. *Current Outages*: Number of services on the node with outages and total number of monitored services, e.g. with the natural meaning of "3 of 3 services are affected".
- 3. *24 Hour Availability*: Availability of all services provided by the node calculated by the last 24 hours.

Resource Graph Viewer

To give a quick entry point diagnose performance issues a *Resource Graph Viewer* allows to navigate to time series data reports which are filtered in the context of the *Surveillance View*.




Figure 9. Show time series based performance with the Resource Graph Viewer

It allows to navigate sequentially through resource graphs provided by nodes filtered by the *Surveillance View* context and selection and shows one graph report at a time.

4.2.2. Advanced configuration

The *Surveillance View* component allows to model multiple views for different monitoring contexts. It gives the possibility to create special view as example for network operators or server operators. The *Dashboard* shows only **one** configured *Surveillance View*. To give different users the possibility using their *Surveillance View* fitting there requirements it is possible to map a logged in user to a given *Surveillance View* used in the *Dashboard*.

The selected nodes from the *Surveillance View* are also aware of *User Restriction Filter*. If you have a group of users, which should see just a subset of nodes the *Surveillance View* will filter nodes which are not related to the assigned user group.

The *Dashboard* is designed to focus, and therefore also restrict, a user's view to devices of their interest. To do this, a new role was added that can be assigned to a user that restricts them to viewing only the *Dashboard* if that is intended.

Using the Dashboard role

The following example illustrates how this *Dashboard* role can be used. For instance the user drv4doe is assigned the dashboard role. So, when logging in as drv4doe, the user is taking directly to the *Dashboard* page and is presented with a custom *Dashboard* based on the drv4doe *Surveillance View* definition.

Step 1: Create an user

The following example assigns a Dashboard to the user "drv4doe" (a router and switch jockey) and restricts the user for navigation to any other link in the OpenNMS Meridian WebUI.

Home / Admin / Users and Groups / User List / New User				
Please enter a user ID and pas	sword below			
User ID:	drv4doe			
Password:	•••••			
Confirm Password:	•••••			
	OK Cancel			

Figure 10. Creating the user drv4doe using the OpenNMS Meridian WebUI

Step 2: Change Security Roles

Now, add the ROLE_PROVISION role to the user through the WebUI or by manually editing the users.xml file in the /opt/opennms/etc directory for the user drv4doe.

Modify User: drv4do	e			
User Passw	ord			
	Reset Password			
User Informa	ation			
Full Name:	Dashboard User			
Comments:				
Security Roles:	Available Roles		Currently in User	
	ROLE_ADMIN ROLE_ASSET_EDIT	OR	ROLE_DASHBOARD	
	ROLE_JMX ROLE_MOBILE			
	ROLE_PROVISION			
	ROLE_READONLY ROLE_REMOTING			
	ROLE_REST ROLE_RTC			
	ROLE_USER			
	» Add		« Remove	

Figure 11. Adding dashboard role to the user drv4doe using the OpenNMS Meridian WebUI

<user></user>
<user-id>drv4doe</user-id>
<full-name>Dashboard User</full-name>
<pre><password< pre=""></password<></pre>
salt="true">6F0ip6hgZsUwDhdzdPUVV5UhkSxdbZTlq8M5LXWG5586eDPa7BFizirjXEfV/srK
>
<role>ROLE_DASHBOARD</role>

Step 3: Define Surveillance View

Edit the **\$OPENNMS_HOME/etc/surveilliance-view.xml** file to add a definition for the user *drv4doe*, which you created in step 1.

```
<?xml version="1.0" encoding="UTF-8"?>
<surveillance-view-configuration
 xmlns:this="http://www.opennms.org/xsd/config/surveillance-views"
 xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance"
 xsi:schemaLocation="http://www.opennms.org/xsd/config/surveillance-views
http://www.opennms.org/xsd/config/surveillance-views.xsd"
 default-view="default" >
 <views >
    <view name="drv4doe" refresh-seconds="300" >
      <rows>
        <row-def label="Servers" >
          <category name="Servers"/>
        </row-def>
      </rows>
      <columns>
        <column-def label="PROD" >
          <category name="Production" />
        </column-def>
        <column-def label="TEST" >
          <category name="Test" />
        </column-def>
      </columns>
    </view>
   <!-- default view here -->
   <view name="default" refresh-seconds="300" >
      <rows>
        <row-def label="Routers" >
          <category name="Routers"/>
        </row-def>
        <row-def label="Switches" >
          <category name="Switches" />
        </row-def>
        <row-def label="Servers" >
          <category name="Servers" />
        </row-def>
      </rows>
      <columns>
        <column-def label="PROD" >
          <category name="Production" />
        </column-def>
        <column-def label="TEST" >
          <category name="Test" />
        </column-def>
        <column-def label="DEV" >
          <category name="Development" />
        </column-def>
      </columns>
    </view>
 </views>
</surveillance-view-configuration>
```

This configuration and proper assignment of node categories will produce a default *Dashboard* for all users, other than drv4doe.



You can hide the upper navigation on any page by specifying **?quiet=true;** adding it to the end of the *OpenNMS Meridian* URL. This is very handy when using the dashboard on a large monitor or tv screen for office wide viewing.

However, when logging in as drv4doe, the user is taking directly to the *Dashboard* page and is presented with a *Dashboard* based on the custom *Surveillance View* definition.



The drv4doe user is not allowed to navigate to URLs other than the dashboard.jsp URL. Doing so will result in an *Access Denied* error.

Anonymous dashboards

You can modify the configuration files for the security framework to give you access to one or more dashboards without logging in. At the end you'll be able to point a browser at a special URL like <code>http://…​/opennms/dashboard1" class="bare">http://…​/opennms/dashboard1" class="bare">http://…​/opennms/dashboard1" class="bare">http://…​/opennms/dashboard2" class="bare">http://…​/opennms/dashboard2" class="bare">http://…​/opennms/dashboard2" class="bare">http://…​/opennms/dashboard2" class="bare">http://…​/opennms/dashboard2" class="bare">http://…​/opennms/dashboard2" class="bare">http://…​/opennms/dashboard2" class="bare">http://…​/opennms/dashboard2" class="bare">http://…​/opennms/dashboard2</br/>/ode> and see a dashboard without any authentication. First, configure surveillance views and create dashboard users as above. For example, make two dashboards and two users called <code>dashboard1</br/>/code> and <code>dashboard2</br/>/code>. Test that you can log in as each of the new users and see the correct dashboard. Now create some aliases you can use to distinguish between dashboards. In <code>/opt/opennms/jetty-webapps/opennms/WEB-INF</code>, edit <code>web.xml</code>. Just before the first <code><servlet-mapping></code> tag, add the following servlet entries:

Just before the first <error-page> tag, add the following servlet-mapping entries:

```
<servlet-mapping>
    <servlet-name>dashboard1</servlet-name>
        <url-pattern>/dashboard1</url-pattern>
    </servlet-mapping>
        <servlet-name>dashboard2</servlet-name>
        <url-pattern>/dashboard2</url-pattern>
        </servlet-mapping>
</servlet-mapping>
```

After the last <filter-mapping> tag, add the following filter-mapping entries:

```
<filter-mapping>
<filter-name>AddRefreshHeader-120</filter-name>
<url-pattern>/dashboard.jsp</url-pattern>
</filter-mapping>
<filter-name>AddRefreshHeader-120</filter-name>
<url-pattern>/dashboard1</url-pattern>
</filter-mapping>
<filter-name>AddRefreshHeader-120</filter-name>
<url-pattern>/dashboard2</url-pattern>
</filter-mapping>
```

Next edit applicationContext-acegi-security.xml to enable anonymous authentication for the /dashboard1 and /dashboard2 aliases. Near the top of the file, find <bean id="filterChainProxy" ...>. Below the entry for /rss.jsp*, add an entry for each of the dashboard aliases:

```
<bean id="filterChainProxy" class="org.acegisecurity.util.FilterChainProxy">
    <property name="filterInvocationDefinitionSource"></pro>
      <value>
        CONVERT_URL_TO_LOWERCASE_BEFORE_COMPARISON
        PATTERN_TYPE_APACHE_ANT
/rss.jsp*=httpSessionContextIntegrationFilter,logoutFilter,authenticationProcessingFil
ter, basicProcessingFilter, securityContextHolderAwareRequestFilter, anonymousProcessingF
ilter, basicExceptionTranslationFilter, filterInvocationInterceptor
/dashboard1*=httpSessionContextIntegrationFilter,logoutFilter,securityContextHolderAwa
reRequestFilter, dash1AnonymousProcessingFilter, filterInvocationInterceptor
/dashboard2*=httpSessionContextIntegrationFilter,logoutFilter,securityContextHolderAwa
reRequestFilter, dash2AnonymousProcessingFilter, filterInvocationInterceptor
/**=httpSessionContextIntegrationFilter,logoutFilter,authenticationProcessingFilter,ba
sicProcessingFilter, securityContextHolderAwareRequestFilter, anonymousProcessingFilter,
exceptionTranslationFilter, filterInvocationInterceptor
. . .
```

About halfway through the file, look for <bean id="filterInvocationInterceptor" ...>. Below the entry for /dashboard.jsp, add an entry for each of the aliases:

```
<bean id="filterInvocationInterceptor" class=
"org.acegisecurity.intercept.web.FilterSecurityInterceptor">
...
/frontpage.htm=ROLE_USER,ROLE_DASHBOARD
/dashboard.jsp=ROLE_USER,ROLE_DASHBOARD
/dashboard1=ROLE_USER,ROLE_DASHBOARD
/dashboard2=ROLE_USER,ROLE_DASHBOARD
/gwt.js=ROLE_USER,ROLE_DASHBOARD
```

Finally, near the bottom of the page, add a new instance of AnonymousProcessingFilter for each alias.

Restart OpenNMS Meridian and you should bring up a dashboard at <code>http://…​/opennms/dashboard1" class="bare">http://…​/opennms/dashboard1" class="bare">http://…​/opennms/dashboard1" class="bare">http://…​/opennms/dashboard1" class="bare">http://…​/opennms/dashboard1" class="bare">http://…​/opennms/dashboard1" class="bare">http://…​/opennms/dashboard1" class="bare">http://…​/opennms/dashboard1" class="bare">http://…​/opennms/dashboard1" class="bare">http://…​/opennms/dashboard1



There's no way to switch dashboards without closing the browser (or deleting the JSESSIONID session cookie).



If you accidentally click a link that requires full user privileges (e.g. Node List), you'll be given a login form. Once you get to the login form, there's no going back to the dashboard without restarting the browser. If this problem bothers you, you can set ROLE_USER in addition to ROLE_DASHBOARD in your userAttribute property. However this will give full user access to anonymous browsers.

4.3. Grafana Dashboard Box

Grafana provides an API key which gives access for 3rd party application like *OpenNMS Meridian*. The *Grafana Dashboard Box* on the start page shows dashboards related to *OpenNMS Meridian*. To filter relevant dashboards, you can use a *tag* for dashboards and make them accessible. If no *tag* is provided all dashboards from *Grafana* will be shown.

The feature is by default deactivated and is configured through opennms.properties. Please note that this feature works with the *Grafana API v2.5.0*.

Quick access to Grafana dashboards from the OpenNMS Meridian start page

			Searc	h Info 🗸 Status 🗸	Reports - Dashboards - Maps - 1 c
ne					
des with Pending Problems	Availability Over the Past 24 Hours				Notifications
ncdaniels.internal.opennms.com has 1 alarm	Categories	Outages	Avai	ability	You have 1 outstanding notice
15 hours)	Network Interfaces	0 0	f 125	100.000%	 There are 1 outstanding notice On-Call Schedule
nephesto.internal.opennms.com has 1 alarm 18 hours)	Web Servers	0	of 51	100.000%	
wc-rr-nc-2-la-ca has 2 alarms (18 hours)	Email Servers	0	of 14	99.995%	Resource Graphs
stanford.internal.opennms.com has 1 alarm	DNS and DHCP Servers) of 9	100.000%	Search
23 hours)	Database Servers) of 0	100.000%	
uglybob.internal.opennms.com has 1 alarm	JMX Servers) of 0	100.000%	KSC Reports
2 days)	Software Update	3	of 22	86.609%	No KSC reports defined
atigate has 2 alarms (2 days)	Other Servers	0	of 71	100.000%	Search
cartman.internal.opennms.com has 1 alarm [2 days]	Total	Outages	Avai	ability	
timmy.internal.opennms.com has 1 alarm (2 days)	Overall Service Availability	6 0	f 339	98.612%	Grafana Dashboards
					JI CPU/Load
odes with Outages					JI OpenNMS
ephesto.internal.opennms.com (18 hours)					J Overview
c-rr-nc-2-la-ca (18 hours) anford.internal.opennms.com (23 hours)					all Perioriance Dashboard
lybob.internal.opennms.com (2 days)					a
cdaniels.internal.opennms.com (4 days)					al

Table 2. Grafana Dashboard configuration properties

Name	Туре	Description	Defau lt
org.opennms.grafanaBox.s how	Boole an	This setting controls whether a grafana box showing the available dashboards is placed on the landing page. The two valid options for this are true or false.	false
org.opennms.grafanaBox.h ostname	Strin g	If the box is enabled you also need to specify hostname of the <i>Grafana</i> server	localh ost
org.opennms.grafanaBox.p ort	Integ er	The port of the <i>Grafana</i> server ReST API	3000
org.opennms.grafanaBox.b asePath	Strin g	The <i>Grafana</i> base path to be used	
org.opennms.grafanaBox.a piKey	Strin g	The API key is needed for the ReST calls to work	
org.opennms.grafanaBox.t ag	Strin g	When a <i>tag</i> is specified only dashboards with this given <i>tag</i> will be displayed. When no <i>tag</i> is given all dashboards will be displayed	
org.opennms.grafanaBox.p rotocol	Strin g	The protocol for the ReST call can also be specified	http
org.opennms.grafanaBox.c onnectionTimeout	Integ er	Timeout in milliseconds for getting information from the <i>Grafana</i> server	500
org.opennms.grafanaBox.s oTimeout	Integ er	Socket timeout	500
org.opennms.grafanaBox.d ashboardLimit	Integ er	Maximum number of entries to be displayed (0 for unlimited)	0

If you have *Grafana* behind a proxy it is important the org.opennms.grafanaBox.hostname is reachable. This host name is used to generate links to the *Grafana* dashboards.

The process to generate an *Grafana API Key* can be found in the HTTP API documentation. Copy the API Key to opennms.properties as org.opennms.grafanaBox.apiKey.

4.4. Operator Board

In a network operation center *(NOC)* the *Ops Board* can be used to visualize monitoring information. The monitoring information for various use-cases are arranged in configurable *Dashlets*. To address different user groups it is possible to create multiple *Ops Boards*.

There are two visualisation components to display *Dashlets*:

- Ops Panel: Shows multiple Dashlets on one screen, e.g. on a NOC operators workstation
- Ops Board: Shows one Dashlet at a time in rotation, e.g. for a screen wall in a NOC




Figure 12. Concept of Dashlets displayed in Ops Panel




Figure 13. Concept to show Dashlets in rotation on the Ops Board

4.4.1. Configuration

To create and configure *Ops Boards* administration permissions are required. The configuration section is in admin area of OpenNMS Meridian and named *Ops Board Config Web Ui*.

	Search into V Status V Reports V Dashboards V Maps V Indigo V
Home / Admin	
OpenNMS System	Descriptions
System Configuration	Detailed Documentation on all options can be found on the OpenNMS wiki.
Configure Users, Groups and On-Call Roles Prov/sioning	Configure Users, Groups and On-Call Roles: Add, modify or delete existing users. Groups contain users. Roles are built from groups and provide a mechanism to implement calendar-based on-call staff rotations. (User: A person, Group: Administrators, Role: On Duty Staff)
Manage Provisioning Requisitions Import and Export Asset Information	Manage Provisioning Requisitions: Add nodes, interfaces and services to OpenNMS based partly or completely on the contents of a Requisition rather than strictly by having OpenNMS discover the network.
Manage Surveillance Categories Configure Discovery Configure SIMP Community Names by IP Address	Import and Export Asset Information: Export and import data into OpenNMS's asset inventory. The comma- delimited file format is supported by most spreadsheet and database applications.
Manually Add an Interface Delete Nodes	Manage Surveillance Categories: Manage surveillance categories (also known as node categories) and edit the list of nodes belonging to each category.
Event Management	Configure Discovery: Set up the IP addresses (individual addresses and/or ranges) that you want OpenNMS to scan periodically in order to detect new nodes.
Manually Send an Event Configure Notifications Customize Event Configurations	Manually Add an Interface: Trigger a scan of an IPv4 or IPv6 interface. If the IP address of the interface is contained in the IP address tables of an existing node, the interface will be added into the node. Otherwise, a new node will be created.
Notification Status: O On Off Update	Delete Nodes: Permanently delete nodes from the database.
	Manually Send an Event: Allows you to build a specific event and send it to the system.
Service Monitoring Configure Scheduled Outages Manage and Unmanage Interfaces and Services	Configure Notifications: Create and manage notification escalation plans, called destination paths. A destination path is associated to an OpenINMS event. Each path can have any arbitrary number of escalations or targets (users, groups, on-call roles) and can send notices through email, pagers, et cetera. Each destination path can be triggered by any number of OpenINMS events and may further be associated with specific interfaces or services.
	Customize Event Configurations: Add and edit configuration files for events definitions.
Performance Measurement Configure SNMP Collections and Data Collection Groups Configure SNMP Data Collection per Interface	Notification Status: Notifications will be sent out only if this setting is switched to On. This is a system-wide setting. As long as this is Off, OpenNMS will not create notifications. The current status of notifications is reflected by the bell icon in the upper right-hand corner of every OpenNMS screen.
Configure Thresholds	Configure Scheduled Outages: Add and edit scheduled outages. You can pause notifications, polling, thresholding and data collection (or any combination of the four) for any interface/node for any time.
Distributed Monitoring Manage Monitoring Locations Manage Applications	Configure SNMP Community Names by IP Address: Configure the Community String used in SNMP Data Collection and other SNMP operations. OpenNMS is shipped with a community string of "public". If you have set a different <i>read</i> community on your devices you must put it here to be able to collect data from these devices.
Manage Remote Pollers Manage Minions Additional Tools Instrumentation Log Reader	Manage and Unmanage Interfaces and Services: Managing an interface or service means that OpenNMS performs tests on this interface or service. If you want to explicitly enable or disable testing you can set that up here. A typical case is if a web server is listening on both an internal and an external interface. If you manage the service on both interfaces, you will get two notifications if it fails. If you want only one, unmanage the service on one of the interfaces.
SNMP MIB Compiler Ops Board Configuration	Manage SNMP Collections and Data Collection Groups: Manage SNMP Collections and the content of the files for data collection groups.
Surveillance Views Configuration JMX Configuration Generator	Configure SNMP Data Collection per Interface: This interface will allow you to configure which IP and non-IP interfaces are used in SNMP Data Collection.

Figure 14. Navigation to the Ops Board configuration

HORIZON

Create or modify Ops Boards is described in the following screenshot.

HORIZON					Ap	r 17, 2016 16	:16 CEST 🖲
	Search	Info 👻	Status 🗸	Reports -	Dashboards -	Maps 👻	💄 indigo 👻
Home / Admin / Ops Board Configuration							
Overview NOC-Mailsystem × +							
Ops Board configuration							Help
Title NOC-Mailsystem 2 Add dashi Previex 4							
Alarm Details Charts Charts Boost-Priority 0 8 Title Image Duration 15 7 Boost-Duration 0 9 RD RTC Surveillance Topology URL Image 10 10 10	Prop Rem	erties 10		(12)	Preview 13		

Figure 15. Adding a Dashlet to an existing Ops Board

- 1. Create a new Ops Board to organize and arrange different Dashlets
- 2. The name to identify the Ops Board
- 3. Add a Dashlet to show OpenNMS Meridian monitoring information

- 4. Show a preview of the whole Ops Board
- 5. List of available *Dashlets*
- 6. *Priority* for this *Dashlet* in *Ops Board* rotation, lower priority means it will be displayed more often
- 7. Duration in seconds for this Dashlet in the Ops Board rotation
- 8. Change *Priority* if the *Dashlet* is in alert state, this is optional and maybe not available in all *Dashlets*
- 9. Change *Duration* if the *Dashlet* is in alert state, it is optional and maybe not available in all *Dashlets*
- 10. Configuration properties for this Dashlet
- 11. Remove this Dashlet from the Ops Board
- 12. Order Dashlets for the rotation on the Ops Board and the tile view in the Ops Panel
- 13. Show a preview for the whole Ops Board

The configured *Ops Board* can be used by navigating in the main menu to *Dashboard* \rightarrow *Ops Board*.

open NMS			Search	Info - Status -	Reports - Dashboards -	
10					Dashboar Ops Boar	
des with Pending Problems	Availability Over the Past 24 Hours				Notifications	
ncdaniels.internal.opennms.com has 1 alarm	Categories	Outages	Availabi	ility	You have no outstandi	
15 hours)	Network Interfaces	0	of 125	100.000%	There are no outstand On-Call Schedule	ing notices
nephesto.internal.opennms.com has 1 alarm 18 hours)	Web Servers		0 of 51	100.000%		
wc-rr-nc-2-la-ca has 2 alarms (18 hours)	Email Servers		0 of 14	99.995%	Resource Graphs	
tanford.internal.opennms.com has 1 alarm	DNS and DHCP Servers		0 of 9	100.000%		Search
22 hours)	Database Servers		0 of 0	100.000%		
glybob.internal.opennms.com has 1 alarm	JMX Servers		0 of 0	100.000%	KSC Reports	
2 days)	Software Update		3 of 22	86.710%		Search
tigate has 2 alarms (2 days)	Other Servers		0 of 71	100.000%		
artman.internal.opennms.com has 1 alarm 2 days)	Total	Outages	Availabi	ility	Quick Search	
immy.internal.opennms.com has 1 alarm (2 days)	Overall Service Availability	6	of 339	98.626%	Node ID:	
, , . ,						Search
des with Outages					Node label like:	
phesto.internal.opennms.com (18 hours)					Node label like.	Quarth
-rr-nc-2-la-ca (18 hours) nford.internal.opennms.com (22 hours)						Search
ybob.internal.opennms.com (2 days) daniels.internal.opennms.com (4 days)					TCP/IP Address like:	
daniela.internal.opennina.com (4 days)					****	Search

Figure 16. Navigation to use the Ops Board

4.4.2. Dashlets

Visualization of information is implemented in *Dashlets*. The different *Dashlets* are described in this section with all available configuration parameter.

To allow filter information the *Dashlet* can be configured with a generic Criteria Builder.

Alarm Details

This Alarm-Details Dashlet shows a table with alarms and some detailed information.

Table 3. Information of the alarms

Field	Description
Alarm ID	OpenNMS Meridian ID for the alarm
Severity	Alarm severity (Cleared, Indeterminate, Normal, Warning, Minor, Major, Critical)
Node label	Node label of the node where the alarm occurred
Alarm count	Alarm count based on reduction key for deduplication
Last Event Time	Last time the alarm occurred
Log Message	Reason and detailed log message of the alarm

The *Alarm Details Dashlet* can be configured with the following parameters.

Boost support	Boosted Severity
Configuration	Criteria Builder

Alarms

This *Alarms Dashlet* shows a table with a short alarm description.

Table 4. Information of the alarm

Field	Description
Time	Absolute time since the alarm appeared
Node label	Node label of the node where the alarm occurred
UEI	OpenNMS Meridian Unique Event Identifier for this alarm

The *Alarms Dashlet* can be configured with the following parameters.

Boost support	Boosted Severity
Configuration	Criteria Builder

Charts

This *Dashlet* displays an existing Chart.

Boost support	false
Chart	Name of the existing chart to display
Maximize Width	Rescale the image to fill display width
Maximize Height	Rescale the image to fill display height

Grafana

This *Dashlet* shows a *Grafana Dashboard* for a given time range. The Grafana Dashboard Box configuration defined in the opennes.properties file is used to access the *Grafana* instance.

Boost support	false
title	Title of the Grafana dashboard to be displayed
uri	URI to the Grafana Dashboard to be displayed
from	Start of time range
to	End of time range

Image

This *Dashlet* displays an image by a given URL.

Boost support	false
imageUrl	URL with the location of the image to show in this Dashlet
maximizeHeight	Rescale the image to fill display width
maximizeWidth	Rescale the image to fill display height

KSC

This *Dashlet* shows an existing KSC report. The view is exact the same as the *KSC report* is build regarding order, columns and time spans.

Boost support	false
KSC-Report	Name of the KSC report to show in this Dashlet

Мар

This *Dashlet* displays the geographical map.

Boost support	false
search	Predefined search for a subset of nodes shown in the geographical map in this <i>Dashlet</i>

RRD

This *Dashlet* shows one or multiple RRD graphs. It is possible to arrange and order the RRD graphs in multiple columns and rows. All RRD graphs are normalized with a given width and height.

Boost support	false
---------------	-------

Columns	Number of columns within the Dashlet
Rows	Number of rows with the Dashlet
KSC Report	Import RRD graphs from an existing KSC report and re-arrange them.
Graph Width	Generic width for all RRD graphs in this Dashlet
Graph Height	Generic height for all RRD graphs in this Dashlet
Timeframe value	Number of the given Timeframe type
Timeframe type	Minute, Hour, Day, Week, Month and Year for all RRD graphs

RTC

This *Dashlet* shows the configured SLA categories from the OpenNMS Meridian start page.

Boost support	false	
-	-	

Summary

This *Dashlet* shows a trend of incoming alarms in given time frame.

Boost support	Boosted Severity
timeslot	Time slot in seconds to evaluate the trend for alarms by severity and UEI.

Surveillance

This *Dashlet* shows a given Surveillance View.

Boost suppo	rt false
viewName	Name of the configured Surveillance View

Topology

This *Dashlet* shows a Topology Map. The *Topology Map* can be configured with the following parameter.

Boost support	false
focusNodes	Which node(s) is in focus for the topology
provider	Which topology should be displayed, e.g. Linkd, VMware
szl	Set the zoom level for the topology

URL

This *Dashlet* shows the content of a web page or other web application, e.g. other monitoring systems by a given URL.

Boost support	false
password	Optional password if a basic authentication is required
url	URL to the web application or web page
username	Optional username if a basic authentication is required

4.4.3. Boosting Dashlet

The behavior to boost a *Dashlet* describes the behavior of a *Dashlet* showing critical monitoring information. It can raise the priority in the *Ops Board* rotation to indicate a problem. This behavior can be configured with the configuration parameter *Boost Priority* and *Boost Duration*. These to configuration parameter effect the behavior on the *Ops Board* in rotation.

- *Boost Priority*: Absolute priority of the *Dashlet* with critical monitoring information.
- *Boost Duration*: Absolute duration in seconds of the *Dashlet* with critical monitoring information.

4.4.4. Criteria Builder

The *Criteria Builder* is a generic component to filter information of a *Dashlet*. Some *Dashlets* use this component to filter the shown information on a *Dashlet* for certain use case. It is possible to combine multiple *Criteria* to display just a subset of information in a given *Dashlet*.

Restrict ion	Property	Value 1	Value 2	Description
Asc	-	-	-	ascending order
Desc	-	-	-	descending order
Between	database attribute	String	String	Subset of data between value 1 and value 2
Contains	database attribute	String	-	Select all data which contains a given text string in a given database attribute
Distinct	database attribute	-	-	Select a single instance
Eq	database attribute	String	-	Select data where attribute equals (==) a given text string

Table 5. Generic Criteria Builder configuration possibilities

Restrict ion	Property	Value 1	Value 2	Description	
Ge	database attribute	String	-	Select data where attribute is greater equals than (>=) a given text value	
Gt	database attribute	String	-	Select data where attribute is greater than (>) a given text value	
Ilike	database attribute	String	-	unknown	
In	database attribute	String	-	unknown	
Iplike	database attribute	String	-	Select data where attribute matches an given IPLIKE expression	
IsNull	database attribute	-	-	Select data where attribute is null	
IsNotNul l	database attribute	-	-	Select data where attribute is not null	
IsNotNul l	database attribute	-	-	Select data where attribute is not null	
Le	database attribute	String	-	Select data where attribute is less equals than (⇐) a given text value	
Lt	database attribute	String	-	Select data where attribute is less than (<) a given text value	
Le	database attribute	String	-	Select data where attribute is less equals than (⇐) a given text value	
Like	database attribute	String	-	Select data where attribute is like a given text value similar to SQL like	
Limit	-	Intege r	-	Limit the result set by a given number	
Ne	database attribute	String	-	Select data where attribute is not equals (!=) a given text value	
Not	database attribute	String	-	<i>unknown</i> difference between Ne	
OrderBy	database attribute	-	-	Order the result set by a given attribute	

 \mathbf{O}

For date values, absolute value can be specified in ISO format, e.g. 2019-06-20T20:45:15.123-05:00. Relative times can be specified by +seconds and -seconds.

4.5. JMX Configuration Generator

OpenNMS Meridian implements the *JMX* protocol to collect long term performance data for *Java* applications. There are a huge variety of metrics available and administrators have to select which information should be collected. The *JMX Configuration Generator Tools* is build to help generating valid complex *JMX* data collection configuration and *RRD graph* definitions for *OpenNMS Meridian*.

This tool is available as CLI and a web based version.

4.5.1. Web based utility

Complex *JMX* data collection configurations can be generated from a web based tool. It collects all available *MBean Attributes* or *Composite Data Attributes* from a *JMX* enabled Java application.

The workflow of the tool is:

- 1. Connect with JMX or JMXMP against a MBean Server provided of a Java application
- 2. Retrieve all *MBean* and *Composite Data* from the application
- 3. Select specific *MBeans* and *Composite Data* objects which should be collected by *OpenNMS Meridian*
- 4. Generate *JMX Collectd* configuration file and *RRD graph* definitions for *OpenNMS Meridian* as downloadable archive

The following connection settings are supported:

- Ability to connect to MBean Server with RMI based JMX
- Authentication credentials for JMX connection
- Optional: JMXMP connection

The web based configuration tool can be used in the *OpenNMS Meridian Web Application* in administration section *Admin* \rightarrow *JMX Configuration Generator*.

Configure JMX Connection

At the beginning the connection to an *MBean Server* of a *Java* application has to be configured.

?	1.	Service	Configuration /	2.	MBeans	Configuration /	3.	OpenNMS	Configuration
---	----	---------	-----------------	----	--------	-----------------	----	---------	---------------

Service name*	OpenNMS-JVM
Host*	localhost
Port*	18980
	Authentication
	🕑 Skip JVM MBeans
	Skip non-number values

>

Figure 17. JMX connection configuration window

- Service name: The name of the service to bind the JMX data collection for Collectd
- *Host*: IP address or *FQDN* connecting to the *MBean Server* to load *MBeans* and *Composite Data* into the generation tool
- Port: Port to connect to the MBean Server
- *Authentication*: Enable / Disable authentication for *JMX* connection with username and password
- Skip non-number values: Skip attributes with non-number values
- JMXMP: Enable / Disable JMX Messaging Protocol instead of using JMX over RMI

By clicking the arrow (>) the *MBeans* and *Composite Data* will be retrieved with the given connection settings. The data is loaded into the *MBeans Configuration* screen which allows to select metrics for the data collection configuration.

Select MBeans and Composite

The *MBeans Configuration* section is used to assign the *MBean* and *Composite Data attributes* to *RRD domain* specific data types and data source names.

DefaultDomain									
HttpAdaptor	MBean details								
HttpAdaptorMgmt		- extended							
OpenNMS		✓ selected							
Collectd	Name*	OpenNMS.JettyServer							
Eventd									
JettyServer	Objectname	OpenNMS:Name=JettyServer							
Manager									
Provisiond	MBean Attrib	utes							
Rtcd	SELECTED	NAME	ALIAS		TYPE				
TestLoadLibraries		HttpsConnectionsOpen	0HttpsConnectioOpen	*	gauge -				
com.mchange.v2.c3p0		HttpConnectionsTotal	OHttpConnectioTotal	*					
C3P0Registry		HupConnections total	OntipConnectio Iotal		gauge 🔹				
PooledDataSource[1bqrgl99a1x3yndg1j0gbuv 4dd328e]		HttpsConnectionsTotal	OHttpsConnectiTotal	*	gauge -				
🗆 java.lang	-	HttpsConnectionsOpenI	OHttpsConnecOpenMax	*					
ClassLoading		HupsconnectionsOpeni	OHupsConnecOpenmax		gauge -				
Compilation		HttpConnectionsOpen	OHttpConnectionOpen	*	gauge -				
 ✓ GarbageCollector ✓ Ø PS MarkSweep 	-	HttpConnectionsOpenN	OHttpConnectOpenMax	*					
v S PS Markoweep ⊮ LastGcinfo		httpconnectionsopeniv	онцрооннесторениках		gauge -				
▼		Status	2Status	*	gauge -				
v to ro scavenge ⊮ LastGcinfo									
▼ □ Memory									
HeapMemoryUsage									
NonHeapMemoryUsage									
MemoryPool									
▼ □ Code Cache									

Figure 18. Select MBeans or Composite Data for OpenNMS Meridian data collection

The left sidebar shows the tree with the *JMX Domain*, *MBeans* and *Composite Data* hierarchy retrieved from the *MBean Server*. To select or deselect all attributes use *Mouse right click* \rightarrow *select/deselect*.

The right panel shows the *MBean Attributes* with the *RRD* specific mapping and allows to select or deselect specific *MBean Attributes* or *Composite Data Attributes* for the data collection configuration.

MBean details							
	selected						
Name*	java.lang.MemoryPool						
Objectname	java.lang:type=MemoryPoo	ol,name=Code Cache					
MBean Attrib	utes						
SELECTED	NAME	ALIAS			TYPE		
	UsageThresho	IdCount 3UsageTh	resholdCnt	•	gauge -		
	CollectionUsageThresh 3Co		geThresCnt	*	gauge -		

Figure 19. Configure MBean attributes for data collection configuration

omposite details			
selected			
lias* PeakUsage			
ame PeakUsage			
omposite Members			
SELECTED	NAME		
	INAME	ALIAS	TYPE
<	committed	ALIAS 3PeakUsageCommit	TYPE gauge
0 0			
-	committed	3PeakUsageCommit *	gauge
-	committed init	3PeakUsageCommit • 3PeakUsageInit •	gauge

Figure 20. Configure Composite attributes for data collection configuration

- MBean Name or Composite Alias: Identifies the MBean or the Composite Data object
- *Selected*: Enable/Disable the *MBean attribute* or *Composite Member* to be included in the data collection configuration
- Name: Name of the MBean attribute or Composite Member
- Alias: the data source name for persisting measurements in RRD or JRobin file
- Type: Gauge or Counter data type for persisting measurements in RRD or JRobin file

The *MBean Name, Composite Alias* and *Name* are validated against special characters. For the *Alias* inputs are validated to be not longer then 19 characters and have to be unique in the data collection configuration.

Download and include configuration

The last step is generating the following configuration files for *OpenNMS Meridian*:

- *collectd-configuration.xml*: Generated sample configuration assigned to a service with a matching data collection group
- *jmx-datacollection-config.xml*: Generated *JMX* data collection configuration with the selected *MBeans* and *Composite Data*
- *snmp-graph.properties*: Generated default *RRD* graph definition files for all selected metrics

The content of the configuration files can be copy & pasted or can be downloaded as *ZIP archive*.



If the content of the configuration file exceeds 2,500 lines, the files can only be downloaded as *ZIP archive*.

4.5.2. CLI based utility

The command line *(CLI)* based tool is not installed by default. It is available as an *RPM* package in the official repositories.

Installation

RHEL based installation with Yum

yum install opennms-jmx-config-generator

Installation from source

It is required to have the *Java 8 Development Kit* with *Apache Maven* installed. The mvn binary has to be in the path environment. After cloning the repository you have to enter the source folder and compile an executable *JAR*.

```
cd opennms/features/jmx-config-generator
mvn package
```

Inside the newly created target folder a file named jmxconfiggenerator-<VERSION>-onejar.jar is present. This file can be invoked by:

java -jar target/jmxconfiggenerator-2020.1.22-onejar.jar

Usage

After installing the the *JMX Config Generator* the tool's wrapper script is located in the **\${OPENNMS_HOME}/bin** directory.

- \$ cd /path/to/opennms/bin
- \$./jmx-config-generator



When invoked without parameters the usage and help information is printed.

The *JMX Config Generator* uses sub-commands for the different configuration generation tasks. Each of these sub-commands provide different options and parameters. The command line tool accepts the following sub-commands.

Sub- command	Description
query	Queries a MBean Server for certain MBeans and attributes.
generate- conf	Generates a valid jmx-datacollection-config.xml file.
generate- graph	Generates a <i>RRD</i> graph definition file with matching graph definitions for a given jmx-datacollection-config.xml.

The following global options are available in each of the sub-commands of the tool:

Option/Argume nt	Description	Defaul t
-h (help)	Show help and usage information.	false
-v (verbose)	Enables verbose mode for debugging purposes.	false

Sub-command: query

This sub-command is used to query a *MBean Server* for it's available *MBean* objects. The following example queries the server myserver with the credentials myusername/mypassword on port 7199 for *MBean objects* in the java.lang domain.

```
./jmx-config-generator query --host myserver --username myusername --password
mypassword --port 7199 "java.lang:*"
java.lang:type=ClassLoading
    description: Information on the management interface of the MBean
    class name: sun.management.ClassLoadingImpl
    attributes: (5/5)
        TotalLoadedClassCount
            id: java.lang:type=ClassLoading:TotalLoadedClassCount
            description: TotalLoadedClassCount
            type: long
            isReadable: true
            isWritable: false
            isIs: false
        LoadedClassCount
            id: java.lang:type=ClassLoading:LoadedClassCount
            description: LoadedClassCount
            type: int
            isReadable: true
            isWritable: false
            isIs: false
<output omitted>
```

The following command line options are available for the *query* sub-command.

Option/Argument	Description	Defa ult
<filter criteria=""></filter>	A filter criteria to query the <i>MBean Server</i> for. The format is <objectname>[:attribute name]. The <objectname> accepts the default <i>JMX</i> object name pattern to identify the <i>MBeans</i> to be retrieved. If null all domains are shown. If no key properties are specified, the domain's <i>MBeans</i> are retrieved. To execute for certain attributes, you have to add :<attribute name="">. The <attribute name=""> accepts regular expressions. When multiple <filter criteria=""> are provided they are OR concatenated.</filter></attribute></attribute></objectname></objectname>	-
host <host></host>	Hostname or IP address of the remote <i>JMX</i> host.	-
ids-only	Only show the ids of the attributes.	false
ignore <filter criteria></filter 	Set <filter criteria=""> to ignore while running.</filter>	-
include-values	Include attribute values.	false
jmxmp	Use JMXMP and not JMX over RMI.	false
password <password></password>	Password for <i>JMX</i> authentication.	-
port <port></port>	Port of <i>JMX</i> service.	-

Option/Argument	Description	Defa ult
show-domains	Only lists the available domains.	true
show-empty	Includes <i>MBeans</i> , even if they do not have attributes. Either due to the <filter criteria=""> or while there are none.</filter>	false
url <url></url>	Custom connection URL <hostname>:<port> service:jmx:<protocol>:<sap> service:jmx:remoting-jmx://<hostname>:<port></port></hostname></sap></protocol></port></hostname>	-
username <username></username>	Username for <i>JMX</i> authentication.	-
-h (help)	Show help and usage information.	false
-v (verbose)	Enables verbose mode for debugging purposes.	false

Sub-command: generate-conf

This sub-command can be used to generate a valid jmx-datacollection-config.xml for a given set of *MBean objects* queried from a *MBean Server*.

The following example generate a configuration file myconfig.xml for *MBean* objects in the java.lang domain of the server myserver on port 7199 with the credentials myusername/mypassword. You have to define either an *URL* or a hostname and port to connect to a *JMX* server.

jmx-config-generator generate-conf --host myserver --username myusername --password mypassword --port 7199 "java.lang:*" --output myconfig.xml Dictionary entries loaded: '18'

The following options are available for the *generate-conf* sub-command.

Option/Argume nt	Description	Default
<attribute id=""></attribute>	A list of attribute Ids to be included for the generation of the configuration file.	-
dictionary <file></file>	Path to a dictionary file for replacing attribute names and part of <i>MBean</i> attributes. The file should have for each line a replacement, e.g. Auxillary:Auxil.	-
host <host></host>	Hostname or IP address of <i>JMX</i> host.	-
jmxmp	Use JMXMP and not JMX over RMI.	false
output <file></file>	Output filename to write generated jmx-datacollection-config.xml.	-

Option/Argume nt	Description	Default
password <password></password>	Password for <i>JMX</i> authentication.	-
port <port></port>	Port of <i>JMX</i> service	-
print -dictionary	Prints the used dictionary to STDOUT. May be used withdictionary	false
service <value></value>	The <i>Service Name</i> used as <i>JMX</i> data collection name.	anyserv ice
skipDefaultVM	Skip default JavaVM Beans.	false
skipNonNumber	Skip attributes with non-number values	false
url <url></url>	Custom connection URL <hostname>:<port> service:jmx:<protocol>:<sap> service:jmx:remoting-jmx://<hostname>:<port></port></hostname></sap></protocol></port></hostname>	-
username <username></username>	Username for <i>JMX</i> authentication	-
-h (help)	Show help and usage information.	false
-v (verbose)	Enables verbose mode for debugging purposes.	false

Q

The option --skipDefaultVM offers the ability to ignore the *MBeans* provided as standard by the *JVM* and just create configurations for the *MBeans* provided by the *Java Application* itself. This is particularly useful if an optimized configuration for the JVM already exists. If the --skipDefaultVM option is not set the generated configuration will include the MBeans of the JVM and the MBeans of the Java Application.



Check the file and see if there are alias names with more than 19 characters. This errors are marked with NAME_CRASH_AS_19_CHAR_VALUE

Sub-command: generate-graph

This sub-command generates a *RRD* graph definition file for a given configuration file. The following example generates a graph definition file mygraph.properties using the configuration in file myconfig.xml.

./jmx-config-generator generate-graph --input myconfig.xml --output mygraph.properties reports=java.lang.ClassLoading.MBeanReport, \ java.lang.ClassLoading.0TotalLoadeClassCnt.AttributeReport, \ java.lang.ClassLoading.0LoadedClassCnt.AttributeReport, \ java.lang.ClassLoading.0UnloadedClassCnt.AttributeReport, \ java.lang.ClassLoading.0UnloadedClassCnt.AttributeReport, \ java.lang.Compilation.MBeanReport, \ <output omitted>

The following options are available for this sub-command.

Option/Argument	Description	Defa ult
input <jmx- datacollection.xml></jmx- 	Configuration file to use as input to generate the graph properties file	-
output <file></file>	Output filename for the generated graph properties file.	-
print-template	Prints the default template.	false
template <file></file>	Template file using <i>Apache Velocity</i> template engine to be used to generate the graph properties.	-
-h (help)	Show help and usage information.	false
-v (verbose)	Enables verbose mode for debugging purposes.	false

Graph Templates

The *JMX Config Generator* uses a template file to generate the graphs. It is possible to use a userdefined template. The option --template followed by a file lets the *JMX Config Generator* use the external template file as base for the graph generation. The following example illustrates how a custom template mytemplate.vm is used to generate the graph definition file mygraph.properties using the configuration in file myconfig.xml.

./jmx-config-generator generate-graph --input myconfig.xml --output mygraph.properties
--template mytemplate.vm

The template file has to be an *Apache Velocity* template. The following sample represents the template that is used by default:

```
reports=#foreach( $report in $reportsList )
${report.id}#if( $foreach.hasNext ), \
#end
#end
#foreach( $report in $reportsBody )
#[[##]]# $report.id
report.${report.id}.name=${report.name}
report.${report.id}.columns=${report.graphResources}
report.${report.id}.type=interfaceSnmp
report.${report.id}.command=--title="${report.title}" \
--vertical-label="${report.verticalLabel}" \
#foreach($graph in $report.graphs )
DEF:${graph.id}={rrd${foreach.count}}:${graph.resourceName}:AVERAGE \
AREA: ${graph.id} #${graph.coloreB} \
LINE2:${graph.id}#${graph.coloreA}:"${graph.description}" \
GPRINT:${graph.id}:AVERAGE:" Avg \\: %8.21f %s" \
GPRINT:${graph.id}:MIN:" Min \\: %8.21f %s" \
GPRINT:${graph.id}:MAX:" Max \\: %8.21f %s\\n" \
#end
#end
```

The *JMX Config Generator* generates different types of graphs from the jmx-datacollection-config.xml. The different types are listed below:

Туре	Description
AttributeReport	For each attribute of any <i>MBean</i> a graph will be generated. Composite attributes will be ignored.
MbeanReport	For each <i>MBean</i> a combined graph with all attributes of the <i>MBeans</i> is generated. Composite attributes will be ignored.
CompositeReport	For each composite attribute of every <i>MBean</i> a graph is generated.
CompositeAttribute Report	For each composite member of every <i>MBean</i> a combined graph with all composite attributes is generated.

4.6. Heatmap

The *Heatmap* can be either be used to display unacknowledged alarms or to display ongoing outages of nodes. Each of this visualizations can be applied on categories, foreign sources or services of nodes. The sizing of an entity is calculated by counting the services inside the entity. Thus, a node with fewer services will appear in a smaller box than a node with more services.

The feature is by default deactivated and is configured through opennms.properties.

Heatmap visualizations of alarms



Table C Heatman	daabbaand	application	manantiaa
Table 6. Heatmap	aasnooara	conneuration	properties
100000 01 110000000000		00.900.00000	p. op 0. 0000

Name	Туре	Description	Default
org.opennms.heatmap.d efaultMode	Strin g	There exist two options for using the heatmap: alarms and outages. This option configures which are displayed per default.	alarms
org.opennms.heatmap.d efaultHeatmap	Strin g	This option defines which <i>Heatmap</i> is displayed by default. Valid options are categories, foreignSources and monitoredServices.	categories
org.opennms.heatmap.c ategoryFilter	Strin g	The following option is used to filter for categories to be displayed in the <i>Heatmap</i> . This option uses the Java regular expression syntax. The default is .* so all categories will be displayed.	.*
org.opennms.heatmap.f oreignSourceFilter	Strin g	The following option is used to filter for foreign sources to be displayed in the <i>Heatmap</i> . This option uses the Java regular expression syntax. The default is .* so all foreign sources will be displayed.	.*
org.opennms.heatmap.s erviceFilter	Strin g	The following option is used to filter for services to be displayed in the <i>Heatmap</i> . This option uses the Java regular expression syntax. The default is .* so all services will be displayed.	.*
org.opennms.heatmap.o nlyUnacknowledged	Bool ean	This option configures whether only unacknowledged alarms will be taken into account when generating the alarm-based version of the <i>Heatmap</i> .	false
org.opennms.web.conso le.centerUrl	Strin g	You can also place the <i>Heatmap</i> on the landing page by setting this option to /heatmap/heatmap-box.jsp.	/surveilland e-box.jsp


\mathbf{O}

You can use negative lookahead expressions for excluding categories you wish not to be displayed in the heatmap, e.g. by using an expression like $^{(?!XY)}$.* you can filter out entities with names starting with XY.

4.7. Trend

The *Trend* feature allows to display small inline charts of database-based statistics. These chart are accessible in the *Status* menu of the *OpenNMS*' web application. Furthermore it is also possible to configure these charts to be displayed on the *OpenNMS*' landing page. To achieve this alter the org.opennms.web.console.centerUrl property to also include the entry /trend/trend-box.htm.

Trend chart structure



These charts can be configured and defined in the trend-configuration.xml file in your *OpenNMS'* etc directory. The following sample defines a *Trend* chart for displaying nodes with ongoing outages.

```
<trend-definition name="nodes">
     <title>Nodes</title> ①
     <subtitle>w/ Outages</subtitle> ②
     <visible>true</visible> ③
     <icon>fa-fire</icon> ④
     <trend-attributes> (5)
         <trend-attribute key="sparkWidth" value="100%"/>
         <trend-attribute key="sparkHeight" value="35"/>
         <trend-attribute key="sparkChartRangeMin" value="0"/>
         <trend-attribute key="sparkLineColor" value="white"/>
         <trend-attribute key="sparkLineWidth" value="1.5"/>
         <trend-attribute key="sparkFillColor" value="#88BB55"/>
         <trend-attribute key="sparkSpotColor" value="white"/>
         <trend-attribute key="sparkMinSpotColor" value="white"/>
         <trend-attribute key="sparkMaxSpotColor" value="white"/>
         <trend-attribute key="sparkSpotRadius" value="3"/>
         <trend-attribute key="sparkHighlightSpotColor" value="white"/>
         <trend-attribute key="sparkHighlightLineColor" value="white"/>
     </trend-attributes>
     <descriptionLink>outage/list.htm?outtype=current</descriptionLink> 6
     <description>${intValue[23]} NODES WITH OUTAGE(S)</description> ⑦
     <query> (8)
         <![CDATA]
             select (
                 select
                     count(distinct nodeid)
                 from
                     outages o, events e
                 where
                     e.eventid = o.svclosteventid
                     and iflostservice < E
                     and (ifreqainedservice is null
                         or ifregainedservice > E)
             ) from (
                 select
                     now() - interval '1 hour' * (0 + 1) AS S,
                     now() - interval '1 hour' * 0 as E
                 from
                     generate_series(0, 23) as 0
             ) I order by S;
         11>
     </query>
 </trend-definition>
```

① title of the *Trend* chart, see below for supported variable substitutions

② subtitle of the *Trend* chart, see below for supported variable substitutions

3 defines whether the chart is visible by default

- ④ icon for the chart, see Icons for viable options
- ⑤ options for inline chart, see jQuery Sparklines for viable options
- 6 the description link
- ⑦ the description text, see below for supported variable substitutions
- ⑧ the SQL statement for querying the chart's values



Don't forget to limit the SQL query's return values!

It is possible to use values or aggregated values in the title, subtitle and description fields. The following table describes the available variable substitutions.

Name	Туре	Description
\${intMax}	Integer	integer maximum value
\${doubleMax}	Double	maximum value
\${intMin}	Integer	integer minimum value
\${doubleMin}	Double	minimum value
\${intAvg}	Integer	integer average value
\${doubleAvg}	Double	average value
\${intSum}	Integer	integer sum of values
\${doubleSum}	Double	sum of value
<pre>\${intValue[]}</pre>	Integer	array of integer result values for the given SQL query
<pre>\${doubleValue[]}</pre>	Double	array of result values for the given SQL query
<pre>\${intValueChange[]}</pre>	Integer	array of integer value changes for the given SQL query
<pre>\${doubleValueChange[]}</pre>	Double	array of value changes for the given SQL query
<pre>\${intLastValue}</pre>	Integer	last integer value
<pre>\${doubleLastValue}</pre>	Double	last value
<pre>\${intLastValueChange}</pre>	Integer	last integer value change
<pre>\${doubleLastValueChange}</pre>	Double	last value change

Table 7. Variables usable in definition's title, subtitle and description fields

You can also display a single graph in your JSP files by including the file /trend/single-trend-box.jsp and specifying the name parameter.

Sample JSP snippet to include a single Trend chart with name 'example'

Chapter 5. Service Assurance

This section will cover the basic functionalities how *OpenNMS Meridian* tests if a service or device available and measure his latency.

In *OpenNMS Meridian* this task is provided by a *Service Monitor* framework. The main component is *Pollerd* which provides the following functionality:

- Track the status of a management resource or an application for availability calculations
- Measure response times for service quality
- Correlation of node and interface outages based on a Critical Service

The following image shows the model and representation of availability and response time.




Figure 21. Representation of latency measurement and availability

This information is based on *Service Monitors* which are scheduled and executed by *Pollerd*. A *Service* can have any arbitrary name and is associated with a *Service Monitor*. For example, we can define two *Services* with the name *HTTP* and *HTTP-8080*, both are associated with the *HTTP Service Monitor* but use a different *TCP port* configuration parameter. The following figure shows how *Pollerd* interacts with other components in *OpenNMS* and applications or agents to be monitored.

The availability is calculated over the last 24 hours and is shown in the *Surveillance Views*, *SLA Categories* and the *Node Detail Page*. Response times are displayed as *Resource Graphs* of the *IP Interface* on the *Node Detail Page*. Configuration parameters of the *Service Monitor* can be seen in the *Service Page* by clicking on the *Service Name* on the *Node Detail Page*. The status of a *Service* can be *Up* or *Down*.

\bigcirc

The *Service Page* also includes timestamps indicating the last time at which the service was polled and found to to be *Up* (Last Good) or *Down* (Last Fail). These fields can be used to validate that *Pollerd* is polling the services as expected.

When a *Service Monitor* detects an outage, *Pollerd* sends an *Event* which is used to create an *Alarm*. *Events* can also be used to generate *Notifications* for on-call network or server administrators. The following images shows the interaction of *Pollerd* in *OpenNMS Meridian*.




Figure 22. Service assurance with Pollerd in OpenNMS platform

Pollerd can generate the following *Events* in *OpenNMS Meridian*:

Event name	Description
uei.opennms.org/nodes/nodeLo stService	<i>Critical Services</i> are still up, just this service is lost.
uei.opennms.org/nodes/nodeRe gainedService	Service came back up
uei.opennms.org/nodes/interf aceDown	<i>Critical Service</i> on an IP interface is down or all services are down.
uei.opennms.org/nodes/interf aceUp	Critical Service on that interface came back up again
uei.opennms.org/nodes/nodeDo wn	All critical services on all IP interfaces are down from node. The whole host is unreachable over the network.
uei.opennms.org/nodes/nodeUp	Some of the <i>Critical Services</i> came back online.

The behavior to generate *interfaceDown* and *nodeDown* events is described in the Critical Service section.



This assumes that node-outage processing is enabled.

5.1. Pollerd Configuration

Table 8. Configuration and log files related to Pollerd.

File	Description
<pre>\$OPENNMS_HOME/etc/poller- configuration.xml</pre>	Configuration file for monitors and global daemon configuration

File	Description
<pre>\$OPENNMS_HOME/logs/poller.log</pre>	Log file for all monitors and the global <i>Pollerd</i>
<pre>\$OPENNMS_HOME/etc/response- graph.properties</pre>	RRD graph definitions for service response time measurements
<pre>\$OPENNMS_HOME/etc/events/opennms.e vents.xml</pre>	Event definitions for <i>Pollerd</i> , i.e. <i>nodeLostService</i> , <i>interfaceDown</i> or <i>nodeDown</i>

To change the behavior for service monitoring, the poller-configuration.xml can be modified. The configuration file is structured in the following parts:

- *Global daemon config*: Define the size of the used *Thread Pool* to run *Service Monitors* in parallel. Define and configure the *Critical Service* for *Node Event Correlation*.
- Polling packages: Package to allow grouping of configuration parameters for Service Monitors.
- *Downtime Model*: Configure the behavior of *Pollerd* to run tests in case of an *Outage* is detected.
- *Monitor service association*: Based on the name of the service, the implementation for application or network management protocols are assigned.

Global configuration parameters for Pollerd

- ① Size of the *Thread Pool* to run *Service Monitors* in parallel.
- ② Enable or Disable *Path Outage* functionality based on a *Critical Node* in a network path.
- ③ In case of unresponsive service services a *serviceUnresponsive* event is generated and not an outage. This prevents the application of the *Downtime Model* in retesting the service after 30 seconds to help prevent false alarms.

Configuration changes are applied by restarting *OpenNMS* and *Pollerd*. It is also possible to send an *Event* to *Pollerd* reloading the configuration. An *Event* can be sent on the *CLI* or the *Web User Interface*.

Send configuration reload event on CLI

```
cd $OPENNMS_HOME/bin
./send-event.pl uei.opennms.org/internal/reloadDaemonConfig --parm 'daemonName
Pollerd'
```

Home / Admin / S

-	_	_	-			_	
-		n	~	E١	10	n	•

Send Event to Op	benNMS	
Event	OpenNMS-defined internal event: reload specified daemon configuration	\$
UUID		
Node ID:	•	
Source Hostname:	vagrant-ubuntu-trusty-64	
Interface:		
Service:		
Parameters:	Name: daemonName Value:	
Description:	Add additional parameter	
Description:	Select One	\$
Operator Instructions:		
	Reset	
Send Event »»		

Figure 23. Send configuration reload event with the Web User Interface

5.1.1. Meta-Data-DSL

Each parameter value can leverage dynamic configuration by using the Meta-Data-DSL.

During evaluation of an expression the following scopes are available:


• Node meta-data

- Interface meta-data
- Service meta-data

5.2. Critical Service

Monitoring services on an *IP network* can be resource expensive, especially in cases where many of these services are not available. When a service is offline, or unreachable, the monitoring system spends most of it's time waiting for retries and timeouts.

In order to improve efficiency, *OpenNMS Meridian* deems all services on a interface to be *Down* if the critical service is *Down*. By default *OpenNMS Meridian* uses *ICMP* as the critical service.



The following image shows, how a Critical Services is used to generate these events.

Figure 24. Service assurance with Pollerd in OpenNMS Meridian platform

- (1) Critical services are all Up on the Node and just a nodeLostService is sent.
- (2) Critical service of one of many *IP interface* is *Down* and *interfaceDown* is sent. All other services are not tested and no events are sent, the services are assumed as unreachable.
- (3) All Critical services on the *Node* are *Down* and just a *nodeDown* is sent. All other services on the other *IP Interfaces* are not tested and no events are sent, these services are assumed as unreachable.

The *Critical Service* is used to correlate outages from *Services* to a *nodeDown* or *interfaceDown* event. It is a global configuration of *Pollerd* defined in *poller-configuration.xml*. The *OpenNMS Meridian* default configuration enables this behavior.

- ① Enable Node Outage correlation based on a Critical Service
- ② Optional: In case of nodes without a *Critical Service* this option controls the behavior. If set to true then all services will be polled. If set to false then the first service in the package that exists on the node will be polled until service is restored, and then polling will resume for all services.
- 3 Define Critical Service for Node Outage correlation

5.3. Downtime Model

By default the monitoring interval for a service is 5 minutes. To detect also short services outages, caused for example by automatic network rerouting, the downtime model can be used. On a detected service outage, the interval is reduced to 30 seconds for 5 minutes. If the service comes back within 5 minutes, a shorter outage is documented and the impact on service availability can be less than 5 minutes. This behavior is called *Downtime Model* and is configurable.




Figure 25. Downtime model with resolved and ongoing outage

In figure Outages and Downtime Model there are two outages. The first outage shows a short outage which was detected as *up* after 90 seconds. The second outage is not resolved now and the monitor has not detected an available service and was not available in the first 5 minutes (10 times 30 second polling). The scheduler changed the polling interval back to 5 minutes.

```
<downtime interval="30000" begin="0" end="300000" /><!-- 30s, 0, 5m -->①
<downtime interval="300000" begin="300000" end="43200000" /><!-- 5m, 5m, 12h -->②
<downtime interval="600000" begin="43200000" end="43200000" /><!-- 10m, 12h, 5d -->③
<downtime interval="3600000" begin="43200000" delete="never"/><!-- 1h, 5d -->④
```

- ① from 0 seconds after an outage is detected until 5 minutes, the polling interval will be set to 30 seconds
- 2 after 5 minutes of an ongoing outage until 12 hours, the polling interval will be set to 5 minutes
- ③ after 12 hours of an ongoing outage until 5 days, the polling interval will be set to 10 minutes
- ④ after 5 days of an ongoing outage the service will be polled only once a hour and we do not delete services

The last downtime interval can have an attribute delete and allows you to influence the service lifecycle. It defines the behavior that happens if a service doesn't come back online after 5 days. The following downtime attributes for delete can be used:

Value	description
never	services will never be deleted automatically
managed	only managed services will be deleted
always	managed and unmanaged services will be deleted
not set	if delete is not configured it is similar to delete="never" and is the default

5.4. Path Outages

An outage of a central network component can cause a lot of node outages. *Path Outages* can be used to suppress *Notifications* based on how *Nodes* depend on each other in the network which are defined in a *Critical Path*. The *Critical Path* needs to be configured from the network perspective of the monitoring system. By default the *Path Outage* feature is disabled and has to be enabled in the poller-configuration.xml.

The following image shows an example network topology.




Figure 26. Path Outage example

From the perspective of the monitoring system, a Router named *default-gw-01* is on the *Critical Path* to reach two networks. If Router *default-gw-01* is down, it is not possible to reach any node in the two networks behind and they will be all unreachable as well. In this case an administrator would like to have just one notification for *default-gw-01* and not for all the other *Nodes* behind. Building this configuration in *OpenNMS Meridian* requires the following information:

- Parent Foreign Source: The Foreign Source where the parent node is defined.
- Parent Foreign ID: The Foreign ID of the parent Node where this node depends on.
- The IP Interface selected as Primary is used as Critical IP

In this example we have created all *Nodes* in a *Provisioning Requisition* named Network-ACME and we use as the *Foreign ID* the same as the *Node Label*.

In the Web UI go to Admin \rightarrow Configure OpenNMS \rightarrow Manage Provisioning Requisitions \rightarrow Edit the Requisition \rightarrow Edit the Node \rightarrow Path Outage to configure the network path by setting the Parent Foreign Source, Parent Foreign ID and Provisioned Node.

Parent Foreign Source	Parent Foreign ID	Provisioned Node
not defined	not defined	default-gw-01
Network-ACME	default-gw-01	node-01
Network-ACME	default-gw-01	node-02
Network-ACME	default-gw-01	default-gw02
Network-ACME	default-gw-02	node-03

Table 9. Provisioning for Topology Example

Parent Foreign	Parent Foreign	Provisioned
Source	ID	Node
Network-ACME	default-gw-02	node-04



The *IP Interface* which is set to *Primary* is selected as the *Critical IP*. In this example it is important the *IP interface* on *default-gw-01* in the network 192.168.1.0/24 is set as *Primary* interface. The IP interface in the network 172.23.42.0/24 on *default-gw-02* is set as *Primary* interface.

5.5. Poller Packages

To define more complex monitoring configuration it is possible to group *Service* configurations into *Polling Packages*. They allow to assign to *Nodes* different *Service Configurations*. To assign a *Polling Package* to nodes the Rules/Filters syntax can be used. Each *Polling Package* can have its own Downtime Model configuration.

Multiple packages can be configured, and an interface can exist in more than one package. This gives great flexibility to how the service levels will be determined for a given device.

Polling package assigned to Nodes with Rules and Filters

- ① Unique name of the polling package.
- ② Filter can be based on IP address, categories or asset attributes of *Nodes* based on Rules/Filters. The filter is evaluated first and is **required**. This package is used for all *IP Interfaces* which don't have 0.0.0.0 as an assigned *IP address* and is **required**.
- ③ Allow to specify if the configuration of *Services* is applied on a range of *IP Interfaces* (IPv4 or IPv6).

Instead of the include-range it is possible to add one or more specific *IP-Interfaces* with:

Defining a specific IP Interfaces

<specific>192.168.1.59</specific>

It is also possible to exclude *IP Interfaces* with:

```
Exclude IP Interfaces
```

```
<exclude-range begin="192.168.0.100" end="192.168.0.104"/>
```

5.5.1. Response Time Configuration

The definition of *Polling Packages* allows to configure similar services with different polling intervals. All the response time measurements are persisted in *RRD Files* and require a definition. Each *Polling Package* contains a *RRD* definition

RRD configuration for Polling Package example1

- Polling interval for all services in this *Polling Package* is reflected in the step of size 300 seconds. All services in this package have to polled in 5 min interval, otherwise response time measurements are not correct persisted.
- 2 1 step size is persisted 2016 times: 1 * 5 min * 2016 = 7 d, 5 min accuracy for 7 d.
- 3 12 steps average persisted 1488 times: 12 * 5 min * 1488 = 62 d, aggregated to 60 min for 62 d.
- ④ 288 steps average persisted 366 times: 288 * 5 min * 366 = 366 d, aggregated to 24 h for 366 d.
- ⑤ 288 steps maximum from 24 h persisted for 366 d.
- 6 288 steps minimum from 24 h persisted for 366 d.



The *RRD* configuration and the service polling interval has to be aligned. In other cases the persisted response time data is not correct displayed in the response time graph.



If the polling interval is changed afterwards, existing *RRD* files needs to be recreated with the new definitions.

5.5.2. Overlapping Services

With the possibility of specifying multiple *Polling Packages* it is possible to use the same *Service* like *ICMP* multiple times. The order how *Polling Packages* in the poller-configuration.xml are defined is important when *IP Interfaces* match multiple *Polling Packages* with the same *Service* configuration.

The following example shows which configuration is applied for a specific service:

```
<package name="less-specific">
 <filter>IPADDR != '0.0.0.0'</filter>
 <include-range begin="1.1.1.1" end="254.254.254.254" />
 <rrd step="300">①
   <rra>RRA:AVERAGE:0.5:1:2016</rra>
   <rra>RRA: AVFRAGE: 0.5:12:1488</rra>
   <rra>RRA:AVERAGE:0.5:288:366</rra>
   <rra>RRA:MAX:0.5:288:366</rra>
   <rra>RRA:MIN:0.5:288:366</rra>
 </rrd>
 <service name="ICMP" interval="300000" user-defined="false" status="on">②
   <parameter key="retry" value="5" />③
   <parameter key="timeout" value="10000" />④
   <parameter key="rrd-repository" value="/var/lib/opennms/rrd/response" />
   <parameter key="rrd-base-name" value="icmp" />
   <parameter key="ds-name" value="icmp" />
 </service>
 <downtime interval="30000" begin="0" end="300000" />
 <downtime interval="300000" begin="300000" end="43200000" />
 <downtime interval="600000" begin="43200000" end="432000000" />
</package>
<package name="more-specific">
 <filter>IPADDR != '0.0.0.0'</filter>
 <include-range begin="192.168.1.1" end="192.168.1.254" />
 <include-range begin="2600:::1" end="2600:::ffff" />
 <rrd step="30">①
   <rra>RRA:AVERAGE:0.5:1:20160</rra>
   <rra>RRA:AVERAGE:0.5:12:14880</rra>
   <rra>RRA:AVERAGE:0.5:288:3660</rra>
   <rra>RRA:MAX:0.5:288:3660</rra>
   <rra>RRA:MIN:0.5:288:3660</rra>
 </rrd>
 <service name="ICMP" interval="30000" user-defined="false" status="on">②
   <parameter key="retry" value="2" />③
   <parameter key="timeout" value="3000" />④
   <parameter key="rrd-repository" value="/var/lib/opennms/rrd/response" />
   <parameter key="rrd-base-name" value="icmp" />
   <parameter key="ds-name" value="icmp" />
 </service>
 <downtime interval="10000" begin="0" end="300000" />
 <downtime interval="300000" begin="300000" end="43200000" />
 <downtime interval="600000" begin="43200000" end="432000000" />
</package>
```

① Polling interval in the packages are 300 seconds and 30 seconds

② Different polling interval for the service *ICMP*

- ③ Different retry settings for the service *ICMP*
- ④ Different timeout settings for the service *ICMP*

The last *Polling Package* on the service will be applied. This can be used to define a less specific catch all filter for a default configuration. A more specific *Polling Package* can be used to overwrite the default setting. In the example above all *IP Interfaces* in 192.168.1/24 or 2600:/64 will be monitored with ICMP with different polling, retry and timeout settings.

Which *Polling Packages* are applied to the *IP Interface* and *Service* can be found in the *Web User Interface*. The *IP Interface* and *Service* page show which *Polling Package* and *Service* configuration is applied for this specific service.

nterface: 10.23.42.1 lew Events by IP Address HTTP Delet	e Rescan Schedule Outage		ICMP service on 10. View Events Delete	23.42.1		
General			General			
Node	default-gw-02		Node	default-	gw-02	
Polling Status	Managed		Interface	10.23.42	2.1	
Polling Package	example1 (*)		Polling Status	Manage	d	
Polling Package	example2 (*)		Polling Package	example	92	
Interface Index			Monitor Class	org.oper	nnms.netmgt.poller.monitors.lcmpMonitor	
Last Service Scan			Service Parameters			
Availability			ds-name		icmp	
10.23.42.1 30 20:00 23:00 02:00	05:00 08:00 11:00 14:00 17:0	97.749%	retry		5	
нттр		97.749%	rrd-base-name		icmp	
ICMP		97.749%	rrd-repository		/var/lib/opennms/rrd/response	
SMTP		97.749%	timeout		10000	
			Overall Availability			
				22:00 01:00	04:00 07:00 10:00 13:00 16:00	99.172%
			ICMP			99.172%
			Application Membershi	ps (Edit)		
			This service is not a mem	nber of any app	lications	

Figure 27. Polling Package applied to IP interface and Service

5.5.3. Service Patterns

Usually, the *Poller* used to monitor a *Service* is found by the matching the pollers name with the service name. In addition, a matching poller can be found if an additional element pattern is specified for the poller. If so, the poller is used for all services matching the *RegEx* pattern, too.

The *RegEx* pattern allows to specify named capture groups. There can be multiple capture groups inside of a pattern, but each must have a unique name. Please note, that the *RegEx* must be escaped or be wrapped in a CDATA-Tag inside the configuration XML to make it a valid property.

If a poller is matched using its pattern, the parts of the service name which matches the capture groups of the pattern are available as parameters to the Meta-Data-DSL using the context pattern and the capture group name as key.

Examples:

<pattern><![CDATA[^HTTP-(?<vhost>.*)\$]]></pattern>

Matches all services which names starts with HTTP- followed by a host name. If the services is called HTTP-www.example.com, the Meta-DSL expression *\${pattern:vhost}* will resolved to

www.example.com.

<pattern><![CDATA[^HTTP-(?<vhost>.*?):(?<port>[0-9]+)\$]]></pattern>"

Matches all services which names starts with HTTP- followed by a hostname and a port. There will be two variables (*fpattern:vhost*) and *fpattern:port*) which can be used in the poller parameters.

The service pattern mechanism can be used to whenever there are multiple instances of a service on the same interface. By specifying a distinct service name to each instance, the services is identifiable, but there is no need to add a poller definition per service. Common use-cases for such services are HTTP Virtual Hosts, where multiple web applications run on the same web-server or BGP session monitoring where each router has multiple neighbours.

5.5.4. Test Services on manually

For troubleshooting it is possible to run a test via the Karaf Shell:

```
ssh -p 8101 admin@localhost
```

Once in the shell, you can print show the commands help as follows:

```
opennms> opennms:poll --help
DESCRIPTION
        opennms:poll
    Used to invoke a monitor against a host at a specified location
SYNTAX
        opennms:poll [options] host [attributes]
ARGUMENTS
        host
                Hostname or IP Address of the system to poll
                (required)
        attributes
                Monitor specific attributes in key=value form
OPTIONS
        --help
                Display this help message
        -l, --location
                Location
                (defaults to Default)
        -s, --system-id
                System ID
        -t, --ttl
                Time to live
        -P, --package
                Poller Package
        -S, --service
                Service name
        -n, --node-id
                Node Id for Service
        -c, --class
                Monitor Class
```

The following example runs the *ICMP* monitor on a specific *IP Interface*.

Run ICMP monitor configuration defined in specific Polling Package

opennms> opennms:poll -S ICMP -P example1 10.23.42.1

The output is verbose which allows debugging of *Monitor* configurations. Important output lines are shown as the following:

Important output testing a service on the CLI

```
Package: example1 ①
Service: ICMP ②
Monitor: org.opennms.netmgt.poller.monitors.IcmpMonitor ③
Parameter ds-name: icmp ④
Parameter retry: 2 ⑤
Parameter rrd-base-name: icmp ④
Parameter rrd-repository: /opt/opennms/share/rrd/response ④
Parameter timeout: 3000 ⑤
Service is Up on 192.168.31.100 using org.opennms.netmgt.poller.monitors.IcmpMonitor:
⑥
response-time: 407,0000 ⑦
```

- ① Service and Package of this test
- 2 Applied Service configuration from Polling Package for this test
- ③ Service Monitor used for this test
- ④ RRD configuration for response time measurement
- ⑤ Retry and timeout settings for this test
- 6 Polling result for the service polled against the *IP address*
- 7 Response time

5.5.5. Test filters on Karaf Shell

Filters are ubiquitous in opennms configurations with <filter> syntax. This karaf shell can be used to verify filters. For more info, refer to Filters.

ssh -p 8101 admin@localhost

Once in the shell, print command help as follows

For ex: Run a filter rule that match a location

opennms:filter "location='MINION'"

Output is displayed as follows

```
nodeId=2 nodeLabel=00000000-0000-0000-0000-000000ddba11 location=MINION
IpAddresses:
127.0.0.1
```

Another ex: Run a filter that match a node location and for a given IP Address range. Refer to IPLIKE for more info on using IPLIKE syntax.

```
opennms:filter "location='Default' & (IPADDR IPLIKE 172.*.*.*)"
```

Output is displayed as follows



Node info displayed will have nodeId, nodeLabel, location and optional fileds like foreignId, foreignSource, categories when they exist.

5.6. Service monitors

To support several specific applications and management agents, *Pollerd* executes *Service Monitors*. This section describes all available built-in *Service Monitors* which are available and can be configured to allow complex monitoring. For information how these can be extended, see *Development Guide* of the *OpenNMS* documentation.

5.6.1. Common Configuration Parameters

Application or Device specific *Monitors* are based on a generic API which provide common configuration parameters. These minimal configuration parameters are available in all *Monitors* and describe the behavior for timeouts, retries, etc.

Table 10. Common implemented configuration parameters

Parameter	Description	Require d	Default value
retry	Number of attempts to test a <i>Service</i> to be up or down.	optional	3
timeout	Timeout for the isReachable method, in milliseconds.	optional	3000
invert-status	Invert the up/down behavior of the monitor	optional	false

In case the *Monitor* is using the *SNMP Protocol* the default configuration for timeout and retry are used from the *SNMP Configuration* (snmp-config.xml).

Minion Configuration Parameters

 \bigcirc

When nodes are configured with a non-default location, the associated *Service Monitors* are executed on a *Minion* configured with that same location. If there are many *Minions* at a given location, the *Service Monitor* may be executed on any of the *Minions* that are currently available. Users can choose to execute a *Service Monitor* on a specific *Minion*, by specifying the *System ID* of the *Minion*. This mechanism is used for monitoring the *Minions* individually.

The following parameters can be used to override this behavior and control **where** the *Service Monitors* are executed.

Parameter	Description	Requi red	Default value
location	Specify the location at which the <i>Service Monitor</i> should be executed.	option al	(The location of the associated node)
system-id	Specify the <i>System ID</i> on which the <i>Service</i> <i>Monitor</i> should be executed	option al	(None)
use-foreign-id-as- system-id	Use the foreign id of the associated node as the <i>System ID</i>	option al	false

Table 11. Minion configuration parameters



When specifying a *System ID* the location should also be set to the corresponding location for that system.

5.6.2. Using Placeholders in Parameters

Some monitor parameters support placeholder substitution. You can reference some node,

interface, and asset record properties by enclosing them in { and }. The supported properties are:

- nodeId
- nodeLabel
- foreignSource
- foreignId
- ipAddr (or ipAddress)
- all node asset record fields (e.g. username, password)

Parameters that support placeholder substitution are marked 'Yes' in the 'Placeholder substitution' column of the **Configuaration and Usage** section of the monitor documentation.

5.6.3. ActiveMQMonitor

This monitor tests the availablity of an ActiveMQ Broker. The service is considered available if a successful connection is made.

Monitor facts

Class Name	org.opennms.netmgt.poller.monitors.ActiveMQMonitor
Remote Enabled	true or false if the monitor can be used by the OpenNMS Meridian remote poller

Configuration and Usage

Table 12. Monitor specific parameters for the ActiveMQMonitor

Paramet er	Description	Requi red	Default value
broker- url	The ActiveMQ Broker URL to connect to.	requi red	vm://localhost?create=false&b roker.persistent=false
USEL	The user name used to login to the ActiveMQ broker.	optio nal	-
password	The password used to authenticate the user on the ActiveMQ broker.	optio nal	-
use- nodelabe l	A boolean to enable using the nodelabel when connecting to the ActiveMQ broker.	optio nal	false
create- session	A boolean to enable creating a JMS Session when connecting to the ActiveMQ broker.	optio nal	false
client- id	The client ID to use when connecting to the ActiveMQ broker.	optio nal	-

This monitor implements the Common Configuration Parameters.

Examples

Some example configuration how to configure the monitor in the poller-configuration.xml.

```
<parameter key="broker-url" value="failover://auto+ssl://192.168.1.1:61616/"/>
<parameter key="use-nodelabel" value="true"/>
```

5.6.4. AvailabilityMonitor

This monitor tests reachability of a node by using the *isReachable* method of the *InetAddress* java class. The service is considered available if isReachable returns true. See Oracle's documentation for more details.



This monitor is deprecated in favour of the IcmpMonitor monitor. You should only use this monitor on remote pollers running on unusual configurations (See below for more details).

Monitor facts

Class Name	<pre>org.opennms.netmgt.poller.monitors.AvailabilityMonitor</pre>
Remote Enabled	true

Configuration and Usage

This monitor implements the Common Configuration Parameters.

Examples

IcmpMonitor vs AvailabilityMonitor

This monitor has been developped in a time when the IcmpMonitor monitor wasn't remote enabled, to circumvent this limitation. Now, with the JNA ICMP implementation, the IcmpMonitor monitor is remote enabled under most configurations and this monitor shouldn't be needed -unless you're running your remote poller on such an unusual configuration (See also issue NMS-6735 for more information)-.

5.6.5. BgpSessionMonitor

This monitor checks if a BGP-Session to a peering partner (peer-ip) is functional. To monitor the BGP-Session the RFC1269 SNMP MIB is used and test the status of the session using the following OIDs is used:

BGP_PEER_STATE_OID = .1.3.6.1.2.1.15.3.1.2.<peer-ip> BGP_PEER_ADMIN_STATE_OID = .1.3.6.1.2.1.15.3.1.3.<peer-ip> BGP_PEER_REMOTEAS_OID = .1.3.6.1.2.1.15.3.1.9.<peer-ip> BGP_PEER_LAST_ERROR_OID = .1.3.6.1.2.1.15.3.1.14.<peer-ip> BGP_PEER_FSM_EST_TIME_OID = .1.3.6.1.2.1.15.3.1.16.<peer-ip>

The <peer-ip> is the far end IP address of the BGP session end point.

A SNMP get request for BGP_PEER_STATE_OID returns a result between 1 to 6. The servicestates for OpenNMS Meridian are mapped as follows:

Resul t	State description	Monitor state in OpenNMS Meridian
1	Idle	DOWN
2	Connect	DOWN
3	Active	DOWN
4	OpenSent	DOWN
5	OpenConfirm	DOWN
6	Established	UP

Monitor facts

Class Name	org.opennms.netmgt.poller.monitors.BgpSessionMonitor
Remote Enabled	false

To define the mapping I used the description from RFC1771 BGP Finite State Machine.

Configuration and Usage

Paramete	Description	Require	Default
r		d	value
bgpPeerIp	IP address of the far end BGP peer session	required	-

This monitor implements the Common Configuration Parameters.

Examples

To monitor the session state *Established* it is necessary to add a service to your poller configuration in '\$OPENNMS_HOME/etc/poller-configuration.xml', for example:

Error code mapping

The *BGP_PEER_LAST_ERROR_OID* gives an error in HEX-code. To make it human readable a codemapping table is implemented:

Error code	Error Message
0100	Message Header Error
0101	Message Header Error - Connection Not Synchronized
0102	Message Header Error - Bad Message Length
0103	Message Header Error - Bad Message Type
0200	OPEN Message Error
0201	OPEN Message Error - Unsupported Version Number
0202	OPEN Message Error - Bad Peer AS
0203	OPEN Message Error - Bad BGP Identifier
0204	OPEN Message Error - Unsupported Optional Parameter
0205	OPEN Message Error (deprecated)
0206	OPEN Message Error - Unacceptable Hold Time
0300	UPDATE Message Error
0301	UPDATE Message Error - Malformed Attribute List
0302	UPDATE Message Error - Unrecognized Well-known Attribute
0303	UPDATE Message Error - Missing Well-known Attribute

Error code	Error Message
0304	UPDATE Message Error - Attribute Flags Error
0305	UPDATE Message Error - Attribute Length Error
0306	UPDATE Message Error - Invalid ORIGIN Attribute
0307	UPDATE Message Error (deprecated)
0308	UPDATE Message Error - Invalid NEXT_HOP Attribute
0309	UPDATE Message Error - Optional Attribute Error
030A	UPDATE Message Error - Invalid Network Field
030B	UPDATE Message Error - Malformed AS_PATH
0400	Hold Timer Expired
0500	Finite State Machine Error
0600	Cease
0601	Cease - Maximum Number of Prefixes Reached
0602	Cease - Administrative Shutdown
0603	Cease - Peer De-configured
0604	Cease - Administrative Reset
0605	Cease - Connection Rejected
0606	Cease - Other Configuration Change
0607	Cease - Connection Collision Resolution
0608	Cease - Out of Resources

Instead of HEX-Code the error message will be displayed in the service down logmessage. To give some additional informations the logmessage contains also

BGP-Peer Adminstate BGP-Peer Remote AS BGP-Peer established time in seconds

Debugging

If you have problems to detect or monitor the BGP Session you can use the following command to figure out where the problem come from.

snmpwalk -v 2c -c <myCommunity> <myRouter2Monitor> .1.3.6.1.2.1.15.3.1.2.99.99.99.99

Replace 99.99.99 with your BGP-Peer IP. The result should be an Integer between 1 and 6.

5.6.6. BSFMonitor

This monitor runs a *Bean Scripting Framework* BSF compatible script to determine the status of a service. Users can write scripts to perform highly custom service checks. This monitor is not optimised for scale. It's intended for a small number of custom checks or prototyping of monitors.

BSFMonitor vs SystemExecuteMonitor

The *BSFMonitor* avoids the overhead of *fork(2)* that is used by the *SystemExecuteMonitor*. *BSFMonitor* also grants access to a selection of *OpenNMS Meridian* internal methods and classes that can be used in the script.

Monitor facts

Class Name	org.opennms.netmgt.poller.monitors.BSFMonitor
Remote Enabled	false

Configuration and Usage

Table 13. Monitor specific parameters for the BSFMonitor	Table 13.	Monitor	specific j	parameters	for the	BSFMonitor
--	-----------	---------	------------	------------	---------	-------------------

Paramet er	Description	Requ ired	Default value
file-name	Path to the script file.	requi red	-
bsf- engine	The BSF Engine to run the script in different languages like Bean Shell: bsh.util.BeanShellBSFEngine Groovy: org.codehaus.groovy.bsf.GroovyEngine Jython: org.apache.bsf.engines.jython.JythonEngine	requi red	-
run-type	one of eval or exec	optio nal	eval
lang- class	The BSF language class, like groovy or beanshell.	optio nal	file-name extension is interpreted by default
file- extension s	comma-separated list	optio nal	-

This monitor implements the Common Configuration Parameters.

Table 14. Beans which can be used in the script

Variabl e	Туре	Description
тар	Map <string, object=""></string,>	The <i>map</i> contains all various parameters passed to the monitor from the service definition it the poller-configuration.xml file.
ip_addr	String	The IP address that is currently being polled.
node_id	int	The Node ID of the node the ip_addr belongs to.
node_la bel	String	The Node Label of the node the <code>ip_addr</code> and service belongs to.
svc_nam e	String	The name of the service that is being polled.
bsf_mon itor	BSFMonitor	The instance of the <i>BSFMonitor</i> object calling the script. Useful for logging via its log(String sev, String fmt, Object args) method.
results	HashMap <string, String></string, 	The script is expected to put its results into this object. The status indication should be set into the entry with key status. If the status is not OK, a key reason should contain a description of the problem.
times	LinkedHashMap <strin g, Number></strin 	The script is expected to put one or more response times into this object.

Additionally every parameter added to the service definition in poller-configuration.xml is available as a *String* object in the script. The key attribute of the parameter represents the name of the *String* object and the value attribute represents the value of the *String* object.



Please keep in mind, that these parameters are also accessible via the *map* bean.



Avoid non-character names for parameters to avoid problems in the script languages.

Response Codes

The script has to provide a status code that represents the status of the associated service. The following status codes are defined:

Table 15. Status codes

Cod e	Description
OK	Service is available
UNK	Service status unknown
UNR	Service is unresponsive
NOK	Service is unavailable

Response time tracking

By default the *BSFMonitor* tracks the whole time the script file consumes as the response time. If the response time should be persisted the response time add the following parameters:

RRD response time tracking for this service in poller-configuration.xml

```
<!-- where in the filesystem response times are stored -->
<parameter key="rrd-repository" value="/opt/opennms/share/rrd/response" />
<!-- name of the rrd file -->
<parameter key="rrd-base-name" value="minimalbshbase" />
<!-- name of the data source in the rrd file -->
<!-- by default "response-time" is used as ds-name -->
<parameter key="ds-name" value="myResponseTime" />
```

It is also possible to return one or many response times directly from the script. To add custom response times or override the default one, add entries to the *times* object. The entries are keyed with a *String* that names the datasource and have as values a number that represents the response time. To override the default response time datasource add an entry into times named response-time.

Timeout and Retry

The *BSFMonitor* does not perform any timeout or retry processing on its own. If retry and or timeout behaviour is required, it has to be implemented in the script itself.

Requirements for the script (run-types)

Depending on the run-type the script has to provide its results in different ways. For minimal scripts with very simple logic run-type eval is the simple option. Scripts running in eval mode have to return a *String* matching one of the status codes.

If your script is more than a one-liner, run-type exec is essentially required. Scripts running in exec mode need not return anything, but they have to add a status entry with a status code to the *results* object. Additionally, the *results* object can also carry a "reason":"message" entry that is used in non OK states.

Commonly used language settings

The *BSF* supports many languages, the following table provides the required setup for commonly used languages.

Table 16. BSF language setups

Languag e	lang- class	bsf-engine	required library
BeanShell	beanshell	bsh.util.BeanShellBSFEngine	supported by default

Languag e	lang- class	bsf-engine	required library
Groovy	groovy	org.codehaus.groovy.bsf.GroovyEngine	groovy-all-[version].jar
Jython	jython	org.apache.bsf.engines.jython.JythonEngine	jython-[version].jar

Example Bean Shell

BeanShell example poller-configuration.xml

```
<service name="MinimalBeanShell" interval="300000" user-defined="true" status="on">
    <parameter key="file-name" value="/tmp/MinimalBeanShell.bsh"/>
    <parameter key="bsf-engine" value="bsh.util.BeanShellBSFEngine"/>
</service>
</monitor service="MinimalBeanShell" class-name=
"org.opennms.netmgt.poller.monitors.BSFMonitor" />
```

BeanShell example MinimalBeanShell.bsh script file

```
bsf_monitor.log("ERROR", "Starting MinimalBeanShell.bsf", null);
File testFile = new File("/tmp/TestFile");
if (testFile.exists()) {
  return "OK";
} else {
  results.put("reason", "file does not exist");
  return "NOK";
}
```

Example Groovy

To use the Groovy language an additional library is required. Copy a compatible groovy-all.jar into to opennms/lib folder and restart *OpenNMS Meridian*. That makes *Groovy* available for the *BSFMonitor*.

Groovy example poller-configuration.xml with default run-type set to eval

```
<service name="MinimalGroovy" interval="300000" user-defined="true" status="on">
    <parameter key="file-name" value="/tmp/MinimalGroovy.groovy"/>
    <parameter key="bsf-engine" value="org.codehaus.groovy.bsf.GroovyEngine"/>
</service>
<monitor service="MinimalGroovy" class-name=
"org.opennms.netmgt.poller.monitors.BSFMonitor" />
```

Groovy example MinimalGroovy.groovy script file for run-type eval

```
bsf_monitor.log("ERROR", "Starting MinimalGroovy.groovy", null);
File testFile = new File("/tmp/TestFile");
if (testFile.exists()) {
  return "OK";
} else {
  results.put("reason", "file does not exist");
  return "NOK";
}
```

Groovy example poller-configuration.xml with run-type set to exec

```
<service name="MinimalGroovy" interval="30000" user-defined="true" status="on">
    <parameter key="file-name" value="/tmp/MinimalGroovy.groovy"/>
    <parameter key="bsf-engine" value="org.codehaus.groovy.bsf.GroovyEngine"/>
    <parameter key="run-type" value="exec"/>
</service>
</monitor service="MinimalGroovy" class-name=
"org.opennms.netmgt.poller.monitors.BSFMonitor" />
```

Groovy example MinimalGroovy.groovy script file for run-type set to exec

```
bsf_monitor.log("ERROR", "Starting MinimalGroovy", null);
def testFile = new File("/tmp/TestFile");
if (testFile.exists()) {
  results.put("status", "OK")
} else {
  results.put("reason", "file does not exist");
  results.put("status", "NOK");
}
```

Example Jython

To use the *Jython (Java* implementation of *Python*) language an additional library is required. Copy a compatible jython-x.y.z.jar into the opennms/lib folder and restart *OpenNMS Meridian*. That makes *Jython* available for the *BSFMonitor*.

Jython example poller-configuration.xml *with* run-type exec

```
<service name="MinimalJython" interval="300000" user-defined="true" status="on">
    <parameter key="file-name" value="/tmp/MinimalJython.py"/>
    <parameter key="bsf-engine" value="org.apache.bsf.engines.jython.JythonEngine"/>
    <parameter key="run-type" value="exec"/>
</service>
</monitor service="MinimalJython" class-name=
"org.opennms.netmgt.poller.monitors.BSFMonitor" />
```

Jython example MinimalJython.py *script file for* run-type *set to* exec

```
from java.io import File
bsf_monitor.log("ERROR", "Starting MinimalJython.py", None);
if (File("/tmp/TestFile").exists()):
    results.put("status", "OK")
else:
    results.put("reason", "file does not exist")
    results.put("status", "NOK")
```



We have to use run-type exec here because *Jython* chokes on the import keyword in eval mode.



As proof that this is really *Python*, notice the substitution of *Python's* None value for Java's null in the log call.

Advanced examples

The following example references all beans that are exposed to the script, including a custom parameter.

Groovy example poller-configuration.xml

```
<service name="MinimalGroovy" interval="30000" user-defined="true" status="on">
<parameter key="file-name" value="/tmp/MinimalGroovy.groovy"/>
<parameter key="bsf-engine" value="org.codehaus.groovy.bsf.GroovyEngine"/>
<!-- custom parameters (passed to the script) -->
<parameter key="myParameter" value="Hello Groovy" />
<!-- optional for response time tracking -->
<parameter key="rrd-repository" value="/opt/opennms/share/rrd/response" />
<parameter key="rrd-base-name" value="minimalgroovybase" />
<parameter key="ds-name" value="minimalgroovyds" />
</service>
```

Groovy example Bean referencing script file

```
bsf_monitor.log("ERROR", "Starting MinimalGroovy", null);
//list of all available objects from the BSFMonitor
Map<String, Object> map = map;
bsf_monitor.log("ERROR", "---- map ----", null);
bsf monitor.log("ERROR", map.toString(), null);
String ip_addr = ip_addr;
bsf monitor.log("ERROR", "---- ip addr ----", null);
bsf_monitor.log("ERROR", ip_addr, null);
int node id = node id;
bsf_monitor.log("ERROR", "---- node_id ----", null);
bsf_monitor.log("ERROR", node_id.toString(), null);
String node_label = node_label;
bsf monitor.log("ERROR", "---- node label ----", null);
bsf monitor.log("ERROR", node label, null);
String svc name = svc name;
bsf_monitor.log("ERROR", "---- svc_name ----", null);
bsf_monitor.log("ERROR", svc_name, null);
org.opennms.netmgt.poller.monitors.BSFMonitor bsf_monitor = bsf_monitor;
bsf_monitor.log("ERROR", "---- bsf_monitor ----", null);
bsf_monitor.log("ERROR", bsf_monitor.toString(), null);
HashMap<String, String> results = results;
bsf_monitor.log("ERROR", "---- results ----", null);
bsf_monitor.log("ERROR", results.toString(), null);
```

```
LinkedHashMap<String, Number> times = times;
bsf_monitor.log("ERROR", "---- times ----", null);
bsf_monitor.log("ERROR", times.toString(), null);
// reading a parameter from the service definition
String myParameter = myParameter;
bsf monitor.log("ERROR", "---- myParameter ----", null);
bsf monitor.log("ERROR", myParameter, null);
// minimal example
def testFile = new File("/tmp/TestFile");
if (testFile.exists()) {
  bsf_monitor.log("ERROR", "Done MinimalGroovy ---- OK ----", null);
  return "OK";
} else {
  results.put("reason", "file does not exist");
  bsf_monitor.log("ERROR", "Done MinimalGroovy ---- NOK ----", null);
  return "NOK";
}
```

5.6.7. CiscoIpSlaMonitor

This monitor can be used to monitor IP SLA configurations on your Cisco devices. This monitor supports the following SNMP OIDS from CISCO-RTT-MON-MIB:

```
RTT_ADMIN_TAG_OID = .1.3.6.1.4.1.9.9.42.1.2.1.1.3
RTT_OPER_STATE_OID = .1.3.6.1.4.1.9.9.42.1.2.9.1.10
RTT_LATEST_OPERSENSE_OID = .1.3.6.1.4.1.9.9.42.1.2.10.1.2
RTT_ADMIN_THRESH_OID = .1.3.6.1.4.1.9.9.42.1.2.1.1.5
RTT_ADMIN_TYPE_OID = .1.3.6.1.4.1.9.9.42.1.2.1.1.4
RTT_LATEST_OID = .1.3.6.1.4.1.9.9.42.1.2.10.1.1
```

The monitor can be run in two scenarios. The first one tests the *RTT_LATEST_OPERSENSE* which is a sense code for the completion status of the latest RTT operation. If the *RTT_LATEST_OPERSENSE* returns *ok(1)* the service is marked as *up*.

The second scenario is to monitor the configured threshold in the *IP SLA* config. If the *RTT_LATEST_OPERSENSE* returns with *overThreshold(3)* the service is marked *down*.

Monitor facts

Class Name	<pre>org.opennms.netmgt.poller.monitors.CiscoIpSlaMonitor</pre>
Remote Enabled	false

Configuration and Usage

Parameter	Description	Requir ed	Default value
admin-tag	The tag attribute from your <i>IP SLA</i> configuration you want to monitor.	require d	-
ignore- thresh	Boolean indicates if just the status or configured threshold should be monitored.	require d	

Table 17. Monitor-specific parameters for the CiscoIpSlaMonitor

This monitor implements the Common Configuration Parameters.

Example for HTTP and ICMP echo reply

In this example we configure an IP SLA entry to monitor Google's website with *HTTP GET* from the Cisco device. We use 8.8.8.8 as our DNS resolver. In our example our SLA says we should reach Google's website within 200ms. To advise co-workers that this monitor entry is used for monitoring, I set the owner to *OpenNMS*. The tag is used to identify the entry later in the SNMP table for monitoring.

Cisco device configuration for IP SLA instance for HTTP GET

```
ip sla monitor 1
type http operation get url http://www.google.de name-server 8.8.8.8
timeout 3000
threshold 200
owner OpenNMS
tag Google Website
ip sla monitor schedule 3 life forever start-time now
```

In the second example we configure a IP SLA to test if the IP address from www.opennms.org is reachable with ICMP from the perspective of the Cisco device. Like the example above we have a threshold and a timeout.

Cisco device configuration for IP SLA instance for ICMP monitoring.

```
ip sla 1
icmp-echo 64.146.64.212
timeout 3000
threshold 150
owner OpenNMS
tag OpenNMS Host
ip sla schedule 1 life forever start-time now
```



It's not possible to reconfigure an IP SLA entry. If you want to change parameters, you have to delete the whole configuration and reconfigure it with your new parameters. Backup your Cisco configuration manually or take a look at RANCID.

To monitor both of the entries the configuration in poller-configuration.xml requires two service definition entries:

```
<service name="IP-SLA-WEB-Google" interval="300000"</pre>
 user-defined="false" status="on">
    <parameter key="retry" value="2" />
    <parameter key="timeout" value="3000" />
    <parameter key="admin-tag" value="Google Website" />
    <parameter key="ignore-thresh" value="false" />①
</service>
<service name="IP-SLA-PING-OpenNMS" interval="300000"</pre>
 user-defined="false" status="on">
    <parameter key="retry" value="2" />
    <parameter key="timeout" value="3000" />
    <parameter key="admin-tag" value="OpenNMS Host" />
    <parameter key="ignore-thresh" value="true" />②
</service>
<monitor service="IP-SLA-WEB-Google" class-name=</pre>
"org.opennms.netmgt.poller.monitors.CiscoIpSlaMonitor" />
<monitor service="IP-SLA-PING-OpenNMS" class-name=
"org.opennms.netmgt.poller.monitors.CiscoIpSlaMonitor" />
```

① Service is *up* if the IP SLA state is *ok(1)*

② Service is *down* if the IP SLA state is *overThreshold(3)*

5.6.8. CiscoPingMibMonitor

This poller monitor's purpose is to create conceptual rows (entries) in the *ciscoPingTable* on *Cisco IOS* devices that support the CISCO-PING-MIB. These entries direct the remote *IOS* device to ping an IPv4 or IPv6 address with a configurable set of parameters. After the *IOS* device has completed the requested ping operations, the poller monitor queries the *IOS* device to determine the results. If the results indicate success according to the configured parameters in the service configuration, then the monitored service is reported as available and the results are available for optional time-series (RRD) storage. If the results indicate failure, the monitored service is reported unavailable with a descriptive reason code. If something goes wrong during the setup of the entry or the subsequent querying of its status, the monitored service is reported to be in an *unknown* state.

Unlike most poller monitors, the CiscoPingMibMonitor does not interpret the
timeout and retries parameters to determine when a poll attempt has timed out or
whether it should be attempted again. The packet-count and packet-timeout
parameters instead service this purpose from the perspective of the remote IOS
device.

ciscoPingEntry	1.3.6.1.4.1.9.9.16.1.1.1
ciscoPingSerialNumber	1.3.6.1.4.1.9.9.16.1.1.1.1
ciscoPingProtocol	1.3.6.1.4.1.9.9.16.1.1.1.2
ciscoPingAddress	1.3.6.1.4.1.9.9.16.1.1.1.3
ciscoPingPacketCount	1.3.6.1.4.1.9.9.16.1.1.1.4
ciscoPingPacketSize	1.3.6.1.4.1.9.9.16.1.1.1.5
ciscoPingPacketTimeout	1.3.6.1.4.1.9.9.16.1.1.1.6
ciscoPingDelay	1.3.6.1.4.1.9.9.16.1.1.1.7
ciscoPingTrapOnCompletion	1.3.6.1.4.1.9.9.16.1.1.1.8
ciscoPingSentPackets	1.3.6.1.4.1.9.9.16.1.1.1.9
ciscoPingReceivedPackets	1.3.6.1.4.1.9.9.16.1.1.1.10
ciscoPingMinRtt	1.3.6.1.4.1.9.9.16.1.1.1.11
ciscoPingAvgRtt	1.3.6.1.4.1.9.9.16.1.1.1.12
ciscoPingMaxRtt	1.3.6.1.4.1.9.9.16.1.1.1.13
ciscoPingCompleted	1.3.6.1.4.1.9.9.16.1.1.1.14
ciscoPingEntryOwner	1.3.6.1.4.1.9.9.16.1.1.1.15
ciscoPingEntryStatus	1.3.6.1.4.1.9.9.16.1.1.1.16
ciscoPingVrfName	1.3.6.1.4.1.9.9.16.1.1.1.17

Prerequisites

- One or more *Cisco* devices running an *IOS* image of recent vintage; any 12.2 or later image is probably fine. Even very low-end devices appear to support the CISCO-PING-MIB.
- The *IOS* devices that will perform the remote pings must be configured with an *SNMP write community* string whose source address access-list includes the address of the OpenNMS Meridian server and whose MIB view (if any) includes the OID of the *ciscoPingTable*.
- The corresponding *SNMP write community* string must be specified in the write-community attribute of either the top-level <snmp-config> element of snmp-config.xml or a <definition> child element that applies to the *SNMP-primary* interface of the *IOS* device(s) that will perform the remote pings.

Scalability concerns

This monitor spends a fair amount of time sleeping while it waits for the remote *IOS* device to complete the requested ping operations. The monitor is pessimistic in calculating the delay between creation of the *ciscoPingTable* entry and its first attempt to retrieve the results of that entry's ping operations — it will always wait at least (packet-count * (packet-timeout + packet-delay)) milliseconds before even checking whether the remote pings have completed. It's therefore prone to hogging poller threads if used with large values for the packet-count, packet-timeout, and/or packet-delay parameters. Keep these values as small as practical to avoid tying up poller threads unnecessarily.

This monitor always uses the current time in whole seconds since the UNIX epoch as the instance identifier of the *ciscoPingTable* entries that it creates. The object that holds this identifier is a signed 32-bit integer type, precluding a finer resolution. It's probably a good idea to mix in the least-significant byte of the millisecond-accurate time as a substitute for that of the whole-second-

accurate value to avoid collisions. *IOS* seems to clean up entries in this table within a manner of minutes after their ping operations have completed.

Monitor facts

Class Name	org.opennms.netmgt.poller.monitors.CiscoPingMibMonitor
Remote Enabled	false

Configuration and Usage

Parameter	Description	Requ ired	Default value
version	SNMP protocol version (1, 2c, or 3) to use for operations performed by this service monitor. Do not use with out a very good reason to do so.	optio nal	from snmp- config.xml
packet-count	Number of ping packets that the remote <i>IOS</i> device should send.	optio nal	5
packet-size	Size, in bytes, of each ping packet that the remote <i>IOS</i> device should send.	optio nal	100
packet-timeout	Timeout, in milliseconds, of each ping packet sent by the remote <i>IOS</i> device.	optio nal	2000
packet-delay	Delay, in milliseconds, between ping packets sent by the remote <i>IOS</i> device.	optio nal	0
entry-owner	String value to set as the value of ciscoPingEntryOwner of entries created for this service.	optio nal	OpenNMS CiscoPingMibMo nitor
vrf-name	String value to set as the VRF (VLAN) name in whose context the remote <i>IOS</i> device should perform the pings for this service.	optio nal	empty String
proxy-node-id	Numeric database identifier of the node whose primary SNMP interface should be used as the <i>proxy</i> for this service. If specified along with the related proxy-node-foreign-source, proxy-node- foreign-id, and/or proxy-ip-addr, this parameter will be the effective one.	optio nal	-

Table 18. Monitor specific parameters for the CiscoPingMibMonitor

Parameter	Description	Requ ired	Default value
proxy-node-foreign- source proxy-node-foreign-id	foreign-source name and foreign-ID of the node whose primary SNMP interface should be used as the "proxy" for this service. These two parameters are corequisites. If they appear along with the related proxy-ip-addr , these parameters will be the effective ones.	optio nal	-
proxy-ip-addr	IP address of the interface that should be used as the <i>proxy</i> for this service. Effective only if none of proxy-node-id , proxy-node-foreign-source , nor proxy-node-foreign-id appears alongside this parameter. A value of \${ipaddr} will be substituted with the IP address of the interface on which the monitored service appears.	optio nal	-
target-ip-addr	IP address that the remote <i>IOS</i> device should ping. A value of \${ipaddr} will be substituted with the IP address of the interface on which the monitored service appears.	optio nal	-
success-percent	A whole-number percentage of pings that must succeed (from the perspective of the remote <i>IOS</i> device) in order for this service to be considered available. As an example, if packet-count is left at its default value of 5 but you wish the service to be considered available even if only one of those five pings is successful, then set this parameter's value to 20.	optio nal	100
rrd-repository	Base directory of an RRD repository in which to store this service monitor's response-time samples	optio nal	-
ds-name	Name of the RRD datasource (DS) name in which to store this service monitor's response-time samples; rrd-base-name Base name of the RRD file (minus the .rrd or .jrb file extension) within the specified rrd-repository path in which this service monitor's response-time samples will be persisted	optio nal	-

This monitor implements the Common Configuration Parameters.

This is optional just if you can use variables in the configuration.

Table 19. Variables which can be used in the configuration

Variabl e	Description
\${ipaddr }	This value will be substituted with the IP address of the interface on which the monitored service appears.

Example: Ping the same non-routable address from all routers of customer Foo

A service provider's client, Foo Corporation, has network service at multiple locations. At each Foo location, a point-of-sale system is statically configured at IPv4 address 192.168.255.1. Foo wants to be notified any time a point-of-sale system becomes unreachable. Using an OpenNMS Meridian remote location monitor is not feasible. All of Foo Corporation's CPE routers must be *Cisco IOS* devices in order to achieve full coverage in this scenario.

One approach to this requirement is to configure all of Foo Corporation's premise routers to be in the surveillance categories Customer_Foo, CPE, and Routers, and to use a filter to create a poller package that applies only to those routers. We will use the special value *\${ipaddr}* for the proxy-ip-addr parameter so that the remote pings will be provisioned on each Foo CPE router. Since we want each Foo CPE router to ping the same IP address 192.168.255.1, we statically list that value for the target-ip-addr address.

```
<package name="ciscoping-foo-pos">
 <filter>catincCustomer_Foo & catincCPE & catincRouters & nodeSysOID LIKE
'.1.3.6.1.4.1.9.%'</filter>
 <include-range begin="0.0.0.0" end="254.254.254.254" />
 <rrd step="300">
    <rra>RRA: AVERAGE: 0.5:1:2016</rra>
    <rra>RRA:AVERAGE:0.5:12:1488</rra>
    <rra>RRA: AVERAGE: 0.5:288:366</rra>
    <rra>RRA:MAX:0.5:288:366</rra>
    <rra>RRA:MIN:0.5:288:366</rra>
 </rrd>
 <service name="FooPOS" interval="300000" user-defined="false" status="on">
    <parameter key="rrd-repository" value="/opt/opennms/share/rrd/response" />
    <parameter key="rrd-base-name" value="ciscoping" />
    <parameter key="ds-name" value="ciscoping" />
    <parameter key="proxy-ip-addr" value="${ipaddr}" />
    <parameter key="target-ip-addr" value="192.168.255.1" />
 </service>
 <downtime interval="30000" begin="0" end="300000" /><!-- 30s, 0, 5m -->
 <downtime interval="300000" begin="300000" end="43200000" /><!-- 5m, 5m, 12h -->
 <downtime interval="600000" begin="43200000" end="432000000" /><!-- 10m, 12h, 5d -->
 <downtime begin="432000000" delete="true" /><!-- anything after 5 days delete -->
</package>
<monitor service="FooPOS" class-name=
"org.opennms.netmgt.poller.monitors.CiscoPingMibMonitor" />
```

Example: Ping from a single IOS device routable address of each router of customer Bar

A service provider's client, Bar Limited, has network service at multiple locations. While OpenNMS Meridian' world-class service assurance is generally sufficient, Bar also wants to be notified any time a premise router at one of their locations unreachable from the perspective of an *IOS* device in Bar's main data center. Some or all of the Bar Limited CPE routers may be non-Cisco devices in this scenario.

To meet this requirement, our approach is to configure Bar Limited's premise routers to be in the surveillance categories Customer_Bar, CPE, and Routers, and to use a filter to create a poller package that applies only to those routers. This time, though, we will use the special value \${ipaddr} not in the proxy-ip-addr parameter but in the target-ip-addr parameter so that the remote pings will be performed for each Bar CPE router. Since we want the same *IOS* device 20.11.5.11 to ping the CPE routers, we statically list that value for the proxy-ip-addr address. Example poller-configuration.xml additions

```
<package name="ciscoping-bar-cpe">
 <filter>catincCustomer Bar & catincCPE & catincRouters</filter>
 <include-range begin="0.0.0.0" end="254.254.254.254" />
 <rrd step="300">
    <rra>RRA:AVERAGE:0.5:1:2016</rra>
    <rra>RRA: AVERAGE: 0.5:12:1488</rra>
    <rra>RRA: AVERAGE: 0.5:288:366</rra>
   <rra>RRA:MAX:0.5:288:366</rra>
   <rra>RRA:MIN:0.5:288:366</rra>
 </rrd>
 <service name="BarCentral" interval="300000" user-defined="false" status="on">
    <parameter key="rrd-repository" value="/opt/opennms/share/rrd/response" />
    <parameter key="rrd-base-name" value="ciscoping" />
    <parameter key="ds-name" value="ciscoping" />
    <parameter key="proxy-ip-addr" value="20.11.5.11" />
    <parameter key="target-ip-addr" value="${ipaddr}" />
 </service>
 <downtime interval="30000" begin="0" end="300000" /><!-- 30s, 0, 5m -->
 <downtime interval="300000" begin="300000" end="43200000" /><!-- 5m, 5m, 12h -->
 <downtime interval="600000" begin="43200000" end="432000000" /><!-- 10m, 12h, 5d -->
 <downtime begin="432000000" delete="true" /><!-- anything after 5 days delete -->
</package>
<monitor service="BarCentral" class-name=
"org.opennms.netmgt.poller.monitors.CiscoPingMibMonitor" />
```

5.6.9. CitrixMonitor

This monitor is used to test if a Citrix® Server or XenApp Server® is providing the *Independent Computing Architecture (ICA)* protocol on TCP 1494. The monitor opens a TCP socket and tests the greeting banner returns with ICA, otherwise the service is unavailable.

Monitor facts

Class Name	org.opennms.netmgt.poller.monitors.CitrixMonitor
Remote Enabled	true

Configuration and Usage

Table 20. Monitor specific parameters for the CitrixMonitor

Paramete	Description	Require	Default
r		d	value
port	TCP port where the <i>ICA</i> protocol is listening.	optional	1494

This monitor implements the Common Configuration Parameters.



If you have configure the *Metaframe Presentation Server Client* using *Session Reliability*, the TCP port is 2598 instead of 1494. You can find additional information on CTX104147. It is not verified if the monitor works in this case.

Examples

The following example configures *OpenNMS Meridian* to monitor the ICA protocol on TCP 1494 with 2 retries and waiting 5 seconds for each retry.

5.6.10. DhcpMonitor

This monitor is used to check the availability and functionality of DHCP servers. The monitor class *DhcpMonitor* is executed by *Pollerd* and opens the background process listening for incoming DHCP responses. A DHCP server is tested by sending a *DISCOVER* message. If the DHCP server responds with an *OFFER* the service is marked as up. The background listening process is only started if the *DhcpMonitor* is used. The behavior for testing the DHCP server can be modified in the *poller-configuration.xml* configuration file.



Make sure no DHCP client is running on the *OpenNMS Meridian* server and using port UDP/67 and UDP/68. If UDP/67 and UDP/68 are already in use, you will find warning messages in your log files. You can test if a process is listening on UDP/68 with sudo ss -lnpu sport = :68.

Monitor facts

Class Name org.opennms.netmgt.poller.monitors.DhcpMonitor

Remote Enabled true

This monitor implements the Common Configuration Parameters.

DhcpMonitor configuration

Table 21. DhcpMonitor parameters in poller-co	:0NT1	guration.xmL.
---	-------	---------------

Parameter	Description	Requi red	Default value
macAddress	The MAC address which OpenNMS Meridian uses for a dhcp request	optio nal	00:06:0D:BE:9C:B2
relayMode	Puts the poller in relay mode	optio nal	false
myIpAddres s	This parameter will usually be set to the IP address of the OpenNMS Meridian server, if relayMode is set to true. In relay mode, the DHCP server being polled will unicast its responses directly back to the IP address specified by myIpAddress rather than broadcasting its responses. This allows DHCP servers to be polled even though they are not on the same subnet as the OpenNMS Meridian server, and without the aid of an external relay.	optio nal	127.0.0.1
extendedMo de	When extendedMode is false, the DHCP poller will send a DISCOVER and expect an OFFER in return. When extendedMode is true, the DHCP poller will first send a DISCOVER. If no valid response is received it will send an INFORM. If no valid response is received it will then send a REQUEST. OFFER, ACK, and NAK are all considered valid responses in extendedMode.	optio nal	false
requestIpA ddress	This parameter only applies to REQUEST queries sent to the DHCP server when extendedMode is true. The IP address specified will be requested in the query.	optio nal	127.0.0.1
rrd- repository	The location to write RRD data. Generally, you will not want to change this from default	requi red	\$OPENNMS_HOME/share /rrd/response
rrd-base- name	The name of the RRD file to write (minus the extension, .rrd or .jrb)	requi red	dhcp
ds-name	This is the name as reference for this particular data source in the RRD file	requi red	dhcp




Figure 28. Visualization of DHCP message flow in broadcast mode




Figure 29. Visualization of DHCP message flow in relay mode

Example testing DHCP server in the same subnet

Example configuration how to configure the monitor in the **poller-configuration.xml**. The monitor will try to send in maximum 3 *DISCOVER* messages and waits 3 seconds for the DHCP server *OFFER* message.

Configure a DHCP service in poller-configuration.xml

```
<service name="DHCP" interval="300000" user-defined="false" status="on">
<parameter key="retry" value="2" />
<parameter key="timeout" value="3000" />
<parameter key="relayMode" value="false"/>
<parameter key="relayMode" value="false"/>
<parameter key="rrd-repository" value="/opt/opennms/share/rrd/response" />
<parameter key="rrd-base-name" value="dhcp" />
<parameter key="ds-name" value="dhcp" />
</service>
<monitor service="DHCP" class-name="org.opennms.netmgt.poller.monitors.DhcpMonitor"/>
```

Example testing DHCP server in a different subnet in extended mode

You can use the same monitor in poller-configuration.xml as in the example above.

Configure DhcpMonitor to test DHCP server in a different subnet. The OFFER from the DHCP server is sent to myIpAddress.

```
<service name="DHCP" interval="300000" user-defined="false" status="on">
  <parameter key="retry" value="2" />
  <parameter key="timeout" value="3000" />
  <parameter key="relayMode" value="false"/>
  <parameter key="relayMode" value="false"/>
  <parameter key="extendedMode" value="false"/>
  <parameter key="myIpAddress" value="1.2.3.4"/>
  <parameter key="rrd-repository" value="/opt/opennms/share/rrd/response" />
  <parameter key="rd-base-name" value="dhcp" />
```

<monitor service="DHCP" class-name="org.opennms.netmgt.poller.monitors.DhcpMonitor"/>



If in extendedMode, the time required to complete the poll for an unresponsive node is increased by a factor of 3. Thus it is a good idea to limit the number of retries to a small number.

5.6.11. DiskUsageMonitor

The DiskUsageMonitor monitor can be used to test the amount of free space available on certain storages of a node. The monitor gets information about the available free storage spaces available by inspecting the *hrStorageTable* of the HOST-RESOURCES-MIB. A storage's description (as found in the corresponding *hrStorageDescr* object) must match the criteria specified by the disk and match-type parameters to be monitored. A storage's available free space is calculated using the corresponding *hrStorageSize* and *hrStorageUsed* objects.



The *hrStorageUsed* doesn't account for filesystem reserved blocks (i.e. for the super-user), so DiskUsageMonitor will report the service as unavailable only when the amount of free disk space is actually lower than **free** minus the percentage of reserved filesystem blocks.

This monitor uses *SNMP* to accomplish its work. Therefore systems against which it is to be used must have an SNMP agent supporting the *HOST-RESOURCES-MIB* installed and configured. Most modern *SNMP agents*, including most distributions of the *Net-SNMP agent* and the *SNMP service* that ships with *Microsoft Windows*, support this *MIB*. Out-of-box support for *HOST-RESOURCES-MIB* among commercial *Unix* operating systems may be somewhat spotty.

Monitor facts

Class Name	org.opennms.netmgt.poller.monitors.DiskUsageMonitor
------------	---

Configuration and Usage

Param eter	Description	Requi red	Default value
disk	A pattern that a storage's description (<i>hrStorageDescr</i>) must match to be taken into account.	requir ed	-
free	The minimum amount of free space that storages matching the criteria must have available. This parameter is evaluated as a percent of the storage's reported maximum capacity.		15
match- type	The way how the pattern specified by the disk parameter must be compared to storages description Must be one of the following symbolic operators: endswith : The disk parameter's value is evaluated as a string that storages' description must end with; exact : The disk parameter's value is evaluated as a string that storages" description must exactly match; regex : The disk parameter's value is evaluated as a regular expression that storages' description must match; startswith : The disk parameter's value is evaluated as a string that storages' description must start with. Note: Comparisons are case-sensitive	option al	exact
port	Destination port where the SNMP requests shall be sent.	option al	from snmp- config.xml
retries	Deprecated. Same as retry. Parameter retry takes precedence when both are set.	option al	from snmp- config.xml

Table 22. Monitor specific parameters for the DiskUsageMonitor

This monitor implements the Common Configuration Parameters.

Examples

DiskUsageMonitor vs thresholds

Storages' available free space can also be monitored using thresholds if you are already collecting these data.

5.6.12. DnsMonitor

This monitor is build to test the availability of the *DNS service* on remote IP interfaces. The monitor tests the service availability by sending a DNS query for A resource record types against the DNS server to test.

The monitor is marked as *up* if the *DNS Server* is able to send a valid response to the monitor. For multiple records it is possible to test if the number of responses are within a given boundary.

The monitor can be simulated with the command line tool host:

```
~ % host -v -t a www.google.com 8.8.8.8
Trying "www.google.com"
Using domain server:
Name: 8.8.8.8
Address: 8.8.8.8#53
Aliases:
;; ->>HEADER<<- opcode: QUERY, status: NOERROR, id: 9324
;; flags: qr rd ra; QUERY: 1, ANSWER: 5, AUTHORITY: 0, ADDITIONAL: 0
;; QUESTION SECTION:
;www.google.com.
                           TN A
;; ANSWER SECTION:
www.google.com.
                               74.125.232.17
                   283 IN A
www.google.com.
                 283 IN A 74.125.232.20
www.google.com.
                               74.125.232.19
                  283 IN A
                   283 IN A
www.google.com.
                               74.125.232.16
www.google.com.
                 283 IN A 74.125.232.18
Received 112 bytes from 8.8.8.8#53 in 41 ms
```

TIP: This monitor is intended for testing the availability of a DNS service. If you want to monitor the DNS resolution of some of your nodes from a client's perspective, please use the DNSResolutionMonitor.

Monitor facts

Class Name	org.opennms.netmgt.poller.monitors.DnsMonitor
Remote Enabled	true

Configuration and Usage

Parameter	Description	Requi red	Default value
retry	Number of retries before the service is marked as <i>down</i>	option al	0
timeout	Time in milliseconds to wait for the <i>A Record</i> response from the server	option al	5000
port	UDP Port for the DNS server	option al	53
lookup	DNS <i>A Record</i> for lookup test	option al	localhost
fatal- response- codes	A comma-separated list of numeric DNS response codes that will be considered fatal if present in the server's response. Default value is 2 corresponds to <i>Server Failed</i> . A list of codes and their meanings is found in RFC 2929	option al	2
min-answers	Minmal number of records in the DNS server respone for the given lookup	option al	-
max-answers	Maximal number of records in the DNS server respone for the given lookup	option al	-

Table 23. Monitor specific parameters for the DnsMonitor

This monitor implements the Common Configuration Parameters.

Examples

The given examples shows how to monitor if the IP interface from a given DNS server resolves a DNS request. This service should be bound to a DNS server which should be able to give a valid DNS respone for DNS request *www.google.com*. The service is *up* if the DNS server gives between 1 and 10 *A record* responses.

Example configuration monitoring DNS request for a given server for www.google.com

```
<service name="DNS-www.google.com" interval="300000" user-defined="false" status="on">
        <parameter key="lookup" value="www.google.com" />
        <parameter key="fatal-response-code" value="2" />
        <parameter key="min-answers" value="1" />
        <parameter key="max-answers" value="10" />
        </service>
```

5.6.13. DNSResolutionMonitor

The DNS resolution monitor, tests if the node label of an OpenNMS Meridian node can be resolved. This monitor uses the name resolver configuration from the poller configuration or from the operating system where OpenNMS Meridian is running on. It can be used to test a client behavior for a given host name. For example: Create a node with the node label www.google.com and an IP interface. Assigning the DNS resolution monitor on the IP interface will test if www.google.com can be resolved using the DNS configuration defined by the poller. The response from the A record lookup can be any address, it is not verified with the IP address on the OpenNMS Meridian IP interface where the monitor is assigned to. This monitor implements placeholder substitution in parameter values.

Monitor facts

Class Name	org.opennms.netmgt.poller.monitors.DNSResolutionMonitor
Remote Enabled	true

Configuration and Usage

Param eter	Description	Req uire d	Default value	Placehold er substituti on
resolut ion- type	Type of record for the node label test. Allowed values v4 for <i>A records</i> , v6 for <i>AAAA record</i> , both <i>A</i> and <i>AAAA record</i> must be available, either <i>A</i> or <i>AAAA record</i> must be available.	nal	either	No
record- types	Alternate DNS record types to search for. The comma separated list can contain A, AAAA, CNAME, NS, MX, PTR, SOA, SRV, or TXT.	optio nal	* *	No
lookup	Alternate DNS record to lookup	optio nal	The node label.	Yes
nameser Ver	The DNS server to query for the records. The string can be in the form of hostname, hostname:port, or [ipv6address]:port.	-	Use name server from host system running <i>OpenNMS</i> <i>Meridian</i>	Yes

Table 24. Monitor specific parameters for the DNSResolutionMonitor

This monitor implements the Common Configuration Parameters.

Examples

The following example shows the possibilities monitoring IPv4 and/or IPv6 for the service configuration:

```
<!-- Assigned service test if the node label is resolved for an A record -->
<service name="DNS-Resolution-v4" interval="300000" user-defined="false" status="on">
    <parameter key="retry" value="2"/>
    <parameter key="timeout" value="2000"/>
    <parameter key="resolution-type" value="v4"/>
    <parameter key="rrd-repository" value="/opt/opennms/share/rrd/response"/>
    <parameter key="rrd-base-name" value="dns-res-v4"/>
    <parameter key="ds-name" value="dns-res-v4"/>
</service>
<!-- Assigned service test if www.google.com is resolved for an A record -->
<service name="DNS-Resolution-v4-lookup" interval="300000" user-defined="false"</pre>
status="on">
    <parameter key="retry" value="2"/>
    <parameter key="timeout" value="2000"/>
    <parameter key="resolution-type" value="v4"/>
    <parameter key="lookup" value="www.google.com"/>
</service>
<!-- Assigned service test if the node label is resolved for an AAAA record using a
specific DNS server -->
<service name="DNS-Resolution-v6" interval="300000" user-defined="false" status="on">
    <parameter key="retry" value="2"/>
    <parameter key="timeout" value="2000"/>
    <parameter key="resolution-type" value="v6"/>
    <parameter key="rrd-repository" value="/opt/opennms/share/rrd/response"/>
    <parameter key="rrd-base-name" value="dns-res-v6"/>
    <parameter key="ds-name" value="dns-res-v6"/>
    <parameter key="nameserver" value="8.8.8.8"/>
</service>
<!-- Use parameter substitution for nameserver and lookup parameter values -->
<service name="DNS-Resolution-Sub" interval="300000" user-defined="false" status="on">
    <parameter key="retry" value="2"/>
    <parameter key="timeout" value="2000"/>
    <parameter key="resolution-type" value="v6"/>
    <parameter key="rrd-repository" value="/opt/opennms/share/rrd/response"/>
    <parameter key="rrd-base-name" value="dns-res-v6"/>
    <parameter key="ds-name" value="dns-res-v6"/>
    <parameter key="nameserver" value="{ipAddr}"/>
    <parameter key="lookup" value="{nodeLabel}"/>
</service>
<!-- Assigned service test if the node label is resolved for an AAAA record AND A
record -->
<service name="DNS-Resolution-v4-and-v6" interval="300000" user-defined="false"</pre>
```

```
status="on">
    <parameter key="retry" value="2"/>
    <parameter key="timeout" value="2000"/>
    <parameter key="resolution-type" value="both"/>
    <parameter key="rrd-repository" value="/opt/opennms/share/rrd/response"/>
    <parameter key="rrd-base-name" value="dns-res-both"/>
    <parameter key="ds-name" value="dns-res-both"/>
</service>
<!-- Assigned service test if the node label is resolved for an AAAA record OR A
record -->
<service name="DNS-Resolution-v4-or-v6" interval="300000" user-defined="false" status</pre>
="on">
    <parameter key="retry" value="2"/>
    <parameter key="timeout" value="2000"/>
    <parameter key="resolution-type" value="either"/>
    <parameter key="rrd-repository" value="/opt/opennms/share/rrd/response"/>
    <parameter key="rrd-base-name" value="dns-res-either"/>
    <parameter key="ds-name" value="dns-res-either"/>
</service>
<!-- Assigned service test if the node label is resolved for an CNAME record AND MX
record -->
<service name="DNS-Resolution-CNAME-and-MX" interval="300000" user-defined="false"</pre>
status="on">
    <parameter key="retry" value="2"/>
    <parameter key="timeout" value="2000"/>
    <parameter key="record-types" value="CNAME,MX"/>
    <parameter key="lookup" value="www.google.comm"/>
    <parameter key="rrd-repository" value="/opt/opennms/share/rrd/response"/>
    <parameter key="rrd-base-name" value="dns-res-cname-mx"/>
    <parameter key="ds-name" value="dns-res-cname-mx"/>
</service>
<monitor service="DNS-Resolution-v4" class-name=
"org.opennms.netmgt.poller.monitors.DNSResolutionMonitor" />
<monitor service="DNS-Resolution-v4-lookup" class-name=</pre>
"org.opennms.netmgt.poller.monitors.DNSResolutionMonitor" />
<monitor service="DNS-Resolution-v6" class-name=
"org.opennms.netmgt.poller.monitors.DNSResolutionMonitor" />
<monitor service="DNS-Resolution-Sub" class-name=
"org.opennms.netmgt.poller.monitors.DNSResolutionMonitor" />
<monitor service="DNS-Resolution-v4-and-v6" class-name=</pre>
"org.opennms.netmgt.poller.monitors.DNSResolutionMonitor" />
<monitor service="DNS-Resolution-v4-or-v6" class-name=
"org.opennms.netmgt.poller.monitors.DNSResolutionMonitor" />
<monitor service="DNS-Resolution-CNAME-and-MX" class-name=
"org.opennms.netmgt.poller.monitors.DNSResolutionMonitor" />
```

To have response time graphs for the name resolution you have to configure RRD graphs for the

given ds-names (dns-res-v4, dns-res-v6, dns-res-both, dns-res-either, dns-res-cname-mx) in '\$OPENNMS_HOME/etc/response-graph.properties'.

DNSResolutionMonitor vs DnsMonitor

The DNSResolutionMonitor is used to measure the availability and record outages of a name resolution from client perspective. The service is mainly used for websites or similar public available resources. It can be used in combination with the Page Sequence Monitor to give a hint if a website isn't available for DNS reasons.

The DnsMonitor on the other hand is a test against a specific DNS server. In OpenNMS Meridian the DNS server is the node and the DnsMonitor will send a lookup request for a given A record to the DNS server IP address. The service goes down if the DNS server doesn't have a valid A record in his zone database or as some other issues resolving A records.

5.6.14. FtpMonitor

The FtpMonitor is able to validate ftp connection dial-up processes. The monitor can test ftp server on multiple ports and specific login data.

The service using the FtpMonitor is *up* if the FTP server responds with return codes between 200 and 299. For special cases the service is also marked as *up* for 425 and 530.

This monitor implements placeholder substitution in parameter values.

Monitor facts

Class Name	org.opennms.netmgt.poller.monitors.FtpMonitor
Remote Enabled	true

Configuration and Usage

Table 25. Monitor specific parameters for the FtpMonitor.

Param eter	Description	Requi red	Default value	Placeholder substitution
retry	Number of attempts to get a valid FTP response/response-text	optio nal	0	No
port	A list of TCP ports to which connection shall be tried.	optio nal	20,21	No
passwo rd	This parameter is meant to be used together with the userid parameter to perform authentication. This parameter specifies the password to be used.	optio nal	empty string	Yes
userid	This parameter is meant to be used together with the password parameter to perform authentication. This parameter specifies the user ID to be used.	optio nal	-	Yes

This monitor implements the Common Configuration Parameters.

Examples

Some example configuration how to configure the monitor in the 'poller-configuration.xml'

```
<service name="FTP" interval="300000" user-defined="false" status="on">
<parameter key="retry" value="1"/>
<parameter key="timeout" value="3000"/>
<parameter key="port" value="21"/>
<parameter key="userid" value=""/>
<parameter key="password" value=""/>
</service>
<service name="FTP-With-Auth-From-Asset" interval="300000" user-defined="false"</pre>
status="on">
<parameter key="retry" value="1"/>
<parameter key="timeout" value="3000"/>
<parameter key="port" value="21"/>
<parameter key="userid" value="{username}"/>
<parameter key="password" value="{password}"/>
</service>
<service name="FTP-Customer" interval="300000" user-defined="false" status="on">
<parameter key="retry" value="1"/>
<parameter key="timeout" value="3000"/>
<parameter key="port" value="21"/>
<parameter key="userid" value="Customer"/>
<parameter key="password" value="MySecretPassword"/>
</service>
<monitor service="FTP" class-name="org.opennms.netmgt.poller.monitors.FtpMonitor"/>
<monitor service="FTP-With-Auth-From-Asset" class-name=
"org.opennms.netmgt.poller.monitors.FtpMonitor"/>
<monitor service="FTP-Customer" class-name=
"org.opennms.netmgt.poller.monitors.FtpMonitor"/>
```

Hint

Comment from FtpMonitor source

Also want to accept the following ERROR message generated by some FTP servers following a QUIT command without a previous successful login: "530 QUIT : User not logged in. Please login with USER and PASS first."

Also want to accept the following ERROR message generated by some FTP servers following a QUIT command without a previously successful login: "425 Session is disconnected."

See also: http://tools.ietf.org/html/rfc959

5.6.15. HostResourceSwRunMonitor

This monitor test the running state of one or more processes. It does this via SNMP by inspecting the *hrSwRunTable* of the HOST-RESOURCES-MIB. The test is done by matching a given process as *hrSwRunName* against the numeric value of the *hrSwRunState*.

This monitor uses *SNMP* to accomplish its work. Therefore systems against which it is to be used must have an SNMP agent installed and configured. Furthermore, the *SNMP agent* on the system must support the *HOST-RESOURCES-MIB*. Most modern *SNMP agents*, including most distributions of the *Net-SNMP agent* and the *SNMP service* that ships with *Microsoft Windows*, support this *MIB*. Out-of-box support for *HOST-RESOURCES-MIB* among commercial *Unix* operating systems may be somewhat spotty.

Monitor facts

Class Name	org.opennms.netmgt.poller.monitors.HostResourceSwRunMonitor
Remote Enabled	false

Configuration and Usage

Parameter	Description	Requi red	Default value
port	The port of the SNMP agent of the server to test.	option al	from snmp- config.xml
service- name	The name of the process to be monitored. This parameter's value is case-sensitive and is evaluated as an exact match.	requir ed	-
match-all	If the process name appears multiple times in the <i>hrSwRunTable</i> , and this parameter is set to true, then all instances of the named process must match the value specified for run-level.	option al	false
run-level	The maximum allowable value of <i>hrSWRunStatus</i> among <i>running(1)</i> , <i>runnable(2)</i> = waiting for resource <i>notRunnable(3)</i> = loaded but waiting for event <i>invalid(4)</i> = not loaded	option al	2
service- name-oid	The numeric object identifier (OID) from which process names are queried. Defaults to <i>hrSwRunName</i> and should never be changed under normal circumstances. That said, changing it to <i>hrSwRunParameters</i> (.1.3.6.1.2.1.25.4.2.1.5) is often helpful when dealing with processes running under <i>Java Virtual Machines</i> which all have the same process name <i>java</i> .	option al	.1.3.6.1.2.1.2 5.4.2.1.2

Table 26. Monitor specific parameters for the HostResourceSwRunMonitor

Parameter	Description	Requi red	Default value
service-	The numeric object identifier (OID) from which run status is queried. Defaults to <i>hrSwRunStatus</i> and should never be changed under normal circumstances.	option	.1.3.6.1.2.1.2
status-oid		al	5.4.2.1.7

This monitor implements the Common Configuration Parameters.

Examples

The following example shows how to monitor the process called *httpd* running on a server using this monitor. The configuration in poller-configuration.xml has to be defined as the following:

```
<service name="Process-httpd" interval="300000" user-defined="false" status="on">
        <parameter key="retry" value="3"/>
        <parameter key="timeout" value="3000"/>
        <parameter key="service-name" value="httpd"/>①
        <parameter key="run-level" value="3"/>②
        <parameter key="run-level" value="3"/>③
        </service>
```

1 Name of the process on the system

2 Test the state if the process is in a valid state, i.e. have a run-level no higher than *notRunnable(3)*

③ If the *httpd* process runs multiple times the test is done for each instance of the process.

5.6.16. HttpMonitor

The HTTP monitor tests the response of an HTTP server on a specific HTTP 'GET' command. During the poll, an attempt is made to connect on the specified port(s). The monitor can test web server on multiple ports. By default the test is made against port 80, 8080 and 8888. If the connection request is successful, an HTTP 'GET' command is sent to the interface. The response is parsed and a return code extracted and verified. This monitor implements placeholder substitution in parameter values.

Monitor facts

Class Name	org.opennms.netmgt.poller.monitors.HttpMonitor
Remote Enabled	true

Configuration and Usage

Table 27. Monitor specific parameters for the HttpMonitor

Parame ter	Description	Req uire d	Default value	Placehol der substitut ion
basic- authenti cation	Authentication credentials to perform basic authentication. Credentials should comply to RFC1945 section 11.1, without the Base64 encoding part. That's: be a string made of the concatenation of: 1- the user ID; 2- a colon; 3- the password. basic-authentication takes precedence over the user and password parameters.	opti onal		Yes
header[0 -9]+	Additional headers to be sent along with the request. Example of valid parameter's names are header0, header1 and header180. header is not a valid parameter name.	opti onal	-	No
host- name	Specify the <i>Host</i> header's value.	opti onal	-	No
nodelabe l-host- name	If the host-name parameter isn't set and the resolve-ip parameter is set to false, then OpenNMS Meridian will use the node's label to set the Host header's value if this parameter is set to true. Otherwise, OpenNMS Meridian will fall back using the node interface's IP address as Host header value.	opti onal	false	No
password	This parameter is meant to be used together with the user parameter to perform basic authentication. This parameter specifies the password to be used. The user and password parameters are ignored when the basic-authentication parameter is defined.	-	empty string	Yes

Parame ter	Description	Req uire d	Default value	Placehol der substitut ion
port	A list of TCP ports to which connection shall be tried.	opti onal	80,8080,8888	No
retry	Number of attempts to get a valid <i>HTTP</i> response/response-text	opti onal	0	No
resolve- ip	If the host-name parameter isn't set and this parameter is set to true, <i>OpenNMS Meridian</i> will use <i>DNS</i> to resolve the node interface's IP address, and use the result to set the <i>Host</i> header's value. When set to false and the host-name parameter isn't set, <i>OpenNMS</i> <i>Meridian</i> will try to use the nodelabel-host-name parameter to set the <i>Host</i> header's value.	opti onal	false	No
response	A comma-separated list of acceptable <i>HTTP</i> response code ranges. Example: 200-202,299	-	If the url parameter is set to /, the default value for this parameter is 100-499, otherwise it's 100-399.	No
response -text	Text to look for in the response body. This will be matched against every line, and it will be considered a success at the first match. If there is a ~ at the beginning of the parameter, the rest of the string will be used as a regular expression pattern match, otherwise the match will be a substring match. The regular expression match is anchored at the beginning and end of the line, so you will likely need to put a .* on both sides of your pattern unless you are going to be matching on the entire line.			No
url	URL to be retrieved via the HTTP 'GET' command	opti onal	/	Yes

Parame ter	Description	Req uire d	Default value	Placehol der substitut ion
USET	This parameter is meant to be used together with the password parameter to perform basic authentication. This parameter specifies the user ID to be used. The user and password parameters are ignored when the basic- authentication parameter is defined.	opti onal		Yes
user- agent	Allows you to set the <i>User-Agent</i> HTTP header (see also RFC2616 section 14.43).	opti onal	OpenNMS HttpMonitor	Yes
verbose	When set to <i>true</i> , full communication between client and the webserver will be logged (with a log level of DEBUG).	opti onal	-	No

This monitor implements the Common Configuration Parameters.

Examples

```
<!-- Test HTTP service on port 80 only -->
<service name="HTTP" interval="300000" user-defined="false" status="on">
 <parameter key="retry" value="2"/>
 <parameter key="timeout" value="3000"/>
 <parameter key="port" value="80"/>
 <parameter key="url" value="/"/>
</service>
<!-- Test for virtual host opennms.com running -->
<service name="OpenNMSdotCom" interval="300000" user-defined="false" status="on">
 <parameter key="retry" value="1"/>
 <parameter key="timeout" value="3000"/>
 <parameter key="port" value="80"/>
 <parameter key="host-name" value="opennms.com"/>
 <parameter key="url" value="/solutions"/>
 <parameter key="response" value="200-202,299"/>
 <parameter key="response-text" value="~.*[Cc]onsulting.*"/>
</service>
<!-- Test for instance of OpenNMS 1.2.9 running -->
<service name="OpenNMS-129" interval="300000" user-defined="false" status="on">
 <parameter key="retry" value="1"/>
 <parameter key="timeout" value="3000"/>
 <parameter key="port" value="8080"/>
 <parameter key="url" value="/opennms/event/list"/>
 <parameter key="basic-authentication" value="admin:admin"/>
 <parameter key="response" value="200"/>
</service>
<!-- Test for instance of OpenNMS 1.2.9 with parameter substitution in basic-
authentication parameter -->
<service name="OpenNMS-22" interval="300000" user-defined="false" status="on">
 <parameter key="retry" value="1"/>
 <parameter key="timeout" value="3000"/>
 <parameter key="port" value="8080"/>
 <parameter key="url" value="/opennms/event/list"/>
 <parameter key="basic-authentication" value="{username}:{password}"/>
 <parameter key="response" value="200"/>
</service>
<monitor service="HTTP" class-name="org.opennms.netmgt.poller.monitors.HttpMonitor" />
<monitor service="OpenNMSdotCom" class-name=
"org.opennms.netmgt.poller.monitors.HttpMonitor" />
<monitor service="OpenNMS-129" class-name=
"org.opennms.netmgt.poller.monitors.HttpMonitor" />
<monitor service="OpenNMS-22" class-name=
"org.opennms.netmgt.poller.monitors.HttpMonitor" />
```

Testing filtering proxies with HttpMonitor

In case a filtering proxy server is set up to allow retrieval of some URLs but deny others, the HttpMonitor can be used to verify this behavior.

As an example a proxy server is running on TCP port 3128, and serves http://www.opennms.org/ but never http://www.myspace.com/. To test this behaviour, the *HttpMonitor* can be configured as the following:

```
<service name="HTTP-Allow-opennms.org" interval="300000" user-defined="false" status=</pre>
"on">
 <parameter key="retry" value="1"/>
 <parameter key="timeout" value="3000"/>
 <parameter key="port" value="3128"/>
 <parameter key="url" value="http://www.opennms.org/"/>
 <parameter key="response" value="200-399"/>
</service>
<service name="HTTP-Block-myspace.com" interval="300000" user-defined="false" status=</pre>
"on">
 <parameter key="retry" value="1"/>
 <parameter key="timeout" value="3000"/>
 <parameter key="port" value="3128"/>
 <parameter key="url" value="http://www.myspace.com/"/>
 <parameter key="response" value="400-599"/>
</service>
<monitor service="HTTP-Allow-opennms.org" class-name=
"org.opennms.netmgt.poller.monitors.HttpMonitor"/>
<monitor service="HTTP-Block-myspace.com" class-name=
"org.opennms.netmgt.poller.monitors.HttpMonitor"/>
```

5.6.17. HttpPostMonitor

If it is required to *HTTP POST* any arbitrary content to a remote *URI*, the HttpPostMonitor can be used. A use case is to HTTP POST to a SOAP endpoint. This monitor implements placeholder substitution in parameter values.

Monitor facts

Class Name	org.opennms.netmgt.poller.monitors.HttpPostMonitor
Remote Enabled	false

Configuration and Usage

Table 28. Monitor specific parameters for the HttpPostMonitor

Paramete r	nete Description		Default value	Placeholder substitution
payload	The body of the POST, for example properly escaped XML.		-	No
auth- password	The password to use for HTTP BASIC auth.	optio nal	-	Yes
auth- username	The username to use for HTTP BASIC auth.	optio nal	-	Yes
header[0- 9]+ Additional headers to be sent along with the request. Example of valid parameter's names are header0, header1 and header180. header is not a valid parameter name.		optio nal	-	No
banner A string that is matched against the response of the HTTP POST. If the output contains the banner, the service is determined as up. Specify a regex by starting with ~.		optio nal	-	Yes
charset	Set the character set for the POST.	optio nal	UTF-8	No
mimetype	Set the mimetype for the POST.	optio nal	text/xm l	No
port	The port for the web server where the POST is send to.	optio nal	80	No
scheme	The connection scheme to use.	optio nal	http	No
usesslfil ter	Entables of alloables the soll certaincate validation. the		false	No
uri	The uri to use during the POST.		/	Yes
use- system- proxy	system proxy settings can be configured in system		false	No

This monitor implements the Common Configuration Parameters.

Examples

The following example would create a POST that contains the payload *Word*.

```
<service name="MyServlet" interval="300000" user-defined="false" status="on">
    <parameter key="banner" value="Hello"/>
    <parameter key="port" value="8080"/>
    <parameter key="uri" value="/MyServlet">
    <parameter key="uri" value="World"/>
    <parameter key="retry" value="World"/>
    <parameter key="retry" value="1"/>
    <parameter key="timeout" value="30000"/>
    </service>
<monitor service="MyServlet" class-name=
"org.opennms.netmgt.poller.monitors.HttpPostMonitor"/>
```

The resulting POST looks like this:

```
POST /MyServlet HTTP/1.1
Content-Type: text/xml; charset=utf-8
Host: <ip_addr_of_interface>:8080
Connection: Keep-Alive
```

World

5.6.18. HttpsMonitor

The HTTPS monitor tests the response of an SSL-enabled HTTP server. The HTTPS monitor is an SSL-enabled extension of the HTTP monitor with a default TCP port value of 443. All HttpMonitor parameters apply, so please refer to HttpMonitor's documentation for more information. This monitor implements placeholder substitution in parameter values.

Monitor facts

Class Name	org.opennms.netmgt.poller.monitors.HttpsMonitor
Remote Enabled	true

Configuration and Usage

Table 29. Monitor specific parameters for the HttpsMonitor

Paramete	Description	Require	Default
r		d	value
port	A list of TCP ports to which connection shall be tried.	optional	443

Examples

5.6.19. IcmpMonitor

The ICMP monitor tests for ICMP service availability by sending *echo request* ICMP messages. The service is considered available when the node sends back an *echo reply* ICMP message within the specified amount of time.

Monitor facts

Class Name	org.opennms.netmgt.poller.monitors.IcmpMonitor
Remote Enabled	true with some restrictions (see below)

Configuration and Usage

Table 30. Monitor specific parameters for the IcmpMonitor

Parameter	Description	Require d	Default value
timeout	Time in milliseconds to wait for a response.	optional	800
allow- fragmentation	Whether to set the "Don't Fragment" bit on outgoing packets	optional	true
dscp	DSCP traffic-control value.	optional	0
packet-size	Number of bytes of the ICMP packet to send.	optional	64
thresholding- enabled	Enables ICMP thresholding.	optional	true

This monitor implements the Common Configuration Parameters.

Examples

```
<service name="ICMP" interval="300000" user-defined="false" status="on">
  <parameter key="retry" value="2"/>
  <parameter key="timeout" value="3000"/>
  <parameter key="rrd-repository" value="/var/lib/opennms/rrd/response"/>
  <parameter key="rrd-base-name" value="icmp"/>
  <parameter key="ds-name" value="icmp"/>
  </service>
<monitor service="ICMP" class-name="org.opennms.netmgt.poller.monitors.IcmpMonitor"/>
```

```
<!-- Advanced example: set DSCP bits and send a large packet with allow-
fragmentation=false -->
<service name="ICMP" interval="300000" user-defined="false" status="on">
    <parameter key="retry" value="2"/>
    <parameter key="timeout" value="3000"/>
    <parameter key="dscp" value="0x1C"/> <!-- AF32: Class 3, Medium drop probability -->
    <parameter key="allow-fragmentation" value="false"/>
    <parameter key="packet-size" value="2048"/>
    <parameter key="rrd-repository" value="/var/lib/opennms/rrd/response"/>
    <parameter key="rrd-base-name" value="icmp"/>
    <parameter key="dscname" value="icmp"/>
    <parameter key="reforme" class-name="org.opennms.netmgt.poller.monitors.IcmpMonitor"/>
```

Note on Remote Poller

The IcmpMonitor needs the JNA ICMP implementation to function on remote poller. Though, corner cases exist where the IcmpMonitor monitor won't work on remote poller. Examples of such corner cases are: Windows when the remote poller isn't running has administrator, and Linux on ARM / Rasperry Pi. JNA is the default ICMP implementation used in the remote poller.

5.6.20. ImapMonitor

This monitor checks if an *IMAP* server is functional. The test is done by initializing a very simple *IMAP* conversation. The ImapMonitor establishes a *TCP* connection, sends a logout command and test the *IMAP* server responses.

The behavior can be simulated with telnet:

telnet mail.myserver.de 143
Trying 62.108.41.197...
Connected to mail.myserver.de.
Escape character is '^]'.
* OK [CAPABILITY IMAP4rev1 LITERAL+ SASL-IR LOGIN-REFERRALS ID ENABLE IDLE STARTTLS
LOGINDISABLED] Dovecot ready. ①
ONMSPOLLER LOGOUT ②
* BYE Logging out ③
ONMSPOLLER OK Logout completed.
Connection closed by foreign host.

① Test IMAP server banner, it has to start * OK to be *up*

- ② Sending a ONMSPOLLER LOGOUT
- ③ Test server responds with, it has to start with * BYE to be *up*

If one of the tests in the sample above fails the service is marked *down*.

Monitor facts

Class Name	org.opennms.netmgt.poller.monitors.ImapMonitor
Remote Enabled	false

Configuration and Usage

Table 31. Monitor specific parameters for the ImapMonitor

Paramete r	Description	Require d	Default value
retry	Number of attempts to get a valid IMAP response	optional	0
port	The port of the IMAP server.	optional	143

This monitor implements the Common Configuration Parameters.

Examples

Some example configuration how to configure the monitor in the poller-configuration.xml

5.6.21. ImapsMonitor

The *IMAPS* monitor tests the response of an *SSL-enabled IMAP* server. The *IMAPS* monitor is an *SSL-enabled* extension of the *IMAP* monitor with a default *TCP* port value of 993. All *ImapMonitor* parameters apply, so please refer to ImapMonitor's documentation for more information.

Monitor facts

Class Name	org.opennms.netmgt.poller.monitors.ImapsMonitor
Remote Enabled	true

Configuration and Usage

Table 32. Monitor specific parameters for the ImapsMonitor

Paramete	Description	Require	Default
r		d	value
port	The destination port where connections shall be attempted.	optional	993

This monitor implements the Common Configuration Parameters.

Examples

5.6.22. JCifsMonitor

This monitor allows to test a file sharing service based on the CIFS/SMB protocol. This monitor implements placeholder substitution in parameter values.



This monitor is not installed by default. You have to install opennmms-pluginprotocol-cifs from your OpenNMS Meridian installation repository.

With the *JCIFS* monitor you have different possibilities to test the availability of the *JCIFS* service:

With the *JCifsMonitor* it is possible to run tests for the following use cases:

- share is available in the network
- a given file exists in the share
- a given folder exists in the share
- a given folder should contain at least one (1) file
- a given folder folder should contain no (0) files
- by testing on files and folders, you can use a regular expression to ignore specific file and folder names from the test

A network resource in SMB like a file or folder is addressed as a UNC Path.

\\server\share\folder\file.txt

The Java implementation *jCIFS*, which implements the *CIFS/SMB* network protocol, uses *SMB* URLs to access the network resource. The same resource as in our example would look like this as an SMB URL:

smb://workgroup;user:password@server/share/folder/file.txt

The *JCifsMonitor* can **not** test:

- file contains specific content
- a specific number of files in a folder, for example folder should contain exactly / more or less than x files
- Age or modification time stamps of files or folders
- Permissions or other attributes of files or folders

Monitor facts

Class Name	org.opennms.netmgt.poller.monitors.JCifsMonitor
Remote Enabled	false

Configuration and Usage

Table 33. Monitor specific parameters for the JCifsMonitor

Paramete r	Description	-		Placeholder substitution
retry	Number of retries before the service is marked as <i>down</i> .	optio nal	0	No

Paramete r	Description	Requ ired	Default value	Placeholder substitution	
domain	Windows domain where the user is located. You don't have to use the domain parameter if you use local user accounts.		empty String	Yes	
username	Username to access the resource over a network	optio nal	empty String	Yes	
password	Password for the user	optio nal	empty String	Yes	
path	Path to the resource you want to test	requi red	empty String	No	
mode	The test mode which has the following options path_exist: Service is up if the resource is accessible path_not_exist: Service is up if the resource is not accessible folder_empty: Service is up if the folder is empty (0 files) folder_not_empty: Service is up if the folder has at least one file	optio nal	path_ex ist	No	
smbHost	Override the IP address of the SMB url to check shares on different file servers.	optio nal	empty String	No	
folderIgno reFiles	Ignore specific files in folder with regular expression. This parameter will just be applied on folder_empty and folder_not_empty, otherwise it will be ignored.	optio nal	-	No	

5

Due to limitations in the JCifs library, only global timeouts can be used reliably.

This monitor implements the Common Configuration Parameters.

It makes little sense to have retries higher than 1. It is a waste of resources during the monitoring.

Q

 \bigcirc

Please consider, if you are accessing shares with Mac OSX you have some side effects with the hidden file '.DS_Store.' It could give you false positives in monitoring, you can use then the folderIgnoreFiles parameter.

Example test existence of a file

This example shows how to configure the *JCifsMonitor* to test if a file share is available over a network. For this example we have access to a share for error logs and we want to get an outage if we have any error log files in our folder. The share is named *log*. The service should go back to normal if the error log file is deleted and the folder is empty.

JCifsMonitor configuration to test that a shared folder is empty

```
<service name="CIFS-ErrorLog" interval="30000" user-defined="true" status="on">
    <parameter key="retry" value="1" />
    <parameter key="timeout" value="3000" />
    <parameter key="timeout" value="3000" />
    <parameter key="domain" value="contoso" />①
    <parameter key="username" value="MonitoringUser" />②
    <parameter key="password" value="MonitoringPassword" />③
    <parameter key="path" value="fileshare/log/" />④
    <parameter key="mode" value="folder_empty" />⑤
  </service>
```

- ① Name of the SMB or Microsoft Windows Domain
- ② User for accessing the share
- ③ Password for accessing the share
- ④ Path to the folder inside of the share as part of the SMB URL
- ⑤ Mode is set to folder_empty

5.6.23. JDBCMonitor

The *JDBCMonitor* checks that it is able to connect to a database and checks if it is able to get the database catalog from that database management system (DBMS). It is based on the JDBC technology to connect and communicate with the database. This monitor implements placeholder substitution in parameter values.

Monitor facts

Class Name	org.opennms.netmgt.poller.monitors.JDBCMonitor
Remote Enabled	true

Configuration and Usage

Table 34 Monitor	specific narameters	for the JDBCMonitor
<i>1 uble 54. Montlor</i>	specific purumeters	

Param eter	Description	Requi red	Default value	Placeholder substitution
driver	JDBC driver class to use	requi red	org.postgresql.Driver	No
url	JDBC Url to connect to.	requi red	jdbc:postgresql://:OPENNMS_J DBC_HOSTNAME/opennms	Yes
user	Database user	requi red	postgres	Yes

Param eter	Description	Requi red	Default value	Placeholder substitution
passwo rd	Database password	requi red	empty string	Yes
retrie s	How many retries should be performed before failing the test	optio nal	0	No



The *OPENNMS_JDBC_HOSTNAME* is replaced in the *url* parameter with the IP or resolved hostname of the interface the monitored service is assigned to.

This monitor implements the Common Configuration Parameters.

Provide the database driver

The *JDBCMonitor* is based on *JDBC* and requires a JDBC driver to communicate with any database. Due to the fact that OpenNMS Meridian itself uses a PostgreSQL database, the PostgreSQL JDBC driver is available out of the box. For all other database systems a compatible JDBC driver has to be provided to OpenNMS Meridian as a *jar-file*. To provide a JDBC driver place the *driver-jar* in the opennms/lib folder of your OpenNMS Meridian. To use the *JDBCMonitor* from a remote poller, the *driver-jar* has to be provided to the *Remote Poller* too. This may be tricky or impossible when using the *Java Webstart Remote Poller*, because of code signing requirements.

Examples

The following example checks if the PostgreSQL database used by OpenNMS Meridian is available.

```
<service name="OpenNMS-DBMS" interval="30000" user-defined="true" status="on">
    <parameter key="driver" value="org.postgresql.Driver"/>
    <parameter key="url" value="jdbc:postgresql://OPENNMS_JDBC_HOSTNAME:5432/opennms"/>
    <parameter key="user" value="opennms"/>
    <parameter key="password" value="opennms"/>
    <parameter key="password" value="opennms"/>
    </service>
```

5.6.24. JDBCStoredProcedureMonitor

The *JDBCStoredProcedureMonitor* checks the result of a stored procedure in a remote database. The result of the stored procedure has to be a boolean value (representing true or false). The service associated with this monitor is marked as up if the stored procedure returns true and it is marked as down in all other cases. It is based on the JDBC technology to connect and communicate with the database. This monitor implements placeholder substitution in parameter values.

Monitor facts

Class Name	org.opennms.netmgt.poller.monitors.JDBCStoredProcedureMonitor
Remote Enabled	false

Configuration and Usage

Table 35. Monitor specific parameters for the JDBCStoredProcedureMonitor

Paramete r	Description	Requ ired	Default value	Placeholder substitution
driver	JDBC driver class to use	requi red	org.postgresql.Driver	No
url	JDBC Url to connect to.	requi red	jdbc:postgresql://:OPENNMS_ JDBC_HOSTNAME/opennms	Yes
user	Database user	requi red	postgres	Yes
password	Database password	requi red	empty string	Yes
retries	How many retries should be performed before failing the test	optio nal	0	No
stored- procedure	Name of the database stored procedure to call	requi red	-	No
schema	Name of the database schema in which the stored procedure is	optio nal	test	No



The *OPENNMS_JDBC_HOSTNAME* is replaced in the *url* parameter with the IP or resolved hostname of the interface the monitored service is assigned to.

This monitor implements the Common Configuration Parameters.

Provide the database driver

The *JDBCStoredProcedureMonitor* is based on *JDBC* and requires a *JDBC driver* to communicate with any database. Due to the fact that OpenNMS Meridian itself uses a *PostgreSQL* database, the *PostgreSQL JDBC driver* is available out of the box. For all other database systems a compatible *JDBC driver* has to be provided to OpenNMS Meridian as a *jar-file*. To provide a *JDBC driver* place the *driver-jar* in the opennms/lib folder of your OpenNMS Meridian. To use the *JDBCStoredProcedureMonitor* from a remote poller, the *driver-jar* has to be provided to the *Remote Poller* too. This may be tricky or impossible when using the *Java Webstart Remote Poller*, because of code signing requirements.

Examples

The following example checks a stored procedure added to the *PostgreSQL* database used by OpenNMS Meridian. The stored procedure returns true as long as less than 250000 events are in the events table of OpenNMS Meridian.

Stored procedure which is used in the monitor

```
CREATE OR REPLACE FUNCTION eventlimit_sp() RETURNS boolean AS
$BODY$DECLARE
num_events integer;
BEGIN
    SELECT COUNT(*) into num_events from events;
    RETURN num_events > 250000;
END;$BODY$
LANGUAGE plpgsql VOLATILE NOT LEAKPROOF
COST 100;
```

5.6.25. JDBCQueryMonitor

The *JDBCQueryMonitor* runs an SQL query against a database and is able to verify the result of the query. A read-only connection is used to run the SQL query, so the data in the database is not altered. It is based on the JDBC technology to connect and communicate with the database. This monitor implements placeholder substitution in parameter values.

Monitor facts

Class Name	org.opennms.netmgt.poller.monitors.JDBCQueryMonitor
Remote Enabled	false

Configuration and Usage

Table 36. Monitor specific parameters for the JDBCQueryMonitor

Para mete r	Description	Requ ired	Default value	Placeholde r substitutio n
drive r	JDBC driver class to use	requi red	org.postgresql.Driver	No
url	JDBC URL to connect to	requi red	jdbc:postgresql://:OPEN NMS_JDBC_HOSTNAME/openn ms	Yes
user	Database user	requi red	postgres	Yes
passw ord	Database password	requi red	empty string	Yes
query	The SQL query to run	requi red	-	No
actio n	What evaluation action to perform	requi red	row_count	No
colum n	The result column to evaluate against when using compare_string method	requi red	-	No
opera tor	Operator to use for the evaluation	requi red	>=	No
opera nd	The operand to compare against the SQL query result	requi red	depends on the action	No
messa ge	The message to use if the service is down. Both operands and the operator are added to the message too.	optio nal	generic message depending on the action	No
retri es	How many retries should be performed before failing the test	optio nal	0	No



The OPENNMS_JDBC_HOSTNAME is replaced in the url parameter with the IP or resolved hostname of the interface the monitored service is assigned to.

This monitor implements the Common Configuration Parameters.

Table 37. Available action parameters and their default operand

Parameter	Description	Default operand
row_count	The number of returned rows is compared, not a value of the resulting rows	1

Parameter	Description	Default operand
compare_stri ng	Strings are always checked for equality with the operand	-
compare_int	An integer from a column of the first result row is compared	1

Table 38. Available operand parameters

Paramete r	XML entity to use in XML configs
=	=
<	8lt;
>	8gt;
!=	!=
⇐	8lt;=
>=	>=

Evaluating the action - operator - operand

Only the first result row returned by the SQL query is evaluated. The evaluation can be against the value of one column or the number of rows returned by the SQL query.

Provide the database driver

The *JDBCQueryMonitor* is based on *JDBC* and requires a JDBC driver to communicate with any database. Due to the fact that OpenNMS Meridian itself uses a PostgreSQL database, the PostgreSQL JDBC driver is available out of the box. For all other database systems a compatible JDBC driver has to be provided to OpenNMS Meridian as a *jar-file*. To provide a JDBC driver place the *driver-jar* in the opennms/lib folder of your OpenNMS Meridian. To use the *JDBCQueryMonitor* from a remote poller, the *driver-jar* has to be provided to the *Remote Poller* too. This may be tricky or impossible when using the *Java Webstart Remote Poller*, because of code signing requirements.

Examples

Row Count

The following example checks if the number of events in the OpenNMS Meridian database is fewer than 250,000.

String Comparison

The following example checks if the queried string matches against a defined operand.

```
<service name="MariaDB-Galera" interval="300000" user-defined="false" status="on">
  <parameter key="driver" value="org.mariadb.jdbc.Driver"/>
  <parameter key="user" value="opennms"/>
  <parameter key="password" value="*******"/>
  <parameter key="url" value="jdbc:mysql://OPENNMS_JDBC_HOSTNAME"/>
  <parameter key="query" value="SELECT VARIABLE_VALUE FROM
INFORMATION_SCHEMA.GLOBAL_STATUS WHERE VARIABLE_NAME = 'wsrep_cluster_status'"/>
  <parameter key="column" value="VARIABLE_VALUE"/>
  <parameter key="action" value="compare_string"/>
  <parameter key="operator" value="emission" value="foalera" value="foalera" value="emission" value="emission" value="emission" value="emission" value="emission" value="foalera" va
```

5.6.26. JmxMonitor

The *JMX* monitor allows to test service availability of Java applications. The monitor offers the following functionalities:

- test the application's connectivity via JMX
- existence of management beans
- test the status of a single or multiple management beans and evaluate their value

Monitor facts

Class Name	org.opennms.netmgt.poller.monitors.Jsr160Monitor
Remote Enabled	true

Configuration and Usage

Table 39. Monitor specific parameters for the JmxMonitor

Parameter	Description	Requir ed	Default value
retry	Number of attempts to get a response	option al	3
timeout	Time in milliseconds to wait for a response	option al	?
port	Destination port where the <i>JMX</i> requests shall be sent	option al	from jmx- config.xml
factory	Set this to PASSWORD-CLEAR if credentials are required	option al	STANDARD
protocol	Protocol used in the <i>JMX</i> connection string	option al	rmi
urlPath	Path used in <i>JMX</i> connection string	option al	/jmxrmi
rmiServerPort	<i>RMI</i> port	option al	45444
remoteJMX	Use an alternative <i>JMX</i> URL scheme	option al	false
beans. <variab le></variab 	Defines a <i>mbeans</i> objectname to access. The ´ <variable>´ name is arbitrary.</variable>	option al	-
tests. <variab le></variab 	Tests a <i>mbeans</i> attribute value. The ´ <variable>´ name is arbitrary.</variable>	option al	-

Examples

Test if a JMX connection can be established

Test a specific management bean for a value



Reserved XML characters like >, <, " need to be escaped.

5.6.27. JolokiaBeanMonitor

The JolokiaBeanMonitor is a JMX monitor specialized for the use with the Jolokia framework. If it is required to execute a method via *JMX* or poll an attribute via *JMX*, the *JolokiaBeanMonitor* can be used. It requires a fully installed and configured *Jolokia agent* to be deployed in the JVM container. If required it allows attribute names, paths, and method parameters to be provided additional arguments to the call. To determine the status of the service the *JolokiaBeanMonitor* relies on the output to be matched against a banner. If the banner is part of the output the status is interpreted as up. If the banner is not available in the output the status is determined as *down*. Banner matching supports regular expression and substring match. This monitor implements placeholder substitution in parameter values.

Monitor facts

Class Name	org.opennms.netmgt.poller.monitors.JolokiaBeanMonitor
Remote Enabled	false

Configuration and Usage

Table 40. Monitor specific parameters for the JolokiaBeanMonitor

Param eter	Description	Required	Defaul t value	Placeholde r substitutio n
beannam e	The bean name to query against.	required	-	No
attrnam e	The name of the JMX attribute to scrape.	optional (attrname or methodname must be set)	-	No
attrpat h	The attribute path.	optional	-	No
auth- usernam e	The username to use for HTTP BASIC auth.	optional	-	Yes
auth- passwor d	The password to use for HTTP BASIC auth.	optional	-	Yes
banner	A string that is match against the output of the system-call. If the output contains the banner, the service is determined as <i>up</i> . Specify a regex by starting with ~.	optional	-	Yes
input1	Method input	optional	-	Yes
input2	Method input	optional	-	Yes
methodn ame	The name of the bean method to execute, output will be compared to banner.	optional (attrname or methodname must be set)	-	Yes
port	The port of the jolokia agent.	optional	8080	No
url	The jolokia agent url. Defaults to "http:// <ipaddr>:<port>/jolokia"</port></ipaddr>	optional	-	Yes

This monitor implements the Common Configuration Parameters.

Table 41. Variables which can be used in the configuration

Variable	Description
\${ipaddr}	IP-address of the interface the service is bound to.
\${port}	Port the service it bound to.

Examples

Some example configuration how to configure the monitor in the poller-configuration.xml

```
<parameter key="url" value="http://${ipaddr}:${port}/jolokia"/><parameter key="url" value="https://${ipaddr}:${port}/jolokia"/>
```

AttrName vs MethodName

The JolokiaBeanMonitor has two modes of operation. It can either scrape an attribute from a bean, or execute a method and compare output to a banner. The method execute is useful when your application has its own test methods that you would like to trigger via OpenNMS Meridian.

The args to execute a test method called "superTest" that take in a string as input would look like this:

```
<parameter key="beanname" value="MyBean" />
<parameter key="methodname" value="superTest" />
<parameter key="input1" value="someString"/>
```

The args to scrape an attribute from the same bean would look like this:

```
<parameter key="beanname" value="MyBean" />
<parameter key="attrname" value="upTime" />
```

5.6.28. LdapMonitor

The LDAP monitor tests for LDAP service availability. The LDAP monitor first tries to establish a TCP connection on the specified port. Then, if it succeeds, it will attempt to establish an LDAP connection and do a simple search. If the search returns a result within the specified timeout and attempts, the service will be considered available. The scope of the LDAP search is limited to the immediate subordinates of the base object. The LDAP search is anonymous by default. The LDAP monitor makes use of the *com.novell.ldap.LDAPConnection* class. This monitor implements placeholder substitution in parameter values.

Monitor facts

Class Name	org.opennms.netmgt.poller.monitors.LdapMonitor
Remote Enabled	true

Configuration and Usage

Table 42. Monitor specific parameters for the LdapMonitor

Param eter	Description	-	Default value	Placeholder substitution
dn	The distinguished name to use if authenticated search is needed.	optio nal	-	Yes

Param eter	Description	Requ ired	Default value	Placeholder substitution
passwor d	The password to use if authenticated search is needed.	optio nal	-	Yes
port	The destination port where connection shall be attempted.	optio nal	389	No
retry	Number of attempts to get a search result.	optio nal	1	No
searchb ase	The base distinguished name to search from.	optio nal	base	No
searchf ilter	The LDAP search's filter.	optio nal	(objectcl ass=*)	No
version	The version of the LDAP protocol to use, specified as an integer. Note: Only LDAPv3 is supported at the moment.	optio nal	3	No

This monitor implements the Common Configuration Parameters.

Examples

5.6.29. LdapsMonitor

The LDAPS monitor tests the response of an SSL-enabled LDAP server. The LDAPS monitor is an SSL-enabled extension of the LDAP monitor with a default TCP port value of 636. All LdapMonitor parameters apply, so please refer to LdapMonitor's documentation for more information. This monitor implements the same placeholder substitution in parameter values as LdapMonitor.

Monitor facts

Class Name org.opennms.netmgt.poller.m	onitors.LdapsMonitor
--	----------------------

Configuration and Usage

Table 43. Monitor specific parameters for the LdapsMonitor

Paramete	Description	Require	Default
r		d	value
port	The destination port where connections shall be attempted.	optional	636

This monitor implements the Common Configuration Parameters.

Examples

5.6.30. MemcachedMonitor

This monitor allows to monitor Memcached, a distributed memory object caching system. To monitor the service availability the monitor tests if the *Memcached* statistics can be requested. The statistics are processed and stored in RRD files. The following metrics are collected:

Metric	Description
uptime	Seconds the <i>Memcached</i> server has been running since last restart.
rusageuser	User time seconds for the server process.
rusagesystem	System time seconds for the server process.
curritems	Number of items in this servers cache.
totalitems	Number of items stored on this server.

Table 44. Collected metrics using the MemcachedMonitor

Metric	Description
bytes	Number of bytes currently used for caching items.
limitmaxbytes	Maximum configured cache size.
currconnections	Number of open connections to this Memcached.
totalconnections	Number of successful connect attempts to this server since start.
connectionstructure	Number of internal connection handles currently held by the server.
cmdget	Number of <i>GET</i> commands received since server startup.
cmdset	Number of SET commands received since server startup.
gethits	Number of successful <i>GET</i> commands (cache hits) since startup.
getmisses	Number of failed <i>GET</i> requests, because nothing was cached.
evictions	Number of objects removed from the cache to free up memory.
bytesread	Number of bytes received from the network.
byteswritten	Number of bytes send to the network.
threads	Number of threads used by this server.

Monitor facts

Class Name	org.opennms.netmgt.poller.monitors.MemcachedMonitor
Remote Enabled	true

Configuration and Usage

Table 45. Monitor specific parameters for the MemcachedMonitor

Paramete r	Description	Require d	Default value
retry	Number of attempts to establish the Memcached connnection.	optional	0
port	TCP port connecting to Memcached.	optional	11211

This monitor implements the Common Configuration Parameters.

Examples

The following example shows a configuration in the poller-configuration.xml.

```
<service name="Memcached" interval="300000" user-defined="false" status="on">
    <parameter key="port" value="11211" />
    <parameter key="retry" value="2" />
    <parameter key="timeout" value="3000" />
    <parameter key="timeout" value="3000" />
    <parameter key="rrd-repository" value="/opt/opennms/share/rrd/response" />
    <parameter key="ds-name" value="memcached" />
    <parameter key="rrd-base-name" value="memcached" />
    <parameter key="rrd-base-name" value="memcached" />
    </service>
```

5.6.31. NetScalerGroupHealthMonitor

This monitor is designed for *Citrix*® *NetScaler*® loadbalancing checks. It checks if more than x percent of the servers assigned to a specific group on a loadbalanced service are active. The required data is gathered via SNMP from the *NetScaler*®. The status of the servers is determined by the *NetScaler*®. The provided service it self is not part of the check. The basis of this monitor is the *SnmpMonitorStrategy*. A valid SNMP configuration in *OpenNMS Meridian* for the *NetScaler*® is required.



A *NetScaler*® can manage several groups of servers per application. This monitor just covers one group at a time. If there are multiple groups to check, define one monitor per group.

This monitor is not checking the loadbalanced service it self.

Monitor facts

Class Name	org.opennms.netmgt.poller.monitors.NetScalerGroupHealthMonitor
Remote Enabled	false

Configuration and Usage

Table 46. Monitor specific parameters for the NetScalerGroupHealthMonitor

Parameter	Description	Requir ed	Default value
group-name	The name of the server group to check	require d	-
group- health	The percentage of active servers vs total server of the group as an integer	optional	60

This monitor implements the Common Configuration Parameters.

Examples

The following example checks a server group called *central_webfront_http*. If at least 70% of the servers are active, the service is up. If less then 70% of the servers are active the service is down. A configuration like the following can be used for the example in the poller-configuration.xml.

```
<service name="NetScaler_Health" interval="300000" user-defined="false" status="on">
        <parameter key="group-name" value="central_webfront_http" />
        <parameter key="group-health" value="70" />
        </service>
</monitor service="NetScaler_Health" class-name=
        "org.opennms.netmgt.poller.monitors.NetScalerGroupHealthMonitor" />
```

Details about the used SNMP checks

The monitor checks the status of the server group based on the *NS-ROOT-MIB* using the *svcGrpMemberState*. *svcGrpMemberState* is part of the *serviceGroupMemberTable*. The *serviceGroupMemberTable* is indexed by *svcGrpMemberGroupName* and *svcGrpMemberName*. A initial lookup for the group-name is performed. Based on the lookup the *serviceGroupMemberTable* is walked with the numeric representation of the server group. The monitor interprets just the server status code 7-up as active server. Other status codes like 2-unknown or 3-busy are counted for total amount of servers.

5.6.32. NrpeMonitor

This monitor allows to test plugins and checks running on the Nagios Remote Plugin Executor (*NRPE*) framework. The monitor allows to test the status output of any available check command executed by *NRPE*. Between OpenNMS Meridian and *Nagios* are some conceptional differences. In OpenNMS Meridian a service can only be available or not available and the response time for the service is measured. *Nagios* on the other hand combines service availability, performance data collection and thresholding in one check command. For this reason a *Nagios* check command can have more states then *OK* and *CRITICAL*. Using the *NrpeMonitor* marks all check command results other than *OK* as *down*. The full output of the check command output message is passed into the service down event in OpenNMS Meridian.



NRPE configuration on the server is required and the check command has to be configured, e.g. command[check_apt]=/usr/lib/nagios/plugins/check_apt



OpenNMS Meridian executes every *NRPE* check in a Java thread without *fork()* a process and it is more resource friendly. Nevertheless it is possible to run *NRPE* plugins which combine a lot of external programs like sed, awk or cut. Be aware, each command end up in forking additional processes.

Monitor facts

Class Name org.opennms.netmgt.poller.monitors.NrpeMonitor

Configuration and Usage

Table 47. Monitor	specific parameters	for the NrpeMonitor
100000 10 10 1000000		

Param eter	Description	Requi red	Default value
retry	Number of retries before the service is marked as <i>down</i> .	option al	0
command	The {check_name} of the command configured as `command[{check_name}]="/path/to/plugin/check-script"	requir ed	empty
port	Port to access <i>NRPE</i> on the remote server.	option al	5666
padding	Padding for sending the command to the <i>NRPE</i> agent.	option al	2
usessl	Enable encryption of network communication. <i>NRPE</i> uses SSL with anonymous DH and the following cipher suite <i>TLS_DH_anon_WITH_AES_128_CBC_SHA</i>	option al	true

This monitor implements the Common Configuration Parameters.

Example: Using *check_apt* with *NRPE*

This examples shows how to configure the *NrpeMonitor* running the *check_apt* command on a configured *NRPE*.

Configuration of the NRPE check command on the agent in 'nrpe.cfg'

command[check_apt]=/usr/lib/nagios/plugins/check_apt

Configuration to test the NRPE plugin with the NrpeMonitor

```
<service name="NRPE-Check-APT" interval="300000" user-defined="false" status="on">
        <parameter key="retry" value="3" />
        <parameter key="timeout" value="3000" />
        <parameter key="port" value="5666" />
        <parameter key="command" value="check_apt" />
        <parameter key="padding" value="2" />
        </service>
</monitor service="NRPE-Check-APT" class-name=
"org.opennms.netmgt.poller.monitors.NrpeMonitor" />
```

5.6.33. NtpMonitor

The NTP monitor tests for NTP service availability. During the poll an NTP request query packet is generated. If a response is received, it is parsed and validated. If the response is a valid NTP response, the service is considered available.

Monitor facts

Class Name	org.opennms.netmgt.poller.monitors.NtpMonitor
Remote Enabled	true

Configuration and Usage

Table 48. Monitor specific parameters for the NtpMonitor

Paramete r	Description	Require d	Default value
port	The destination port where the NTP request shall be sent.	optional	123
retry	Number of attempts to get a response.	optional	0
timeout	Time in milliseconds to wait for a response.	optional	5000

This monitor implements the Common Configuration Parameters.

Examples

5.6.34. OmsaStorageMonitor

With *OmsaStorageMonitor* you are able to monitor your Dell OpenManaged servers *RAID* array status. The following *OIDs* from the STORAGEMANAGEMENT-MIB are supported by this monitor:

virtualDiskRollUpStatus arrayDiskLogicalConnectionVirtualDiskNumber arrayDiskNexusID arrayDiskLogicalConnectionArrayDiskNumber	.1.3.6.1.4.1.674.10893.1.20.130.4.1.26 .1.3.6.1.4.1.674.10893.1.20.140.3.1.3
arrayDiskState	.1.3.6.1.4.1.674.10893.1.20.130.4.1.4

To test the status of the disk array the virtualDiskRollUpStatus is used. If the result of the virtualDiskRollUpStatus is not 3 the monitors is marked as *down*.

Resul t	State description	Monitor state in OpenNMS Meridian
1	other	DOWN
2	unknown	DOWN
3	ok	UP
4	non-critical	DOWN
5	critical	DOWN
6	non-recoverable	DOWN

Table 49. Possible result of virtual disk rollup status



You'll need to know the maximum number of possible logical disks you have in your environment. For example: If you have 3 RAID arrays, you need for each logical disk array a service poller.

To give more detailed information in case of an disk array error, the monitor tries to identify the problem using the other *OIDs*. This values are used to enrich the error reason in the service down event. The disk array state is resolved to a human readable value by the following status table.

Table 50. Possible array disk state errors

Valu e	Status
1	Ready
2	Failed
3	Online
4	Offline
6	Degraded
7	Recovering
11	Removed
15	Resynching
24	Rebuilding
25	noMedia
26	Formating

Valu e	Status
28	Running Diagnostics
35	Initializing

Monitor facts

Class Name	org.opennms.netmgt.poller.monitors.OmsaStorageMonitor
Remote Enabled	false

Configuration and Usage

Table 51. Monitor specific parameters for the OmsaStorageMonitor

Parameter	Description	Require d	Default value
virtualDiskNumber	The disk index of your RAID array	optional	1
port	The TCP port OpenManage is listening	optional	<pre>from snmp-config.xml</pre>

This monitor implements the Common Configuration Parameters.

Examples

Some example configuration how to configure the monitor in the poller-configuration.xml. The *RAID* array monitor for your first array is configured with virtualDiskNumber = 1 and can look like this:

```
<service name="OMSA-Disk-Array-1" interval="300000" user-defined="false" status="on">
  <parameter key="retry" value="3"/>
  <parameter key="timeout" value="6000"/>
  <parameter key="virtualDiskNumber" value="1"/>
  </service>
<monitor service="OMSA-Disk-Array-1" class-name=
"org.opennms.netmgt.poller.monitors.OmsaStorageMonitor"/>
```

If there is more than one RAID array to monitor you need an additional configuration. In this case virtualDiskNumber = 2.

```
<service name="OMSA-Disk-Array-2" interval="300000" user-defined="false" status="on">
  <parameter key="retry" value="3"/>
  <parameter key="timeout" value="6000"/>
  <parameter key="virtualDiskNumber" value="2"/>
  </service>
</monitor service="OMSA-Disk-Array-2" class-name=
  "org.opennms.netmgt.poller.monitors.OmsaStorageMonitor"/>
```

5.6.35. OpenManageChassisMonitor

The *OpenManageChassis* monitor tests the status of a *Dell* chassis by querying its *SNMP* agent. The monitor polls the value of the node's *SNMP OID* .1.3.6.1.4.1.674.10892.1.300.10.1.4.1 (MIB-Dell-10892::chassisStatus). If the value is *OK* (3), the service is considered available.

As this monitor uses *SNMP*, the queried nodes must have proper *SNMP* configuration in *snmp*-config.xml.

Monitor facts

Class Name	org.opennms.netmgt.poller.monitors.OpenManageChassisMonitor
Remote Enabled	false

Configuration and Usage

Table 52. Monitor specific parameters for the OpenManageChassisMonitor

Paramete r	Description	Require d	Default value
port	The port to which connection shall be tried.	optional	<pre>from snmp-config.xml</pre>

This monitor implements the Common Configuration Parameters.

Examples

Dell MIBs

Dell MIBs can be found here. Download the *DCMIB<version>.zip* or *DCMIB<version>.exe* file corresponding to the version of your *OpenManage* agents. The latest one should be good enough for all previous version though.

5.6.36. PageSequenceMonitor

The *PageSequenceMonitor* (PSM) allows OpenNMS to monitor web applications. This monitor has several configuration options regarding *IPv4*, *IPv6* and how to deal with name resolution. To add flexibility, the node label and IP address can be passed as variable into the monitor. This allows running the monitor with node dependent configuration. Beyond testing a web application with a single *URL* it can also test a path through a web application. A test path through an web application can look like this:

- 1. login to a certain web application
- 2. Execute an action while being logged in
- 3. Log off

The service is considered as *up* if all this is working ok. If there's an error somewhere, your application will need attention and the service changes the state to *down*.

Monitor facts

Class Name	org.opennms.netmgt.poller.monitors.PageSequenceMonitor
Remote Enabled	true

Configuration and Usage

The configuration for this monitor consists of several parts. First is the overall configuration for retries and timeouts. These parameters are global for the whole path through the web application.

param	neters
	Page Sequence
	r ago ocquone
	Page Path
	Page Path
	Page Path
	pre
	session variables
••••	headors headers

Figure 30. Configuration overview of the PSM

The overall layout of the monitor configuration is more complex. Additionally, it is possible to configure a page sequence containing a path through a web application.

Parameter	Description	Requi red	Default value
retry	The number of retries per page.	option al	0
strict- timeout	Defines a timer to wait before a retry attempt is made. It is only used if at least one (1) retry is configured. If retry >= 1 and strict- timeout is true the next attempt is delayed and the <i>Poller Daemon</i> waits NOW - InitialAttempt ms + Timeout ms. With strict-timout = false the next attempt is started right after a failure.	option al	false
page- sequence	Definition of the page-sequence to execute, see table with <i>Page Sequence Parameter</i>	requir ed	-
sequence- retry	The retry parameter for the entire page sequence.	option al	0

Table 53. Monitor parameters for the PageSequenceMonitor

Parameter	Description	Requi red	Default value
use-system- proxy	Should the system wide proxy settings be used? The system proxy settings can be configured via system properties	option al	false

Table 54. Page Sequence Parameter

Parameter	Description	Requ ired	Default
name	The name of the page-sequence. (Is this relevant/used?)	optio nal	-
method	HTTP method for example GET or POST	-	-
http-version	<i>HTTP</i> protocol version number, 0.9, 1.0 or 1.1	optio nal	HTTP/1.1
user-agent	Set the <i>user agent</i> field in <i>HTTP</i> header to identify the OpenNMS monitor	optio nal	OpenNMS PageSequenceMonitor (Service name: "\${SERVICE NAME}")
virtual-host	Set the <i>virtual host</i> field in <i>HTTP</i> header. In case of an HTTPS request, this is also the virtual domain to send as part of the <i>TLS</i> negotiation, known as server name indication (<i>SNI</i>) (See: RFC3546 section 3.1)	-	-
path	The relative URL to call in the request.	requi red	-
scheme	Define the <i>URL</i> scheme as http or https	optio nal	http
user-info	Set user info field in the HTTP header	-	-
host	Set <i>host</i> field in <i>HTTP</i> header	optio nal	IP interface address of the service
requireIPv6	Communication requires a connection to an <i>IPv6</i> address. (true or false)	-	-
requireIPv4	Communication requires a connection to an <i>IPv4</i> address. (true or false)	-	-
disable-ssl- verification	Enable or disable <i>SSL</i> certificate verification for <i>HTTPS</i> tests. Please use this option carefully, for self-signed certificates import the CA certificate in the JVM and don't just disable it.	optio nal	false

Parameter	Description	Requ ired	Default
port	Port of the web server connecting to	optio nal	80
query	??	-	-
failureMatch	Text to look for in the response body. This is a <i>Regular Expression</i> matched against every line, and it will be considered a failure at the first match and sets the service with this monitor <i>Down</i> .	-	-
failureMessa ge	The failure message is used to construct the reason code. \${n} values may be used to pull information from matching groups in the failureMatch regular expression.	-	-
successMatch	Text to look for in the response body. This is a <i>Regular Expression</i> matched against every line, and it will be considered a success at the first match and sets the service with this monitor <i>Up</i> .	optio nal	-
locationMatc h	The relative URL which must be loaded for the request to be considered successful.	optio nal	-
response- range	Range for allowed HTTP error codes from the response.	-	-
session- variable	Assign the value of a regex match group to a session variable with a user-defined name. The match group is identified by number and must be zero or greater.	-	-
response- range	A comma-separated list of acceptable <i>HTTP</i> response code ranges (200-202, 299).	optio nal	100-399



If you set requireIPv4 and requireIPv6 false, the host IP for connection will be resolved from system name resolver and the associated IP address from the IP interface is ignored.

Table 55. Variables which can be passed in the configuration

Varia	able	Description
\${nod	lelabel}	Nodelabel of the node the monitor is associated to.

Session variables

It is possible to assign strings from a retrieved page to variables that can be used in page parameters later in the same sequence. First, specify one or more capturing groups in the successMatch expression (see Java Class Pattern for more information on regular expressions in Java). The captured values can then be assigned to variable names by using the session-variable parameter, and used in a later page load.

Per-page response times

It is possible to collect response times for individual pages in a sequence. To use this functionality, a ds-name attribute must be added to each page whose load time should be tracked. The response time for each page will be stored in the same *RRD* file specified for the service via the rrd-base-name parameter under the specified datasource name.



You will need to delete existing *RRD* files and let them be recreated with the new list of datasources when you add a ds-name attribute to a page in a sequence that is already storing response time data.

Examples

The following example shows how to monitor the *OpenNMS* web application using several mechanisms. It first does an *HTTP GET* of *fipaddr/opennms* (following redirects as a browser would) and then checks to ensure that the resulting page has the phrase *Password* on it. Next, a login is attempted using *HTTP POST* to the relative *URL* for submitting form data (usually, the *URL* which the form action points to). The parameters (*j_username* and *j_password*) indicate the form's data and values to be submitted. Furthermore a custom header (foo) is set for demonstration purposes. After getting the resulting page, first the expression specified in the page's *failureMatch* attribute is verified, which when found anywhere on the page indicates that the page has failed. If the *failureMatch* expression is not found in the resulting page, then the expression specified in the page's *successMatch* attribute is checked to ensure it matches the resulting page. If the *successMatch* expression is not found on the page fails. If the monitor was able to successfully login, then the next page is processed. In the example, the monitor navigates to the Event page, to ensure that the text *Event Queries* is found on the page. Finally, the monitor calls the URL of the logout page to close the session. By using the *locationMatch* parameter, it is verified that the logout was successful and a redirect was triggered.



Each page is checked to ensure its *HTTP* response code fits into the response-range, before the failureMatch, successMatch, and locationMatch expressions are evaluated.

Configuration to test the login to the OpenNMS Web application

```
<service name="OpenNMS-Web-Login" interval="30000" user-defined="true" status="on">
  <parameter key="retry" value="1"/>
 <parameter key="timeout" value="5000"/>
 <parameter key="rrd-repository" value="/opt/opennms/share/rrd/response"/>
 <parameter key="ds-name" value="opennmslogin"/>
 <parameter key="page-sequence">
    <page-sequence>
      <page path="/opennms/login.jsp"</pre>
            port="8980"
            successMatch="Password" />
      <page path="/opennms/j_spring_security_check"</pre>
            port="8980"
            method="POST">
        <parameter key="j_username" value="admin"/>
        <parameter key="j_password" value="admin"/>
        <header name="foo" value="bar"/>
      </page>
      <page path="/opennms/index.jsp"</pre>
            port="8980"
            successMatch="Log Out" />
      <page path="/opennms/event/index"</pre>
            port="8980" successMatch="Event Queries" />
      <page path="/opennms/j_spring_security_logout"</pre>
            port="8980"
            method="POST"
            response-range="300-399"
            locationMatch="/opennms" />
    </page-sequence>
 </parameter>
</service>
<monitor service="OpenNMS-Web-Login" class-name=
"org.opennms.netmgt.poller.monitors.PageSequenceMonitor"/>
```

Test with mixing HTTP and HTTPS in a page sequence

```
<service name="OpenNMS-Web-Login" interval="30000" user-defined="true" status="on">
 <parameter key="retry" value="1"/>
 <parameter key="timeout" value="5000"/>
 <parameter key="rrd-repository" value="/opt/opennms/share/rrd/response"/>
 <parameter key="ds-name" value="opennmslogin"/>
 <parameter key="page-sequence">
    <page-sequence>
      <page scheme="http"
            host="ecomm.example.com"
            port="80"
            path="/ecomm/jsp/Login.jsp"
            virtual-host="ecomm.example.com"
            successMatch="eComm Login"
            timeout="10000"
            http-version="1.1"/>
      <page scheme="https"</pre>
            method="POST"
            host="ecomm.example.com" port="443"
            path="/ecomm/controller"
            virtual-host="ecomm.example.com"
            successMatch="requesttab select.gif"
            failureMessage="Login failed: ${1}"
            timeout="10000"
            http-version="1.1">
        <parameter key="action_name" value="XbtnLogin"/>
        <parameter key="session_timeout" value=""/>
        <parameter key="userid" value="EXAMPLE"/>
        <parameter key="password" value="econ"/>
      </page>
      <page scheme="http"
            host="ecomm.example.com" port="80"
            path="/econsult/controller"
            virtual-host="ecomm.example.com"
            successMatch="You have successfully logged out of eComm"
            timeout="10000" http-version="1.1">
        <parameter key="action_name" value="XbtnLogout"/>
      </page>
    </page-sequence>
 </parameter>
</service>
<monitor service="OpenNMS-Web-Login" class-name=
"org.opennms.netmgt.poller.monitors.PageSequenceMonitor"/>
```

Test login with dynamic credentials using session variables

```
<service name="OpenNMS-Web-Login" interval="30000" user-defined="true" status="on">
 <parameter key="retry" value="1"/>
 <parameter key="timeout" value="5000"/>
 <parameter key="rrd-repository" value="/opt/opennms/share/rrd/response"/>
 <parameter key="ds-name" value="opennmslogin"/>
 <parameter key="page-sequence">
    <page-sequence name="opennms-login-seq-dynamic-credentials">
      <page path="/opennms"</pre>
            port="80"
            virtual-host="demo.opennms.org"
            successMatch="(?s)User:.*<strong>(.*?)</strong>.*?Password:.*?
<strong>(.*?)</strong>">
        <session-variable name="username" match-group="1" />
        <session-variable name="password" match-group="2" />
      </page>
      <page path="/opennms/j_acegi_security_check"</pre>
            port="80"
            virtual-host="demo.opennms.org"
            method="POST"
            failureMatch="(?s)Your log-in attempt failed.*Reason: ([^<]*)"</pre>
            failureMessage="Login Failed: ${1}"
            successMatch="Log out">"
        <parameter key="j_username" value="${username}" />
        <parameter key="j_password" value="${password}" />
      </page>
      <page path="/opennms/event/index.jsp"</pre>
            port="80"
            virtual-host="demo.opennms.org"
            successMatch="Event Queries" />
      <page path="/opennms/j acegi logout"</pre>
            port="80"
            virtual-host="demo.opennms.org"
            successMatch="logged off" />
    </page-sequence>
 </parameter>
</service>
<monitor service="OpenNMS-Web-Login" class-name=
"org.opennms.netmgt.poller.monitors.PageSequenceMonitor"/>
```

```
<service name="OpenNMS-Demo-Login" interval="300000" user-defined="true" status="on">
 <parameter key="page-sequence">
    <page-sequence>
      <page path="/opennms"</pre>
            port="80"
            virtual-host="demo.opennms.org"
            successMatch="(?s)User:.*<strong>(.*?)</strong>.*?Password:.*?
<strong>(.*?)</strong>">
        <session-variable name="username" match-group="1" />
        <session-variable name="password" match-group="2" />
      </page>
      <page path="/opennms/j_acegi_security_check"</pre>
            port="80"
            virtual-host="demo.opennms.org"
            method="POST"
            successMatch="Log out">"
        <parameter key="j_username" value="${username}" />
        <parameter key="j_password" value="${password}" />
      </page>
      <page path="/opennms/j_acegi_logout"</pre>
            port="80"
            virtual-host="demo.opennms.org"
            successMatch="logged off" />
    </page-sequence>
 </parameter>
</service>
<monitor service="OpenNMS-Demo-Login" class-name=
"org.opennms.netmgt.poller.monitors.PageSequenceMonitor"/>
```

Example with per-page response times

```
<service name="OpenNMS-Login" interval="300000" user-defined="false" status="on">
 <parameter key="rrd-repository" value="/opt/opennms/share/rrd/response"/>
 <parameter key="rrd-base-name" value="opennmslogin"/>
 <parameter key="ds-name" value="overall"/>
 <parameter key="page-sequence">
    <page-sequence>
      <page path="/opennms/acegilogin.jsp"</pre>
            port="8980"
            ds-name="login-page"/>
      <page path="/opennms/event/index.jsp"</pre>
            port="8980"
            ds-name="event-page"/>
    </page-sequence>
 </parameter>
</service>
<monitor service="OpenNMS-Login" class-name=
"org.opennms.netmgt.poller.monitors.PageSequenceMonitor"/>
```

5.6.37. PercMonitor

This monitor tests the status of a PERC RAID array.

The monitor first polls the *RAID-Adapter-MIB::logicaldriveTable* (1.3.6.1.4.1.3582.1.1.2) to retrieve the status of the *RAID* array you want to monitor. If the value of the status object of the corresponding *logicaldriveEntry* is not 2, the array is degraded and the monitor further polls the *RAID-Adapter-MIB::physicaldriveTable* (1.3.6.1.4.1.3582.1.1.3) to detect the failed drive(s).



This monitor requires the outdated persnmpd software to be installed on the polled nodes. Please prefer using OmsaStorageMonitor monitor where possible.

Monitor facts

Class Name	org.opennms.netmgt.poller.monitors.PercMonitor
Remote Enabled	false (relies on SNMP configuration)

Configuration and Usage

Table 56. Monitor specific parameters for the PercMonitor

Paramete r	Description	Require d	Default value
аггау	The RAID array you want to monitor.	optional	0.0
port	The UDP port to connect to	optional	from snmp-config.xml

Examples

```
<!-- Monitor 1st RAID arrays using configuration from snmp-config.xml -->
<service name="PERC" interval="300000" user-defined="false" status="on" />
<monitor service="PERC" class-name="org.opennms.netmgt.poller.monitors.PercMonitor" />
```

5.6.38. Pop3Monitor

The *POP3* monitor tests for *POP3* service availability on a node. The monitor first tries to establish a *TCP* connection on the specified port. If a connection is established, a service banner should have been received. The monitor makes sure the service banner is a valid *POP3* banner (ie: starts with +0K). If the banner is valid, the monitor sends a QUIT *POP3* command and makes sure the service answers with a valid response (ie: a response that starts with +0K). The service is considered available if the service's answer to the QUIT command is valid.

The behaviour can be simulated with telnet:

```
$ telnet mail.opennms.org 110
Trying 192.168.0.100
Connected to mail.opennms.org.
Escape character is '^]'.
+OK <21860.1076718099@mail.opennms.org>
quit
+OK
Connection closed by foreign host.
```

Monitor facts

Class Name	org.opennms.netmgt.poller.monitors.Pop3Monitor
Remote Enabled	true

Configuration and Usage

Table 57. Monitor	r specific parameters	s for the Pop3Monitor
-------------------	-----------------------	-----------------------

Parameter	Description	Requir ed	Default value
port	TCP port to connect to.	option al	110
retry	Number of attempts to find the service available.	option al	0

Parameter	Description	Requir ed	Default value
strict- timeout	If set to true, makes sure that at least timeout milliseconds are elapsed between attempts.	option al	false

Examples

```
<service name="POP3" interval="300000" user-defined="false" status="on">
  <parameter key="retry" value="2"/>
  <parameter key="timeout" value="3000"/>
  <parameter key="rrd-repository" value="/var/lib/opennms/rrd/response"/>
  <parameter key="rrd-base-name" value="pop3"/>
  <parameter key="ds-name" value="pop3"/>
  </service>
<monitor service="POP3" class-name="org.opennms.netmgt.poller.monitors.Pop3Monitor"/>
```

5.6.39. PrTableMonitor

The *PrTableMonitor* monitor tests the **prTable** of a *Net-SNMP* agent.

prTable definition

A table containing information on running programs/daemons configured for monitoring in the snmpd.conf file of the agent. Processes violating the number of running processes required by the agent's configuration file are flagged with numerical and textual errors.

— UCD-SNMP-MIB

The monitor looks up the *prErrorFlag* entries of this table. If the value of a *prErrorFlag* entry in this table is set to "1" the service is considered unavailable.

prErrorFlag definition

An Error flag to indicate trouble with a process. It goes to 1 if there is an error, 0 if no error.

— UCD-SNMP-MIB

Monitor facts

Class Name	org.opennms.netmgt.poller.monitors.PrTableMonitor
Remote Enabled	false

Configuration and Usage

Parame ter	Description	Requir ed	Default value
port	The port to which connection shall be tried.		<pre>from snmp- config.xml</pre>
retries	Deprecated . Same as retry. Parameter retry takes precedence if both are set.	optiona l	<pre>from snmp- config.xml</pre>

Table 58. Monitor specific parameters for the PrTableMonitor

This monitor implements the Common Configuration Parameters.

Examples

UCD-SNMP-MIB

The UCD-SNMP-MIB may be found here.

5.6.40. RadiusAuthMonitor

This monitor allows to test the functionality of the RADIUS authentication system. The availability is tested by sending an *AUTH* packet to the *RADIUS server*. If a valid *ACCEPT* response is received, the *RADIUS* service is *up* and considered as available. This monitor implements placeholder substitution in parameter values.



To use this monitor it is required to install the *RADIUS* protocol for OpenNMS Meridian.

{apt-get,yum} install {opennms-package-base-name}-plugin-protocol-radius

The test is similar to test the behavior of a *RADIUS* server by evaluating the result with the command line tool radtest.

① The Access-Accept message which is evaluated by the monitor.

Monitor facts

Class Name	org.opennms.protocols.radius.monitor.RadiusAuthMonitor
Remote Enabled	false

Configuration and Usage

Table 59. Monitor specific parameters for the RadiusAuthMonitor

Paramet er	Description	Requ ired	Default value	Placeholder substitution
timeout	Time in milliseconds to wait for the <i>RADIUS</i> service.	optio nal	5000	No
retry	This is a placeholder for the second optional monitor parameter description.	optio nal	0	No
authport	<i>RADIUS</i> authentication port.	optio nal	1812	No
acctport	<i>RADIUS</i> accounting port.	optio nal	1813	No
user	Username to test the authentication	optio nal	OpenNMS	Yes
password	Password to test the authentication	optio nal	OpenNMS	Yes
secret	The <i>RADIUS</i> shared secret used for communication between the <i>client/NAS</i> and the <i>RADIUS</i> server.	optio nal	secret	Yes
authtype	<i>RADIUS</i> authentication type. The following authentication types are supported: chap, pap, mschapv1, mschapv2, eapmd5, eapmschapv2, eapttls	optio nal	рар	No
nasid	The Network Access Server identifier originating the <i>Access-Request</i> .	optio nal	opennms	Yes

Paramet er	Description	Requ ired	Default value	Placeholder substitution
inner- protocol	When using EAP-TTLS authentication, this property indicates the tunnelled authentication type. Only pap is currently supported.	optio nal	рар	No
inner- user	Username for the tunnelled pap authentication when using EAP-TTLS.	optio nal	Inner- OpenNMS	Yes

Examples

Example configuration how to configure the monitor in the poller-configuration.xml.

5.6.41. SmbMonitor

This monitor is used to test the *NetBIOS over TCP/IP* name resolution in *Microsoft Windows* environments. The monitor tries to retrieve a *NetBIOS name* for the IP address of the interface. Name services for *NetBIOS* in *Microsoft Windows* are provided on port 137/UDP or 137/TCP.

The service uses the IP address of the interface, where the monitor is assigned to. The service is *up* if for the given IP address a *NetBIOS name* is registered and can be resolved.

For troubleshooting see the usage of the Microsoft Windows command line tool nbtstat or on Linux nmblookup.



Microsoft deprecated the usage of *NetBIOS*. Since Windows Server 2000 *DNS* is used as the default name resolution.

Monitor facts

Class Name	org.opennms.netmgt.poller.monitors.SmbMonitor
------------	---

Configuration and Usage

Table 60. Monitor specific parameters for the SmbMonitor

Parameter	Description	Require d	Default value
do-node- status	Try to get the <i>NetBIOS</i> node status type for the given address	optional	true

This monitor implements the Common Configuration Parameters.

Examples

Some example configuration how to configure the monitor in the poller-configuration.xml.

```
<service name="SMB" interval="300000" user-defined="false" status="on">
  <parameter key="retry" value="1"/>
  <parameter key="timeout" value="3000"/>
  </service>
<monitor service="SMB" class-name="org.opennms.netmgt.poller.monitors.SmbMonitor"/>
```

5.6.42. SmtpMonitor

The SMTP monitor tests for SMTP service availability on a node. The monitor first tries to establish a TCP connection on the specified port. If a connection is established, a service banner should have been received. The monitor makes sure the service banner is a valid SMTP banner (starts with "220"). If the banner is valid, the monitor sends a *HELO* SMTP command, identifying itself with the hostname of the OpenNMS server, and makes sure the service answers with a valid response (starts with "250"). If the response to the *HELO* is valid, the monitor issues a *QUIT* SMTP command. The service is considered available if the service's answer to the *HELO* command is valid (starts with "221").

The behaviour can be simulated with telnet or netcat:

```
$ nc -v gmail-smtp-in.l.google.com 25
Ncat: Version 7.60 ( https://nmap.org/ncat )
Ncat: Connected to 2607:f8b0:4002:c06::1a:25.
220 mx.google.com ESMTP j17-v6si13545102ywb.87 - gsmtp
HELO opennms.com
250 mx.google.com at your service
QUIT
221 2.0.0 closing connection j17-v6si13545102ywb.87 - gsmtp
```

Monitor facts

Class Name	org.opennms.netmgt.poller.monitors.SmtpMonitor
Remote Enabled	true

Configuration and Usage

Table 61. Monitor specific parameters for the SmtpMonitor

Paramet er	Description	Requir ed	Default value
port	TCP port to connect to.	optiona l	25
retry	Number of attempts to find the service available.	optiona l	0
timeout	Timeout in milliseconds for the underlying socket's <i>connect</i> and <i>read</i> operations.	optiona l	3000

Examples

```
<service name="SMTP" interval="30000" user-defined="false" status="on">
  <parameter key="retry" value="1" />
  <parameter key="timeout" value="3000" />
  <parameter key="port" value="25" />
  <parameter key="rrd-repository" value="${install.share.dir}/rrd/response" />
  <parameter key="rrd-base-name" value="smtp" />
  <parameter key="ds-name" value="smtp" />
  </service>
<monitor service="SMTP" class-name="org.opennms.netmgt.poller.monitors.SmtpMonitor" />
```

5.6.43. SnmpMonitor

The SNMP monitor gives a generic possibility to monitor states and results from SNMP agents. This monitor has two basic operation modes:

- Test the response value of one specific OID (scalar object identifier);
- Test multiple values in a whole *table*.

To decide which mode should be used, the walk and match-all parameters are used.

See the Operating mode selection'' and Monitor specific parameters for the SnmpMonitor'' tables below for more information about these operation modes.

Table 62. Operating mode selection

walk	match- all	Operating mode
true true tabular, all values must match		tabular, all values must match
	false	tabular, any value must match
	count	specifies that the value of at least minimum and at most maximum objects encountered in
fals e	true	scalar
C	false	scalar
	count	tabular, between minimum and maximum values must match



This monitor can't be used on the OpenNMS Meridian Remote Poller. It is currently not possible for the Remote Poller to have access to the SNMP configuration of a central OpenNMS Meridian.

Monitor facts

Class Name	org.opennms.netmgt.poller.monitors.SnmpMonitor		
Remote Enabled	false		

When the monitor is configured to persist the response time, it will count the total amount of time spent until a successful response is obtained, including the retries. It won't store the time spent during the last successful attempt.

Configuration and Usage

Table 63. Monitor specific parameters for the SnmpMonitor

Paramet er	Description	Requ ired	Default value
hex	Specifies that the value monitored should be compared against its hexadecimal representation. Useful when the monitored value is a string containing non-printable characters.	optio nal	false

Paramet er	Description	Requ ired	Default value
match-all	Can be set to: count: specifies that the value of at least minimum and at most maximum objects encountered in the walk must match the criteria specified by operand and operator. true and walk is set to true: specifies that the value of every object encountered in the walk must match the criteria specified by the operand and operator parameters. false and walk is set to true: specifies that the value of any object encountered in the walk must match the criteria specified by the operand and operator parameters.	optio nal	true
maximum	Valid only when match-all is set to count, otherwise ignored. Should be used in conjunction with the minimum parameter. Specifies that the value of <i>at most</i> maximum objects encountered in the walk must meet the criteria specified by the operand and operator parameters.	optio nal	0
minimum	Valid only when match-all is set to count, otherwise ignored. Should be used in conjunction with the maximum parameter. Specifies that the value of <i>at least</i> minimum objects encountered in the walk must meet the criteria specified by the operand and operator parameters.	optio nal	0
oid	The object identifier of the <i>MIB</i> object to monitor. If no other parameters are present, the monitor asserts that the agent's response for this object must include a valid value (as opposed to an error, no-such-name, or end-of-view condition) that is non-null.	optio nal	.1.3.6.1.2.1.1.2.0 (SNMPv2- MIB::SysObjectID)
operand	The value to be compared against the observed value of the monitored object. Note: Comparison will always succeed if either the operand or operator parameter isn't set and the monitored value is non- null.	optio nal	-

Paramet er	Description	Requ ired	Default value
operator	The operator to be used for comparing the monitored object against the operand parameter. Must be one of the following symbolic operators: \$lt; (<): Less than. Both operand and observed object value must be numeric. \$gt; (>): Greater than. Both operand and observed object value must be numeric. $\$lt;= (\Leftarrow)$: Less than or equal to. Both operand and observed object value must be numeric. \$gt;= (>=): Greater than or equal to. Both operand and observed object value must be numeric. =: Equal to. Applied in numeric context if both operand and observed object value are numeric, otherwise in string context as a case-sensitive exact match. !=: Not equal to. Applied in numeric context if both operand and observed object value are numeric, otherwise in string context as a case-sensitive exact match. *: Regular expression match. Always applied in string context. Note: Comparison will always succeed if either the operand or operator parameter isn't set and the monitored value is non-null. Keep in mind that you need to escape all < and > characters as XML entities ($\$lt$; and $\$gt$; respectively)	optio nal	
port	Destination port where the SNMP requests shall be sent.	optio nal	<pre>from snmp-config.xml</pre>
reason- template	A user-provided template used for the monitor's reason code if the service is unvailable. Defaults to a reasonable value if unset. See below for an explanation of the possible template parameters.	optio nal	depends on operation mode
retries	Deprecated Same as retry. Parameter retry takes precedence if both are set.	optio nal	<pre>from snmp-config.xml</pre>
walk	<pre>false: Sets the monitor to poll for a scalar object unless if the match-all parameter is set to count, in which case the match-all parameter takes precedence. true: Sets the monitor to poll for a tabular object where the match-all parameter defines how the tabular object's values must match the criteria defined by the operator and operand parameters. See also the match-all, minimum, and maximum parameters.</pre>	optio nal	false

Variable	Description
\${hex}	Value of the hex parameter.
\${ipaddr}	IP address polled.
\${matchAll}	Value of the match-all parameter.
\${matchCount}	When match-all is set to count, contains the number of matching instances encountered.
\${maximum}	Value of the maximum parameter.
\${minimum}	Value of the minimum paramater.
\${observedValue }	Polled value that made the monitor succeed or fail.
\${oid}	Value of the oid parameter.
\${operand}	Value of the operand parameter.
\${operator}	Value of the operator parameter.
\${port}	Value of the port parameter.
\${retry}	Value of the retry parameter.
<pre>\${timeout}</pre>	Value of the timeout parameter.
\${walk}	Value of the walk parameter.

Table 64. Variables which can be used in the reason-template parameter

Example for monitoring scalar object

As a working example we want to monitor the thermal system fan status which is provided as a scalar object ID.

```
cpqHeThermalSystemFanStatus .1.3.6.1.4.1.232.6.2.6.4.0
```

The manufacturer *MIB* gives the following information:

```
SYNTAX INTEGER {
    other
            (1),
    ok
             (2),
    degraded (3),
    failed (4)
}
ACCESS read-only
DESCRIPTION
"The status of the fan(s) in the system.
This value will be one of the following:
other(1)
Fan status detection is not supported by this system or driver.
ok(2)
All fans are operating properly.
degraded(3)
A non-required fan is not operating properly.
failed(4)
A required fan is not operating properly.
If the cpqHeThermalDegradedAction is set to shutdown(3) the
system will be shutdown if the failed(4) condition occurs."
```

The SnmpMonitor is configured to test if the fan status returns *ok(2)*. If so, the service is marked as *up*. Any other value indicates a problem with the thermal fan status and marks the service *down*.

Example SnmpMonitor as HP InsightManager fan monitor in poller-configuration.xml

- ① Scalar object ID to test
- 2 Operator for testing the response value
- ③ Integer 2 as operand for the test

④ Encode *MIB* status in the reason code to give more detailed information if the service goes down

Example test SNMP table with all matching values

The second mode shows how to monitor values of a whole SNMP table. As a practical use case the status of a set of physical drives is monitored. This example configuration shows the status monitoring from the CPQIDA-MIB.

We use as a scalar object id the physical drive status given by the following tabular OID:

```
cpqDaPhyDrvStatus .1.3.6.1.4.1.232.3.2.5.1.1.6
```

Description of the cpqDaPhyDrvStatus object id from CPQIDA-MIB

```
SYNTAX INTEGER {
    other
                      (1),
    ok
                      (2),
    failed
                      (3),
    predictiveFailure (4)
}
ACCESS read-only
DESCRIPTION
Physical Drive Status.
This shows the status of the physical drive.
The following values are valid for the physical drive status:
other (1)
 Indicates that the instrument agent does not recognize
 the drive. You may need to upgrade your instrument agent
 and/or driver software.
ok (2)
 Indicates the drive is functioning properly.
failed (3)
 Indicates that the drive is no longer operating and
 should be replaced.
predictiveFailure(4)
 Indicates that the drive has a predictive failure error and
 should be replaced.
```

The configuration in our monitor will test all physical drives for status *ok(2)*.

Example SnmpMonitor as HP Insight physical drive monitor in poller-configuration.xml

① OID for SNMP table with all physical drive states

- ② Enable *walk mode* to test every entry in the table against the test criteria
- ③ Test operator for integer
- ④ Integer 2 as operand for the test
- ⑤ Test in *walk mode* has to be passed for every entry in the table
- 6 Encode *MIB* status in the reason code to give more detailed information if the service goes down

Example test SNMP table with all matching values

This example shows how to use the SnmpMonitor to test if the number of static routes are within a given boundary. The service is marked as *up* if at least 3 and at maxium 10 static routes are set on a network device. This status can be monitored by polling the table *ipRouteProto* from the RFC1213-MIB2.

ipRouteProto 1.3.6.1.2.1.4.21.1.9

The *MIB* description gives us the following information:

```
SYNTAX INTEGER {
    other(1),
    local(2),
    netmgmt(3),
    icmp(4),
    egp(5),
    ggp(6),
    hello(7),
    rip(8),
    is-is(9),
    es-is(10),
    ciscoIgrp(11),
    bbnSpfIgp(12),
    ospf(13),
    bgp(14)
}
ACCESS read-only
DESCRIPTION
"The routing mechanism via which this route was learned.
Inclusion of values for gateway routing protocols is not
intended to imply that hosts should support those protocols."
```

To monitor only local routes, the test should be applied only on entries in the *ipRouteProto* table with value 2. The number of entries in the whole *ipRouteProto* table has to be counted and the boundaries on the number has to be applied.

Example SnmpMonitor used to test if the number of local static route entries are between 3 or 10.

```
<service name="All-Static-Routes" interval="30000" user-defined="false" status="on">
    <parameter key="oid" value=".1.3.6.1.2.1.4.21.1.9" />①
    <parameter key="walk" value="true" />②
    <parameter key="operator" value="=" />③
    <parameter key="operand" value="=" />④
    <parameter key="match-all" value="count" />⑤
    <parameter key="match-all" value="count" />⑤
    <parameter key="minimum" value="3" />⑥
    <parameter key="maximum" value="10" />⑦
    </service>
```

- ① OID for SNMP table *ipRouteProto*
- 2 Enable *walk mode* to test every entry in the table against the test criteria
- **③** Test operator for integer
- ④ Integer 2 as operand for testing local route entries
- (5) Test in *walk mode* has is set to count to get the number of entries in the table regarding operator and operand

6 Lower count boundary set to 3

⑦ High count boundary is set to 10

5.6.44. SshMonitor

The *SshMonitor* tests the availability of a *SSH* service. During the poll an attempt is made to connect on the specified port. If the connection request is successful, then the service is considered up. Optionaly, the banner line generated by the service may be parsed and compared against a pattern before the service is considered up.

Monitor facts

Class Name	org.opennms.netmgt.poller.monitors.SshMonitor
Remote Enabled	true

Configuration and Usage

Table 65. Monitor specific parameters for the SshMonitor

Paramet er	Description	Requi red	Default value
banner	Regular expression to be matched against the service's banner.	option al	-
client- banner	The client banner that OpenNMS Meridian will use to identify itself on the service.	option al	SSH-1.99- OpenNMS_1.5
match	Regular expression to be matched against the service's banner. Deprecated, please use the banner parameter instead. Note that this parameter takes precedence over the banner parameter, though.	option al	-
port	<i>TCP</i> port to which <i>SSH</i> connection shall be tried.	option al	22
retry	Number of attempts to establish the <i>SSH</i> connnection.	option al	0

This monitor implements the Common Configuration Parameters.

Examples

5.6.45. SSLCertMonitor

This monitor is used to test if a SSL certificate presented by a remote network server are valid. A certificate is invalid if its initial time is prior to the current time, or if the current time is prior to 7 days (configurable) before the expiration time.

You can simulate the behavior by running a command like this:

```
echo | openssl s_client -connect <site>:<port> 2>/dev/null | openssl x509 -noout
-dates
```

The output shows you the time range a certificate is valid:

notBefore=Dec 24 14:11:34 2013 GMT notAfter=Dec 25 10:37:40 2014 GMT

You can configure a threshold in days applied on the **notAfter** date.

While the monitor is mainly useful for plain SSL sockets, the monitor does provide limited support for STARTTLS protocols by providing the user with the ability to specify a STARTTLS message to be sent prior to the SSL negotiation and a regular expression to match to the response received from the server. An additional preliminary message and response regular expression pair is available for protocols that require it (such as XMPP).

This monitor implements placeholder substitution in parameter values.

Monitor facts

Class Name	org.opennms.netmgt.poller.monitors.SSLCertMonitor
Remote Enabled	true

Configuration and Usage

Table 66. Monitor specific parameters for the SSLCertMonitor

Parameter	Description	Requ ired	Default value	Placeholde r substition
port	TCP port for the service with SSL certificate.	requi red	-1	No
retry	Number of attempts to get the certificate state	optio nal	0	No
days	Number of days before the certificate expires that we mark the service as failed.	optio nal	7	No
server-name	This is the DNS hostname to send as part of the <i>TLS</i> negotiation, known as server name indication (<i>SNI</i>) (See: RFC3546 section 3.1)	optio nal	-	No
starttls- preamble	Preliminary message to send to server prior to STARTTLS command.	optio nal	~ ~	Yes
starttls- preamble- response	Regular expression which must match response to preliminary message sent to server prior to STARTTLS command.	optio nal		Yes
starttls-start	STARTTLS command.	optio nal	~ ~	Yes
starttls- start-response	Regular expression which must match response to STARTTLS command sent to server.	optio nal	~ ~	Yes

Table 67. Variables which can be passed in the configuration for server-name

Variable	Description
\${ipaddr}	The node's IP-Address
\${nodeid}	The node ID
<pre>\${nodelabel}</pre>	Label of the node the monitor is associated to.
\${svcname}	The service name



The monitor has limited support for communicating on other protocol layers above the SSL session layer. The STARTTLS support has only been tested with a single XMPP server. It is not known if the same approach will prove useful for other use cases, like sending a Host header for HTTPS, or issue a STARTTLS command for IMAP, POP3, SMTP, FTP, LDAP, or NNTP.

Examples

The following examples show how to monitor SSL certificates on services like IMAPS, SMTPS and

HTTPS as well as an example use of the STARTTLS feature for XMPP. If the certificates expire within 30 days the service goes down and indicates this issue in the reason of the monitor. In this example the monitoring interval is reduced to test the certificate every 2 hours (7,200,000 ms). Configuration in poller-configuration.xml is as the following:

```
<service name="SSL-Cert-IMAPS-993" interval="7200000" user-defined="false" status="on</pre>
">
    <parameter key="retry" value="2"/>
    <parameter key="timeout" value="2000"/>
    <parameter key="port" value="993"/>
    <parameter key="days" value="30"/>
</service>
<service name="SSL-Cert-SMTPS-465" interval="7200000" user-defined="false" status="on</pre>
">
    <parameter key="retry" value="2"/>
    <parameter key="timeout" value="2000"/>
    <parameter key="port" value="465"/>
    <parameter key="days" value="30"/>
</service>
<service name="SSL-Cert-HTTPS-443" interval="7200000" user-defined="false" status="on</pre>
">
    <parameter key="retry" value="2"/>
    <parameter key="timeout" value="3000"/>
    <parameter key="port" value="443"/>
    <parameter key="days" value="30"/>
    <parameter key="server-name" value="${nodelabel}.example.com"/>
</service>
<service name="XMPP-STARTTLS-5222" interval="7200000" user-defined="false" status="on</pre>
">
    <parameter key="retry" value="2"/>
    <parameter key="timeout" value="3000"/>
    <parameter key="port" value="5222"/>
    <parameter key="days" value="30"/>
    <parameter key="starttls-preamble" value="<stream:stream</pre>
xmlns:stream='http://etherx.jabber.org/streams' xmlns='jabber:client' to='{ipAddr}'
version='1.0'>"/>
    <parameter key="starttls-preamble-response" value="^.*starttls.*$"/>
    <parameter key="starttls-start" value="<starttls</pre>
xmlns='urn:ietf:params:xml:ns:xmpp-tls'/>"/>
    <parameter key="starttls-start-response" value="^.*starttls.*$"/>
</service>
<monitor service="SSL-Cert-IMAPS-993" class-name=
"org.opennms.netmgt.poller.monitors.SSLCertMonitor" />
<monitor service="SSL-Cert-SMTPS-465" class-name=
"org.opennms.netmgt.poller.monitors.SSLCertMonitor" />
<monitor service="SSL-Cert-HTTPS-443" class-name=
"org.opennms.netmgt.poller.monitors.SSLCertMonitor" />
<monitor service="XMPP-STARTTLS-5222" class-name=
"org.opennms.netmgt.poller.monitors.SSLCertMonitor" />
```

5.6.46. StrafePingMonitor

This monitor is used to monitor packet delay variation to a specific endpoint using ICMP. The main

use case is to monitor a *WAN* end point and visualize packet loss and *ICMP* packet round trip time deviation. The *StrafePingMonitor* performs multiple *ICMP echo requests* (ping) and stores the response-time of each as well as the packet loss, in a *RRD* file. Credit is due to Tobias Oetiker, as this graphing feature is an adaptation of the <u>SmokePing</u> tool that he developed.




Figure 31. Visualization of a graph from the StrafePingMonitor

Monitor facts

Class Name	org.opennms.netmgt.poller.monitors.StrafePingMonitor
Remote Enabled	false

Configuration and Usage

Monitor specific parameters for the StrafePingMonitor

Parameter	Description	Requi red	Default value
timeout	Time in milliseconds to wait before assuming that a packet has not responded	option al	800
retry	The number of retries to attempt when a packet fails to respond in the given timeout	option al	2
ping-count	The number of pings to attempt each interval	requir ed	20
failure- ping-count	The number of pings that need to fail for the service to be considered down	requir ed	20
allow- fragmentatio n	Whether to set the "Don't Fragment" bit on outgoing packets	option al	true
dscp	DSCP traffic-control value.	option al	0

Parameter	Description	Requi red	Default value
packet-size	Number of bytes of the ICMP packet to send.	option al	64
wait- interval	Time in milliseconds to wait between each <i>ICMP echo-</i> <i>request</i> packet	requir ed	50
rrd- repository	The location to write <i>RRD data</i> . Generally, you will not want to change this from default	requir ed	\$OPENNMS_HOME/share/ rrd/response
rrd-base- name	The name of the RRD file to write (minus the extension, .rrd or .jrb)	requir ed	strafeping

Examples

The *StrafePingMonitor* is typically used on WAN connections and not activated for every ICMP enabled device in your network. Further this monitor is much I/O heavier than just a simple RRD graph with a single ICMP response time measurement. By default you can find a separate *poller package* in the 'poller-configuration.xml' called *strafer*. Configure the include-range or a filter to enable monitoring for devices with the service *StrafePing*.



Don't forget to assign the service *StrafePing* on the IP interface to be activated.

The following example enables the monitoring for the service *StrafePing* on IP interfaces in the range 10.0.0.1 until 10.0.0.20. Additionally the Nodes have to be in a *surveillance category* named Latency.

```
<package name="strafer" >
  <filter>categoryName == 'Latency'</filter>
  <include-range begin="10.0.0.1" end="10.0.0.20"/>
  <rrd step="300">
    <rra>RRA:AVERAGE:0.5:1:2016</rra>
     <rra>RRA: AVERAGE: 0.5:12:1488</rra>
    <rra>RRA: AVERAGE: 0.5:288:366</rra>
    <rra>RRA:MAX:0.5:288:366</rra>
    <rra>RRA:MIN:0.5:288:366</rra>
  </rrd>
  <service name="StrafePing" interval="300000" user-defined="false" status="on">
     <parameter key="retry" value="0"/>
    <parameter key="timeout" value="3000"/>
    <parameter key="ping-count" value="20"/>
    <parameter key="failure-ping-count" value="20"/>
    <parameter key="wait-interval" value="50"/>
    <parameter key="rrd-repository" value="/opt/opennms/share/rrd/response"/>
    <parameter key="rrd-base-name" value="strafeping"/>
  </service>
  <downtime interval="30000" begin="0" end="300000"/>
  <downtime interval="300000" begin="300000" end="43200000"/>
  <downtime interval="600000" begin="43200000" end="432000000"/>
  <downtime begin="432000000" delete="true"/>
</package>
<monitor service="StrafePing" class-name=
"org.opennms.netmgt.poller.monitors.StrafePingMonitor"/>
```

5.6.47. TcpMonitor

This monitor is used to test IP Layer 4 connectivity using *TCP*. The monitor establishes an *TCP* connection to a specific port. To test the availability of the service, the greetings banner of the application is evaluated. The behavior is similar to a simple test using the telnet command as shown in the example.

Simulating behavior of the monitor with telnet

```
root@vagrant:~# telnet 127.0.0.1 22
Trying 127.0.0.1...
Connected to 127.0.0.1.
Escape character is '^]'.
SSH-2.0-OpenSSH_6.6.1p1 Ubuntu-2ubuntu2 (1)
```

① Service greeting banner

Monitor facts

Class Name	org.opennms.netmgt.poller.monitors.TcpMonitor
Remote Enabled	true

Configuration and Usage

Table 68. Monito	or specific parameter	s for the TcpMonitor
------------------	-----------------------	----------------------

Param eter	Description	Requi red	Default value
port	TCP port of the application.	requir ed	-1
retry	Number of retries before the service is marked as <i>down</i> .	option al	0
banner	Evaluation of the service connection banner with regular expression. By default any banner result is valid.	option al	*

This monitor implements the Common Configuration Parameters.

Examples

This example shows to test if the ICA service is available on *TCP* port 1494. The test evaluates the connection banner starting with ICA.

```
<service name="TCP-Citrix-ICA" interval="300000" user-defined="false" status="on">
    <parameter key="retry" value="0" />
    <parameter key="banner" value="ICA" />
    <parameter key="port" value="1494" />
    <parameter key="timeout" value="3000" />
    <parameter key="timeout" value="3000" />
    <parameter key="rrd-repository" value="/var/lib/opennms/rrd/response" />
    <parameter key="rrd-base-name" value="tcpCitrixIca" />
    <parameter key="ds-name" value="tcpCitrixIca" />
    </parameter key="Citrix-ICA" class-name=
"org.opennms.netmgt.poller.monitors.TcpMonitor" />
```

5.6.48. SystemExecuteMonitor

If it is required to execute a system call or run a script to determine a service status, the *SystemExecuteMonitor* can be used. It is calling a script or system command, if required it provides additional arguments to the call. To determine the status of the service the *SystemExecuteMonitor* can rely on 0 or a *non-0* exit code of system call. As an alternative, the output of the system call can be matched against a banner. If the banner is part of the output the status is interpreted as up. If the banner is not available in the output the status is determined as down.

Monitor facts

Class Name	org.opennms.netmgt.poller.monitors.SystemExecuteMonitor
Remote Enabled	true

Configuration and Usage

Param eter	Description	Requi red	Default value
script	The system-call to execute.	requir ed	-
args	The arguments to hand over to the system-call. It supports variable replacement, see below.	option al	-
banner	A string that is match against the output of the system-call. If the output contains the banner, the service is determined as <i>UP</i> .	option al	-

Table 69. Monitor specific parameters for the SystemExecuteMonitor

The parameter args supports variable replacement for the following set of variables.

 \bigcirc

Providing always a script output with a more detailed test error makes it easier to diagnose the problem when the nodeLostDown event occurs.

This monitor implements the Common Configuration Parameters.

Table 70. Variables which can be used in the configuration

Variable	Description
<pre>\${timeout}</pre>	Timeout in milliseconds, based on config of the service.
<pre>\${timeoutsec}</pre>	Timeout in seconds, based on config of the service.
\${retry}	Amount of retries based on config of the service.
\${svcname}	Service name based on the config of the service.
\${ipaddr}	IP-address of the interface the service is bound to.
\${nodeid}	Nodeid of the node the monitor is associated to.
<pre>\${nodelabel}</pre>	Nodelabel of the node the monitor is associated to.

Examples

Placeholder usage

```
<parameter key="args" value="-i ${ipaddr} -t ${timeout}"/>
<parameter key="args" value="http://${nodelabel}/${svcname}/static"/>
```

Exit status example

```
<service name="Script_Example" interval="300000" user-defined="true" status="on">
    <parameter key="script" value="/opt/opennms/contrib/Script_Example.sh"/>
    <parameter key="timeout" value="5000"/>
</service>
```

```
<monitor service="Script_Example" class-name=
"org.opennms.netmgt.poller.monitors.SystemExecuteMonitor"/>
```

```
#!/usr/bin/env bash
# ...some test logic
RESULT="TEST OK"
if [[ "TEST OK" == "${RESULT}" ]]; then
    echo "This test passed"
    exit 0
else
    echo "This test failed because of ..."
    exit 1
fi
```

Banner matching example

```
<service name="Script_Example" interval="300000" user-defined="true" status="on">
    <parameter key="script" value="/opt/opennms/contrib/Script_Example.sh"/>
    <parameter key="banner" value="PASSED"/>
    <parameter key="timeout" value="5000"/>
</service>
</monitor service="Script_Example" class-name=
"org.opennms.netmgt.poller.monitors.SystemExecuteMonitor"/>
```

```
#!/usr/bin/env bash
# ...some test logic
RESULT="TEST OK"
if [[ "TEST OK" == "${RESULT}" ]]; then
    echo "PASSED"
else
    echo "FAILED"
fi
```

SystemExecuteMonitor vs GpMonitor

The SystemExecuteMonitor is the successor of the GpMonitor. The main differences are:

- Variable replacement for the parameter args
- There are no fixed arguments handed to the system-call
- The SystemExecuteMonitor supports RemotePoller deployment

To migrate services from the *GpMonitor* to the *SystemExecuteMonitor* it is required to alter the parameter args. To match the arguments called hoption for the hostAddress and toption for the timeoutInSeconds. The args string that matches the *GpMonitor* call looks like this:

<parameter key="args" value="--hostname \${ipaddr} --timeout \${timeoutsec}" />

To migrate the GpMonitor parameters hoption and toption just replace the --hostname and --timeout directly in the args key.

5.6.49. VmwareCimMonitor

This monitor is part of the VMware integration provided in *Provisiond*. The monitor is specialized to test the health status provided from all *Host System* (host) sensor data.

This monitor is only executed if the host is in power state *on*.

This monitor requires to import hosts with *Provisiond* and the *VMware* import. OpenNMS Meridian requires network access to *VMware vCenter* and the hosts. To get the sensor data the credentials from *vmware-config.xml* for the responsible *vCenter* is used. The following asset fields are filled from *Provisiond* and is provided by *VMware* import feature: *VMware Management Server, VMware Managed Entity Type* and the *foreignId* which contains an internal *VMware vCenter Identifier*.

The global health status is evaluated by testing all available host sensors and evaluating the state of each sensor. A sensor state could be represented as the following:

- Unknown(0)
- OK(5)
- Degraded/Warning(10)
- Minor failure(15)
- Major failure(20)
- Critical failure(25)
- Non-recoverable error(30)

The service is *up* if **all** sensors have the status *OK*(*5*). If any sensor gives another status then *OK*(*5*) the service is marked as *down*. The monitor error reason contains a list of all sensors which not



In case of using Distributed Power Management the *standBy* state forces a service *down*. The health status is gathrered with a direct connection to the host and in stand by this connection is unavailable and the service is *down*. To deal with stand by states, the configuration *ignoreStandBy* can be used. In case of a stand by state, the service is considered as *up*.

state can be changed see the ignoreStandBy configuration parameter.

Monitor facts

Class Name	org.opennms.netmgt.poller.monitors.VmwareCimMonitor
Remote Enabled	false

Configuration and Usage

Table 71. Monitor specific parameters for the VmwareCimMonitor

Parameter	Description	Require d	Default value
retry	Number of retries before the service is marked as down.	optional	0
ignoreStandBy	Treat power state <i>standBy</i> as <i>up</i> .	optional	false

This monitor implements the Common Configuration Parameters.

Examples

Some example configuration how to configure the monitor in the poller-configuration.xml.

5.6.50. VmwareMonitor

This monitor is part of the VMware integration provided in *Provisiond* and test the power state of a virtual machine (VM) or a host system (host). If the power state of a VM or host is *poweredOn* the service is *up*. The state *off* the service on the VM or Host is marked as *down*. By default *standBy* is also considered as *down*. In case of using Distributed Power Management the *standBy* state can be changed see the ignoreStandBy configuration parameter.



The information for the status of a virtual machine is collected from the responsible *VMware vCenter* using the credentials from the *vmware-config.xml*. It is also required to get specific asset fields assigned to an imported virtual machine and host system. The following asset fields are required, which are populated by the *VMware* integration in *Provisiond: VMware Management Server, VMware Managed Entity Type* and the *foreignId* which contains an internal *VMware vCenter Identifier*.

Monitor facts

Class Name	org.opennms.netmgt.poller.monitors.VmwareMonitor
Remote Enabled	false

Configuration and Usage

Paramet	Description	Requi	Default
er		red	value
retry	Number of retries before the service is marked as <i>down</i> .	option al	0
ignoreSta ndBy	Treat power state <i>standBy</i> as <i>up</i> .	option al	false
reportAla	Checks for unacknowledged vSphere alarms for a given comma-	option	~ ~
rms	separated list of severities (red, yellow, green, gray).	al	

This monitor implements the Common Configuration Parameters.

Examples

Some example configuration how to configure the monitor in the poller-configuration.xml. With this configuration the monitor will go *down* if any unacknowledged vSphere alarms with severity red or yellow exist for this managed entity.

5.6.51. WebMonitor

WebMonitor is a clone of HttpMonitor, that uses a different underlying library for doing HTTP connections. WebMonitor uses Apache HttpClient, which acts more like a real browser (follows redirects, etc.) than HttpMonitor.

Monitor facts

Class Name org.opennms.netmgt.poller.monitors.WebMonitor

Configuration and Usage

Note that all parameters listed are optional.

Table 73	Configuration	parameters
----------	---------------	------------

Parameter	Description	Default value
use-system-proxy	Specifies that system-wide proxy settings be used. The system proxy settings can be configured via system properties.	false
scheme	Protocol/scheme to use.	http, https
port	The port to connect to.	80
path	The path of the URL to request (e.g., /store/index.html).	
queryString	The query string to add to the URL after a ? (e.g., foo=bar&baz=zot)	
timeout	The connection/socket timeout.	
user-agent	The User-Agent: header to send.	
virtual-host	The Host: header to send.	
http-1.0	True/false whether to use HTTP 1.0 or 1.1.	
header_#/header_#_ value	Headers to add	
use-ssl-filter	Defaults to false, if true it will trust self-signed certificates.	false
auth-enabled	Whether to enable basic authentication.	
auth-user	The username for basic authentication.	
auth-password	The password	
auth-preemptive	Whether to send basic authentication even if the site did not ask for it.	true
response-text	The response text to look for.	
response-range	What HTTP status ranges are considered success.	100-399

5.6.52. Win32ServiceMonitor

The Win32ServiceMonitor enables OpenNMS Meridian to monitor the running state of any Windows service. The service status is monitored using the Microsoft Windows® provided SNMP agent providing the LAN Manager MIB-II. For this reason it is required the SNMP agent and OpenNMS Meridian is correctly configured to allow queries against part of the *MIB* tree. The status of the service is monitored by polling the

svSvcOperatingState = 1.3.6.1.4.1.77.1.2.3.1.3

of a given service by the display name.

Monitor facts

Class Name	<pre>org.opennms.netmgt.poller.monitors.Win32ServiceMonitor</pre>
Remote Enabled	false

Configuration and Usage

			• •	
Table 74 Monitor s	necitic	narameters	for the	Win32ServiceMonitor
10010 / 1. 10000000 0	pecque	parameters	joi the	

Paramet	Description	Requi	Default
er		red	value
service-	The name of the service, this should be the exact name of the Windows service to monitor as it appears in the Services <i>MSC snap-</i>	requir	Server
name	<i>in</i> . Short names such as you might use with net start will not work here.	ed	

This monitor implements the Common Configuration Parameters.



Non-English Windows The service-name is sometime encoded in languages other than English. Like in French, the *Task Scheduler* service is *Planificateur de tâche*. Because of the "â" (non-English character), the OID value is encoded in hexa (0x50 6C 61 6E 69 66 69 63 61 74 65 75 72 20 64 65 20 74 C3 A2 63 68 65 73).

Troubleshooting

If you've created a *Win32ServiceMonitor* poller and are having difficulties with it not being monitored properly on your hosts, chances are there is a difference in the name of the service you've created, and the actual name in the registry.

For example, I need to monitor a process called *Example Service* on one of our production servers. I retrieve the *Display name* from looking at the service in service manager, and create an entry in the poller-configuration.xml files using the exact name in the *Display name* field.

However, what I don't see is the errant space at the end of the service display name that is revealed when doing the following:

snmpwalk -v 2c -c <communitystring> <hostname> .1.3.6.1.4.1.77.1.2.3.1.1

This provides the critical piece of information I am missing:

iso.3.6.1.4.1.77.1.2.3.1.1.31.83.116.97.102.102.119.97.114.101.32.83.84.65.70.70.86.73
.69.87.32.66.97.99.107.103.114.111.117.110.100.32 = STRING: "Example Service "



Note the extra space before the close quote.

The extra space at the end of the name was difficult to notice in the service manager GUI, but is easily visible in the snmpwalk output. The right way to fix this would be to correct the service *Display name* field on the server, however, the intent of this procedure is to recommend verifying the true name using snmpwalk as opposed to relying on the service manager GUI.

Examples

Monitoring the service running state of the *Task Scheduler* on an English local Microsoft Windows® Server requires at minimum the following entry in the poller-configuration.xml.

5.6.53. WsManMonitor

This monitor can be used to issue a WS-Man *Get* command and validate the results using a SPEL expression. This monitor implements placeholder substitution in parameter values.

Monitor facts

Class Name	org.opennms.netmgt.poller.monitors.WsManMonitor
Remote Enabled	false

Configuration and Usage

Table 75. Monitor specific parameters for the WsManMonitor

Paramet er	Description	Requi red	Default value	Placeholder substitution
resource- uri	Resource URI	requir ed	-	No
rule	SPEL expression applied against the result of the <i>Get</i>	requir ed	-	Yes
selector.	Used to filter the result set. All selectors must prefixed with selector.	option al	(None)	No

This monitor implements the Common Configuration Parameters.

Examples

The following monitor will issue a *Get* against the configured resource and verify that the correct service tag is returned:

5.6.54. XmpMonitor

The XMP monitor tests for XMP service/agent availability by establishing an XMP session and querying the target agent's *sysObjectID* variable contained in the *Core MIB*. The service is considered available when the session attempt succeeds and the agent returns its *sysObjectID* without error.

Monitor facts

Class Name	org.opennms.netmgt.poller.monitors.XmpMonitor
Remote Enabled	false

Configuration and Usage

These parameters can be set in the *XMP* service entry in *collectd-configuration.xml* and will override settings from *xmp-config.xml*. Also, don't forget to add an entry in *response*-

graph.properties so that response values will be graphed.

Table 76. Monitor specific parameters for the XmpMonitor

Paramete r	Description	Require d	Default value
timeout	Time in milliseconds to wait for a successful session.	optional	5000
authenUser	The authenUser parameter for use with the XMP session.	optional	xmpUser
port	TCP port to connect to for XMP session establishment	optional	5270
mib	Name of MIB to query	optional	core
object	Name of MIB object to query	optional	sysObjectID

This monitor implements the Common Configuration Parameters.

Examples

Adding entry in collectd-configuration.xml

```
<service name="XMP" interval="30000" user-defined="false" status="on">
  <parameter key="timeout" value="3000"/>
  <parameter key="rrd-repository" value="/opt/opennms/share/rrd/response"/>
  <parameter key="rrd-base-name" value="xmp"/>
  <parameter key="ds-name" value="xmp"/>
  </service>
<monitor service="XMP" class-name="org.opennms.netmgt.poller.monitors.XmpMonitor"/>
```

Add entry in response-graph.properties

```
reports=icmp, \
xmp, \ . . . .
report.xmp.name=XMP
report.xmp.columns=xmp
report.xmp.type=responseTime
report.xmp.command=--title="XMP Response Time" \
 --vertical-label="Seconds" \
DEF:rtMills={rrd1}:xmp:AVERAGE \
DEF:minRtMills={rrd1}:xmp:MIN \
DEF:maxRtMills={rrd1}:xmp:MAX \
CDEF:rt=rtMills,1000,/ \
CDEF:minRt=minRtMills,1000,/ \
CDEF:maxRt=maxRtMills,1000,/ \
LINE1:rt#0000ff:"Response Time" \
GPRINT:rt:AVERAGE:" Avg \\: %8.2lf %s" \
GPRINT:rt:MIN:"Min \\: %8.21f %s" \
GPRINT:rt:MAX:"Max \\: %8.2lf %s\\n"
```

Chapter 6. Performance Management

OpenNMS Meridian collects performance data using the *Collectd* daemon, which is enabled by default. *Collectd* schedules data collection on *OpenNMS Meridian* entities (currently nodes and interfaces), using *management agents* and protocol-specific *collectors* (SNMP, HTTPS, JMX, JDBC, etc.) to collect performance metrics. Each collector has its own associated configuration that defines parameters for the collector.




Figure 32. Collectd overview for associated files and configuration

By default, data collection is enabled for SNMP and for OpenNMS-JVM (to monitor itself through JMX). Data collection works out of the box with SNMP, provided you have your SNMP community string configured properly. The default value of the community string is public. If your community string is different, you need to change the value:

- 1. Login to the web UI.
- 2. Go to admin>Configure OpenNMS.
- 3. In the **Provisioning** section, select **Configure SNMP Community Names by IP Address**.
- 4. Under v1/v2c specific parameters change the Read Community String value and click Save Config.

Performance data collection on other protocols (HTTPS, JMX, JDBC, etc.), requires additional configuration. You may also want to change how *collectd* works: when, how, and what data it collects.

Learn how to manage performance data collection:

- collectd configuration
- collection for specific protocols
- resource type management
- collectd administration (logging, graphing, and event properties)

6.1. Configuring Collectd

The *collectd-configuration.xml* file defines the nodes, services and parameters on which *collectd* collects metrics. It also specifies the list of available collectors.

The file is located in **\$OPENNMS_HOME**.

Edit the *collectd-configuration.xml* file to:

- set the thread pool
- configure collector packages
- specify collectors to use

In addition to editing the *collectd-configuration.xml*, you need to configure collectors for the protocols from which you want to collect data by editing the configuration files associated with them.

6.1.1. Setting the Thread Pool

A globally defined thread attribute limits the number of threads the data collection process uses in parallel. Increase or decrease this value based on your network and the size of your server by changing the value in <code>\$OPENNMS_HOME/etc/collectd-configuration.xml</code>:

<collectd-configuration threads="50">

6.1.2. Configuring Collector Packages

Collector packages in the *collectd-configuration.xml* file contain the information (IP addresses, interfaces, services, and connection parameters) that collectd needs to activate data collection.

Collectd activates data collection for each node that contains an IP interface in the configured range and also contains any of the services listed in the package associated with the selected IP interface.

Edit existing collector packages or create new ones to customize data collection for your needs. If you create a new collector package, we recommend copying and pasting an existing package in the *collectd-configuration.xml* to use as a template.

A collector package has two categories of information to edit or specify:

- collector package attributes
- collector package services

Collector Package Attributes

At a minimum, collector package attributes include a package name and a filter that specifies the interfaces to include in the collector package:

Note that remote="false" means that the services in this package are tested only from the OpenNMS core system itself and not from a different remote location.

Each package must have a filter tag that performs the initial test to see if an interface should be included in a package. Filters operate on interfaces (not nodes). Each package can have only one filter tag.

The following tags are also available for an interface filter:

Tag	Description	Example
specific	Specify an actual IP address to include in the package.	<specific>192.168.1.59</specific>
include- range	Specify a range of IP addresses to include in a package.	<include-range begin="192.168.0.1" end="192.168.0.254"/>`</include-range
exclude- range	Specify a range of IP addresses to exclude in a package. This will override an include-range tag.	<exclude-range begin="192.168.0.100" end="192.168.0.104"/>`</exclude-range
include- url	Specify a file that contains a list of #IP addresses to include.	<include- url>file:/opt/OpenNMS/etc/include `</include-

The following example illustrates collector package attributes that use some of these additional tags:

- ① Unique name of the collection package.
- (2) Apply this package to all *IP interfaces* with a configured *IPv4* address (not equal 0.0.0)
- ③ Evaluate *IPv4 rule* to collect for all *IPv4 interfaces* in the given range
- ④ Evaluate *IPv6 rule* to collect for all *IPv6 interfaces* in the given range

Service Configuration Attributes

Service configuration attributes define the collector to use and which performance metrics to collect. Each service is associated with a specific collector; the collector and its related Java class must appear at the bottom of the *collectd-configuration.xml* file:

<collector service="SNMP" class-name="org.opennms.netmgt.collectd.SnmpCollector"/>⑦

- ① Service configuration name, which is mapped to a specific collector.
- 2 The interval at which to collect the service (in milliseconds).
- ③ Marker to say if service is user defined (used for UI purposes).
- ④ Service is collected only if "on".
- (5) Assign the performance data collection schema named default (found in the corresponding configuration file for the type of collection, in this case *datacollection-config.xml*).
- 6 Enable threshold evaluation for metrics provided by this service.
- ⑦ Run the *SnmpCollector* implementation for the service named SNMP.

The following table lists service attributes common to all services. For a list of collector-specific parameters and their default values, refer to the specific collector listed in the Collectors section.

Attribute	Description
name	Service name
interval	Polling interval, in milliseconds (5 minutes by default).
user-defined	Set to "true" if user defined the collection source in the UI.
status	Indicates that data collection for the service is on or off.




Figure 33. Configuration overview for data collection with Collectd

6.1.3. Guidelines for Collector Packages

You can configure multiple packages, and an interface can exist in more than one package. This gives great flexibility in determining the service levels for a given device.

When IP interfaces match multiple collector packages with the same service configuration, collectd applies the last collector package on the service:

• Use this "final" collector package as a less-specific, catch-all filter for a default configuration.

OR

• Use it as a more-specific collector package to overwrite the default setting.

Meta-Data-DSL

Metadata-DSL allows you to use dynamic configuration in each parameter value to interpolate metadata into a parameter. The syntax allows for the use of patterns in an expression, whereby the metadata is replaced with a corresponding value during the collection process.

During evaluation of an expression the following scopes are available:

- Node metadata
- Interface metadata
- Service metadata

6.2. Configuring Collectors

Collectors collect performance data via specific agents and protocols. This section includes the following information for each collector:

- collector-specific parameters (used in the *collectd-configuration.xml* file)
- configuration file(s)



Understanding resource types helps when editing collector-specific configuration files.

6.2.1. SnmpCollector

The *SnmpCollector* collects performance data through the *SNMP protocol*. Configure access to the *SNMP Agent* through the *SNMP configuration* in the Web UI (Admin>Configure SNMP Community Names by IP Address).

Collector Facts

Class Name	org.opennms.netmgt.collectd.SnmpCollector
Package	core
Supported on Minion	Yes

Collector Parameters

Use these parameters used in the *collectd-configuration.xml* file.

Table 77. Collector-specific parameters for the SnmpCollector

Parameter	Description	Requir ed	Default value
collection	The name of the SNMP Collection to use.	require d	default
thresholding- enabled	Whether collected performance data should be tested against thresholds.	option al	true
timeout	Timeout in milliseconds to wait for SNMP responses.	option al	<i>SNMP</i> configuration

SNMP Collection Configuration



Understanding resource types helps when editing collector-specific configuration files.

Define *SNMP Collection* in etc/datacollection-config.xml and etc/datacollection.d/*.xml.

```
<?xml version="1.0"?>
<datacollection-config rrd-repository="/var/lib/opennms/rrd/snmp/">①
    <snmp-collection name="default"②</pre>
                     snmpStorageFlag="select">③
        <rrd step="300">④
            <rra>RRA:AVERAGE:0.5:1:2016</rra>
            <rra>RRA:AVERAGE:0.5:12:1488</rra>
            <rra>RRA:AVERAGE:0.5:288:366</rra>
            <rra>RRA:MAX:0.5:288:366</rra>
            <rra>RRA:MIN:0.5:288:366</rra>
        </rrd>
        <include-collection dataCollectionGroup="MIB2"/>⑤
        <include-collection dataCollectionGroup="3Com"/>
        . .
        <include-collection dataCollectionGroup="VMware-Cim"/>
    </snmp-collection>
</datacollection-config>
```

- ① Directory where to persist *RRD* files on the file system, ignored if *NewTS* is used as time-series storage.
- ② Name of the SNMP data collection referenced in the collection package in collectdconfiguration.xml.
- ③ Configure SNMP MIB-II interface metric collection behavior: *all* means collect metrics from all interfaces, *primary* only from interface provisioned as *primary* interface, *select* only from manually selected interfaces from the *Web UI*.
- ④ *RRD* archive configuration for this set of performance metrics, ignored when *NewTS* is used as time series storage.
- **(5)** Include device- or application-specific performance metric *OIDS* to collect.




Figure 34. Configuration overview for SNMP data collection

SnmpCollectorNG

The SnmpCollectorNG provides an alternate implementation to the SnmpCollector that takes advantages of new *APIs* in the platform. It is provided as a separate collector while we work to validate its functionality and run-time characteristics, with the goal of eventually having it replace the SnmpCollector.

Known caveats include:

- No support for alias type resources
- No support for min/max values

6.2.2. JmxCollector

The *JmxCollector* collects performance data via *JMX*. Attributes are extracted from the available *MBeans*.

Collector Facts

Class Name	org.opennms.netmgt.collectd.Jsr160Collector
Package	core
Supported on Minion	Yes

Collector Parameters

Use these parameters in the *collectd-configuration.xml* file.

Table 78. Collector-specific parameters for the Jsr160Collector

Parameter	Description	Requ ired	Default value
collection	The name of the <i>JMX Collection</i> to use.	requi red	(none)
thresholdin g-enabled	Whether collected performance data should be tested against thresholds	optio nal	true
retry	Number of retries	optio nal	3
friendlyNam e	Name of the path in which the metrics should be stored	optio nal	Value of the port, or 'jsr160' if no port is set.
factory	The password strategy to use. Supported values are: STANDARD (for authentication), PASSWORD_CLEAR (same as STANDARD) and SASL (if secure connection is required).	optio nal	STANDARD
url	The connection url, e.g., <pre>service:jmx:rmi:localhost:18980. The IP address can be substituted. Use \${ipaddr} in that case, e.g., service:jmx:rmi:\${ipaddr}:18980</pre>	optio nal	(none)

Parameter	Description	Requ ired	Default value
username	The username if authentication is required.	optio nal	(none)
password	The password if authentication is required.	optio nal	(none)
port	Deprecated. JMX port.	optio nal	1099
protocol	Deprecated . Protocol used in the JMX connection string.	optio nal	rmi
urlPath	Deprecated . Path used in JMX connection string.	optio nal	/jmxrmi
rmiServerPo rt	Deprecated. RMI port.	optio nal	45444
remoteJMX	Deprecated . Use an alternative JMX URL scheme.	optio nal	false



The deprecated parameters port, protocol, urlPath, rmiServerPort and remoteJMX should be replaced with the url parameter. If url is not defined the collector falls back to legacy mode and the deprecated parameters are used instead to build the connection url.



If a service requires different configuration, an entry in \$OPENNMS_HOME/etc/jmxconfig.xml can overwrite it.

JMX Collection Configuration



Understanding resource types helps when editing collector-specific configuration files.

Define *JMX Collections* in etc/jmx-datacollection-config.xml and etc/jmx-datacollection-config.d/.

This snippet provides a collection definition named opennms-poller:

```
<jmx-collection name="opennms-poller">
    </rd step="300">
        </rra>RRA:AVERAGE:0.5:1:2016</rra>
        </rra>RRA:AVERAGE:0.5:12:1488</rra>
        </rra>RRA:AVERAGE:0.5:288:366</rra>
        </rra>RRA:MAX:0.5:288:366</rra>
        </rra>RRA:MIN:0.5:288:366</rra>
        </rra>
        </rra>
        </rra>Rma:MIN:0.5:288:366</rra>
        </rra>
        </rra>RRA:MIN:0.5:288:366</rra>
        </rra>
        </
```

Once added to etc/jmx-datacollection-config.xml you can test it using the collect command available in the *Karaf Shell*:

opennms:collect org.opennms.netmgt.collectd.Jsr160Collector 127.0.0.1
collection=opennms-poller port=18980

Generic Resource Type

To support wildcard (*) in objectname, JMX collector supports generic resource types. JMX configuration requires two changes for this to work:

• Create a custom resource type in etc/resource-types.d/. For example, there is already a definition in jmx-resource.xml that defines a custom resource for Kafka lag

```
<resource-types>
<resourceType name="kafkaLag" label="Kafka Lag"
resourceLabel="${index}">
<persistenceSelectorStrategy class=
"org.opennms.netmgt.collection.support.PersistAllSelectorStrategy"/>
<storageStrategy class=
"org.opennms.netmgt.dao.support.SiblingColumnStorageStrategy">
<parameter key="sibling-columnStorageStrategy">
<parameter key="sibling-column-name" value="name" />
</storageStrategy>
</resourceType>
</resource-types>
```

• Match the resourceType name as resource-type in MBean definition:

Resource definition

JMX objectname is the full name of MBean in form of (domain:key=value, key=value, ..). Wildcard (*) can exist anywhere in the objectname.

Depending on wildcard definition, use SiblingColumnStorageStrategy to extract resource label. If wildcard exists in the value (usual case), use corresponding key as the sibling-column-name parameter. For example: org.apache.activemq:BrokerName=*,Type=Queue,Destination=com.mycompany.myqueue

Here BrokerName can be defined as parameter for SiblingColumnStorageStrategy

<parameter key="sibling-column-name" value="BrokerName" />

The extracted BrokerNames from the wildcard will be the resource folders in the form of nodeId/resourceTypeName/{resource-label}

Wildcard may exist in domain as well. For example: org.apache.*:BrokerName=trap, Type=Queue. Then domain can be defined as the sibling-column-name parameter.

<parameter key="sibling-column-name" value="domain" />

To use the objectname itself as a resource label, use IndexStorageStrategy as storageStrategy in resource-type definition.

Third-Party JMX Services

Some Java applications provide their own JMX implementation and require certain libraries to be present on the classpath, e.g., the Java application server Wildfly. To successfully collect data, you may need to do the following:

- Place the jmx client lib to the \$OPENNMS_HOME/lib folder (e.g., jboss-cli-client.jar)
- Configure the collection accordingly (see above)
- Configure the JMX-Collector in *collectd-configuration.xml* (see below)

```
Example
```

```
<service name="JMX-WILDFLY" interval="300000" user-defined="false" status="on">
                                                                                                                                                                                                                                                                                                                                          <
```

6.2.3. HttpCollector

The *HttpCollector* collects performance data via *HTTP* and *HTTPS*. Attributes are extracted from the *HTTP* responses using a regular expression.

Collector Facts

Class Name	org.opennms.netmgt.collectd.HttpCollector
Package	core
Supported on Minion	Yes

Collector Parameters

Use these parameters in the *collectd-configuration.xml* file.

Table 79. Collector-specific parameters for the HttpCollector

Parameter	Description	Requi red	Default value
collection	The name of the <i>HTTP Collection</i> to use.	requir ed	(none)
thresholding- enabled	Whether collected performance data should be tested against thresholds.	option al	true
port	Override the default port in all of the URIs	option al	80
timeout	Connection and socket timeout in milliseconds	option al	3000

Parameter	Description	Requi red	Default value
retry	Number of retries	option al	2
use-system- proxy	Should the system-wide proxy settings be used? Configure system proxy settings via system properties	option al	false

HTTP Collection Configuration



Understanding resource types helps when editing collector-specific configuration files.

Define *HTTP Collections* in etc/http-datacollection-config.xml.

This snippet provides a collection definition named opennms-copyright:

```
<http-collection name="opennms-copyright">
 <rrd step="300">
    <rra>RRA:AVERAGE:0.5:1:2016</rra>
    <rra>RRA:AVERAGE:0.5:12:1488</rra>
    <rra>RRA:AVERAGE:0.5:288:366</rra>
    <rra>RRA:MAX:0.5:288:366</rra>
    <rra>RRA:MIN:0.5:288:366</rra>
 </rrd>
 <uris>
    <uri name="login-page">
      <url path="/opennms/login.jsp"</pre>
           matches=".*2002\-([0-9]+).*" response-range="100-399" dotall="true" >
      </url>
      <attributes>
        <attrib alias="copyrightYear" match-group="1" type="gauge"/>
      </attributes>
    </uri>
 </uris>
</http-collection>
```

Once added to etc/http-datacollection-config.xml you can test it using the collect command available in the *Karaf Shell*:

opennms:collect org.opennms.netmgt.collectd.HttpCollector 127.0.0.1
collection=opennms-copyright port=8980

6.2.4. JdbcCollector

The *JdbcCollector* collects performance data via *JDBC* drivers. Attributes are retrieved using *SQL* queries.

Collector Facts

Class Name	org.opennms.netmgt.collectd.JdbcCollector
Package	core
Supported on Minion	Yes (see limitations)

Limitations on Minion

When running on *Minion* the data sources in opennms-datasources.xml cannot be referenced. Instead, you must set the *JDBC* connection settings using the service parameters.

Also, the *JDBC* driver must be properly loaded in the *Minion* container (see Installing JDBC drivers in Minion) By default, only the *JDBC* driver for *PostgreSQL* is available.

Collector Parameters

Use these parameters in the *collectd-configuration.xml* file.

Table 80. Collector-specific parameters for the JdbcCollector

Parame ter	Description	Requi red	Default value
collecti on	The name of the <i>JDBC Collection</i> to use.	requir ed	(empty)
data- source	Use an existing datasource defined in <i>opennms-datasources.xml</i>	option al	NO_DATASOURCE_FOUND
driver	Driver class name	option al	org.postgresql.Driver
url	JDBC URL	option al	jdbc:postgresql://:OPENNMS_JDBC_H OSTNAME/opennms
user	JDBC username	option al	postgres
password	JDBC password	option al	(empty string)

JDBC Collection Configuration



Understanding resource types helps when editing collector-specific configuration files.

Define *JDBC Collections* in etc/jdbc-datacollection-config.xml.

This snippet provided a collection definition named opennms-stats:

```
<jdbc-collection name="opennms-stats">
 <rrd step="300">
    <rra>RRA: AVERAGE: 0.5:1:2016</rra>
    <rra>RRA:AVERAGE:0.5:12:1488</rra>
    <rra>RRA:AVERAGE:0.5:288:366</rra>
    <rra>RRA:MAX:0.5:288:366</rra>
    <rra>RRA:MIN:0.5:288:366</rra>
 </rrd>
 <queries>
    <query name="opennmsQuery" ifType="ignore">
      <statement data-source="opennms">
        <queryString>select count(*) as event_count from events;</queryString>
      </statement>
      <columns>
        <column name="event_count" data-source-name="event_count" alias="event_count"
type="GAUGE"/>
      </columns>
    </query>
 </queries>
</idbc-collection>
```

Once added to etc/jdbc-datacollection-config.xml you can test it using the collect command available in the *Karaf Shell*:

opennms:collect org.opennms.netmgt.collectd.JdbcCollector 127.0.0.1 collection=opennms-stats data-source=opennms

To test this same collection on *Minion* you must specify the *JDBC* settings as service attributes, for example:

```
opennms:collect -l MINION org.opennms.netmgt.collectd.JdbcCollector 127.0.0.1
collection=opennms-stats driver=org.postgresql.Driver
url=jdbc:postgresql://localhost:5432/opennms user=opennms password=opennms
```

6.2.5. NSClientCollector

The NSClientCollector collects performance data over HTTP from NSClient++.

Collector Facts

Class Name	org.opennms.protocols.nsclient.collector.NSClientCollector
Package	opennms-plugin-protocol-nsclient
Supported on Minion	Yes

Collector Parameters

Use these parameters in the *collectd-configuration.xml* file).

Table 81. Collector-specific parameters for the NSClientCollector

Paramete r	Description	Require d	Default value
collection	The name of the NSClient Collection to use.	optional	default

6.2.6. PrometheusCollector

The *PrometheusCollector* collects performance metrics via HTTP(S) using the text-based Prometheus Exposition format. This has been adopted by many applications and is in the process of being standardized in the OpenMetrics project.

This collector provides tools for parsing and mapping the metrics to the collection model used by OpenNMS Meridian.

Collector Facts

Class Name	org.opennms.netmgt.collectd.prometheus.PrometheusCollecto	
Package	core	
Supported on Minion	Yes	

Collector Parameters

Table 82. Collector-specific parameters for the PrometheusCollector

Paramete r	Description	Require d	Default value
collection	The name of the <i>Prometheus Collection</i> to use	required	
url	HTTP URL to query for the metrics	required	
timeout	HTTP socket and read timeout in milliseconds	optional	10000 (10 seconds)
retry	Number of retries before failing	optional	2
`header-*	Optional headers to pass in the HTTP request	optional	(none)

Prometheus Collector Usage

Let's demonstrate the usage of the collector with an example running against node_exporter.

Obtain a copy of the appropriate release binary from the node_exporter release page.

Extract and start the service:

\$ tar xvf node_exporter-0.18.1.linux-amd64.tar.gz \$./node_exporter-0.18.1.linux-amd64/node_exporter INFO[0000] Starting node exporter (version=0.18.1, branch=HEAD, revision=3db77732e925c08f675d7404a8c46466b2ece83e) source="node_exporter.go:156" INFO[0000] Build context (go=go1.12.5, user=root@b50852a1acba, date=20190604-16:41:18) source="node exporter.go:157" INFO[0000] Enabled collectors: source="node_exporter.go:97" INFO[0000] - arp source="node_exporter.go:104" INFO[0000] - bcache source="node exporter.go:104" INFO[0000] - bonding source="node_exporter.go:104" INFO[0000] - conntrack source="node_exporter.go:104" INFO[0000] - cpu source="node_exporter.go:104" INFO[0000] - cpufreq source="node_exporter.go:104" . . . INFO[0000] - uname source="node_exporter.go:104" INFO[0000] - vmstat source="node_exporter.go:104" INF0[0000] - xfs source="node exporter.go:104" INFO[0000] - zfs source="node_exporter.go:104" INFO[0000] Listening on :9100 source="node_exporter.go:170"

From the Karaf Shell, you can now issue an ad hoc collection request against the node_exporter process

```
admin@opennms> opennms:collect
org.opennms.netmgt.collectd.prometheus.PrometheusCollector 127.0.0.1
collection=node_exporter url='http://127.0.0.1:9100/metrics'
NOTE: Some collectors require a database node and IP interface.
NodeLevelResource[nodeId=0,path=null]
Group: node_exporter_loadavg
Attribute[load1:1.26]
Attribute[load15:1.0]
Attribute[load5:0.59]
Group: node_exporter_memory
Attribute[Active_anon_bytes:1.1776770048E10]
Attribute[Active_bytes:2.4471535616E10]
Attribute[Active_file_bytes:1.2694765568E10]
```

Update the IP addresses in the command as necessary.

Prometheus Collector Configuration

Prometheus collection definitions are maintained in etc/prometheus-datacollection.d/.

Let's look at an excerpt of the node_exporter collection:

```
<!---

node_memory_Active 1.3626548224e+10

node_memory_Active_anon 6.314020864e+09

node_memory_Active_file 7.31252736e+09

....

node_memory_HugePages_Free 0

....

-->

<group name="node_exporter_memory"

resource-type="node"

filter-exp="name matches 'node_memory_.*'">

<numeric-attribute alias-exp="name.substring('node_memory_'.length())"/>

</group>
```

This group definition matches metrics that start the node_memory_ prefix, extracts the suffix as the metric name and associates these metrics with the node_exporter_memory group in the node-level resource.

Expression are written in Spring Expression Language (SpEL). The metric instances are used as the expression context, which means you have access to the name and label properties.

Here's another excerpt where we extract metrics grouped by CPU:

```
<!---

node_cpu{cpu="cpu0",mode="guest"} 0

node_cpu{cpu="cpu0",mode="idle"} 16594.88

...

node_cpu{cpu="cpu1",mode="guest"} 0

node_cpu{cpu="cpu1",mode="idle"} 17790.51

-->

<group name="node_exporter_cpus"

resource-type="nodeExporterCPU"

filter-exp="name matches 'node_cpu'"

group-by-exp="labels[cpu]">

<numeric-attribute alias-exp="labels[mode]"/>

</group>
```

This group definition matches metrics called 'node_cpu', groups them by the value of the cpu label and extracts the name of the mode for the name of the numeric attributes.

6.2.7. TcaCollector

The *TcaCollector* collects special SNMP data from Juniper TCA Devices.

Collector Facts

Class Name	org.opennms.netmgt.collectd.tca.TcaCollector
Package	opennms-plugin-collector-juniper-tca
Supported on Minion	Yes

Collector Parameters

Use these parameters in the *collectd-configuration.xml* file.

Table 83. Collector-specific parameters for the TcaCollector

Paramete r	Description	Require d	Default value
collection	The name of the <i>TCA Collection</i> to use.	required	

6.2.8. VmwareCimCollector

The VmwareCimCollector collects ESXi host and sensor metrics from vCenter.

Collector Facts

Class Name	org.opennms.netmgt.collectd.VmwareCimCollector
Package	core
Supported on Minion	Yes

Collector Parameters

Use these parameters in the *collectd-configuration.xml* file.

Table 84. Collector-specific parameters for the VmwareCimCollector

Paramete r	Description	Require d	Default value
collection	The name of the VMWare CIM Collection to use.	required	
timeout	Connection timeout in milliseconds	optional	

6.2.9. VmwareCollector

The *VmwareCollector* collects peformance metrics for managed entities from *vCenter*.

Collector Facts

Package	core
Supported on Minion	Yes

Collector Parameters

Use these parameters in the *collectd-configuration.xml* file.

Table 85. Collector-specific parameters for the VmwareCollector

Paramete r	Description	Require d	Default value
collection	The name of the VMWare Collection to use.	required	
timeout	Connection timeout in milliseconds	optional	

6.2.10. WmiCollector

The *WmiCollector* collects peformance metrics from *Windows* systems using Windows Management Instrumentation (WMI).

Collector Facts

Class Name	org.opennms.netmgt.collectd.WmiCollector
Package	core
Supported on Minion	Yes

Collector Parameters

Use these parameters in the *collectd-configuration.xml* file.

Table 86. Collector-specific parameters for the WmiCollector

Paramete	Description	Require	Default
r		d	value
collection	The name of the <i>WMI Collection</i> to use.	required	

6.2.11. WsManCollector

The *WsManCollector* collects peformance metrics using the Web Services-Management (WS-Management) protocol.

Web Services-Management (WS-Management) is a DMTF open standard defining a SOAP-based protocol for the management of servers, devices, applications and various Web services. Windows Remote Management (WinRM) is the Microsoft implementation of WS-Management Protocol.

Collector Facts

Class Name	org.opennms.netmgt.collectd.WsManCollector
Package	core
Supported on Minion	Yes

Collector Parameters

Use these parameters in the *collectd-configuration.xml* file.

Table 87. Collector-specific parameters for the WsManCollector

Paramete	Description	Require	Default
r		d	value
collection	The name of the WS-Man Collection to use.	required	

WS-Management Setup

Before setting up OpenNMS Meridian to communicate with a WS-Management agent, you should confirm that it is properly configured and reachable from the OpenNMS Meridian system. If you need help enabling the WS-Management agent, consult the documentation from the manufacturer. Here are some resources that could help:

- Installation and Configuration for Windows Remote Management
- Troubleshooting WinRM connection and authentication

We suggest using the Openwsman command line client to validate authentication and connectivity. Packages are available for most distributions under wsmancli.

For example:

wsman identify -h localhost -P 5985 -u wsman -p secret

Once validated, add the agent-specific details to the OpenNMS Meridian configuration, defined in the next section.

Troubleshooting and Commands

For troubleshooting there is a set of commands you can use in *Powershell* verified on *Microsoft Windows Server 2012*.

Enable WinRM in PowerShell

Enable-PSRemoting

netsh advfirewall firewall add rule name="WinRM-HTTP" dir=in localport=5985
protocol=TCP action=allow

Set up Firewall for WinRM over HTTPS

```
netsh advfirewall firewall add rule name="WinRM-HTTPS" dir=in localport=5986
protocol=TCP action=allow
```

Test WinRM on local Windows Server

winrm id

Show WinRM configuration on Windows Server

winrm get winrm/config

Show listener for configuration on Windows Server

winrm e winrm/config/listener

Test connectivity from a Linux system

nc -z -w1 <windows-server-ip-or-host> 5985;echo \$?



Use BasicAuthentication just with *WinRM* over *HTTPS* with verifiable certificates in production environment.

Enable BasicAuthentication

```
winrm set winrm/config/client/auth '@{Basic="true"}'
winrm set winrm/config/service/auth '@{Basic="true"}'
winrm set winrm/config/service '@{AllowUnencrypted="true"}'
```

WS-Management Agent Configuration



Understanding resource types helps when editing collector-specific configuration files.

The agent-specific configuration details are maintained in etc/wsman-config.xml. This file has a similar structure as etc/snmp-config.xml, which the reader may already be familiar with.

This file is consulted when a connection to a WS-Man Agent is made. If the IP address of the agent is matched by the range, specific or ip-match elements of a definition, then the attributes on that

definition are used to connect to the agent. Otherwise, the attributes on the outer wsman-config definition are used.

This etc/wsman-config.xml files automatically reload when modified.

Here is an example with several definitions:

```
<?xml version="1.0"?>
<wsman-config retry="3" timeout="1500" ssl="true" strict-ssl="false" path="/wsman">
<definition ssl="true" strict-ssl="false" path="/wsman" username="root" password=
"calvin" product-vendor="Dell" product-version="iDRAC 6">
<range begin="192.168.1.1" end="192.168.1.10"/>
</definition>
<definition>
<definition ssl="false" port="5985" path="/wsman" username="Administrator"
password="P@ssword">
<ip-match>172.23.1-4.1-255</ip-match>
<specific>172.23.1.105</specific>
</definition>
</wsman-config>
```

Attribute	Description	Default
timeout	<i>HTTP</i> Connection and response timeout in milliseconds.	<i>HTTP</i> client default
retry	Number of retries on connection failure.	0
username	Username for basic authentication.	none
password	Password used for basic authentication.	none
port	<i>HTTP/S</i> port	Default for protocol
max- elements	Maximum number of elements to retrieve in a single request.	no limit
ssl	Enable SSL	False
strict-ssl	Enforce SSL certificate verification.	True
path	Path in the URL to the WS-Management service.	/
product- vendor		
product- version	ebeu to over mine the detected product verbion	
gss-auth Enables GSS authentication. When enabled a reverse lookup is performed on the target IP address in order to determine the canonical host name.		False



If you try to connect against *Microsoft Windows Server* make sure to set specific ports for *WinRM* connections. By default *Microsoft Windows Server* uses port TCP/5985 for plain text and port TCP/5986 for *SSL* connections.

WS-Management Collection Configuration

Configuration for the WS-Management collector is stored in etc/wsman-datacollection.config.xml and etc/wsman-datacollection.d/*.xml.



The contents of these files are automatically merged and reloaded when changed. The default WS-Management collection looks as follows:

```
<?xml version="1.0"?>
<wsman-datacollection-config rrd-repository="${install.share.dir}/rrd/snmp/">
    <collection name="default">
        <rrd step="300">
            <rra>RRA:AVERAGE:0.5:1:2016</rra>
            <rra>RRA:AVERAGE:0.5:12:1488</rra>
            <rra>RRA: AVERAGE: 0.5:288:366</rra>
            <rra>RRA:MAX:0.5:288:366</rra>
            <rra>RRA:MIN:0.5:288:366</rra>
        </rrd>
        <!--
             Include all of the available system definitions
         -->
        <include-all-system-definitions/>
    </collection>
</wsman-datacollection-config>
```

The magic happens with the <include-all-system-definitions/> element which automatically includes all of the system definitions into the collection group.



If required, you can include a specific system-definition with <include-system-definition>sys-def-name</include-system-definition>.

System definitions and related groups can be defined in the root etc/wsman-datacollectionconfig.xml file, but it is preferred that be added to a device specific configuration files in etc/wsmandatacollection-config.d/*.xml.



Avoid modifying any of the distribution configuration files and create new ones to store you specific details instead.

Here is an example configuration file for a *Dell iDRAC*:

```
<?xml version="1.0"?>
<wsman-datacollection-config>
    <group name="drac-system"</pre>
           resource-uri="http://schemas.dell.com/wbem/wscim/1/cim-
schema/2/root/dcim/DCIM_ComputerSystem"
           resource-type="node">
        <attrib name="OtherIdentifyingInfo" index-of="#IdentifyingDescriptions matches
'.*ServiceTag'" alias="serviceTag" type="String"/>
    </group>
    <group name="drac-power-supply"</pre>
           resource-uri="http://schemas.dmtf.org/wbem/wscim/1/*"
           dialect="http://schemas.microsoft.com/wbem/wsman/1/WQL"
           filter="select
InputVoltage,InstanceID,PrimaryStatus,SerialNumber,TotalOutputPower from
DCIM_PowerSupplyView where DetailedState != 'Absent'"
           resource-type="dracPowerSupplyIndex">
        <attrib name="InputVoltage" alias="inputVoltage" type="Gauge"/>
        <attrib name="InstanceID" alias="instanceId" type="String"/>
        <attrib name="PrimaryStatus" alias="primaryStatus" type="Gauge"/>
        <attrib name="SerialNumber" alias="serialNumber" type="String"/>
        <attrib name="TotalOutputPower" alias="totalOutputPower" type="Gauge"/>
    </group>
    <system-definition name="Dell iDRAC (All Version)">
        <rule>#productVendor matches '^Dell.*' and #productVersion matches
'.*iDRAC.*'</rule>
        <include-group>drac-system</include-group>
        <include-group>drac-power-supply</include-group>
    </system-definition>
</wsman-datacollection-config>
```

System Definitions

Rules in the system definition are written using SpEL expressions.

The expression has access to the following variables in its evaluation context:

Name	Туре
(root)	org.opennms.netmgt.model.OnmsNode
agent	org.opennms.netmgt.collection.api.CollectionAgent
productVendor	java.lang.String
productVersion	java.lang.String

If a particular agent is matched by any of the rules, then the collector will attempt to collect the referenced groups from the agent.

Group Definitions

Groups are retrieved by issuing an Enumerate command against a particular Resource URI and parsing the results. The Enumerate commands can include an optional filter in order to filter the records and attributes that are returned.



When configuring a filter, you must also specify the dialect.

The resource type used by the group must of be of type node or a generic resource type. Interface level resources are not supported.

When using a generic resource type, the IndexStorageStrategy cannot be used since records have no implicit index. Instead, you must use an alternative such as the SiblingColumnStorageStrategy.

If a record includes a multi-valued key, you can collect the value at a specific index with an index-of expression. This is best demonstrated with an example. Let's assume we wanted to collect the ServiceTag from the following record:

<IdentifyingDescriptions>CIM:GUID</IdentifyingDescriptions> <IdentifyingDescriptions>CIM:Tag</IdentifyingDescriptions> <IdentifyingDescriptions>DCIM:ServiceTag</IdentifyingDescriptions> <OtherIdentifyingInfo>4545454C4C-3700-104A-8052-C3C01BB25031</OtherIdentifyingInfo> <OtherIdentifyingInfo>mainsystemchassis</OtherIdentifyingInfo> <OtherIdentifyingInfo>C8BBBP1</OtherIdentifyingInfo>

Specifying, the attribute name OtherIdentifyingInfo would not be sufficient, since there are multiple values for that key. Instead, we want to retrieve the value for the OtherIdentifyingInfo key at the same index where IdentifyingDescriptions is set to DCIM:ServiceTag.

This can be achieved using the following attribute definition:

```
<attrib name="OtherIdentifyingInfo" index-of="#IdentifyingDescriptions matches
'.*ServiceTag'" alias="serviceTag" type="String"/>
```

Special Attributes

A group can contain the placeholder attribute **ElementCount** that, during collection, will be populated with the total number of results returned for that group. This can be used to threshold on the number results returned by an enumeration.

```
<group name="Event-1234"
    resource-uri="http://schemas.microsoft.com/wbem/wsman/1/wmi/root/cimv2/*"
    dialect="http://schemas.microsoft.com/wbem/wsman/1/WQL"
    filter="select * from Win32_NTLogEvent where LogFile = 'Some-Application-
Specific-Logfile/Operational' AND EventCode = '1234'"
    resource-type="node">
    <attrib name="##ElementCount##" alias="elementCount" type="Gauge"/>
    </group>
```

6.2.12. XmlCollector

The XmlCollector collects and extracts metrics from XML and JSON documents.

Collector Facts

Class Name	org.opennms.protocols.xml.collector.XmlCollector
Package	core
Supported on Minion	Yes (see limitations)

Limitations on Minion

The following handlers are not currently supported on *Minion*:

- DefaultJsonCollectionHandler
- Sftp3gppXmlCollectionHandler
- Sftp3gppVTDXmlCollectionHandler

Collector Parameters

Use these parameters in the *collectd-configuration.xml* file.

Table 89. Collector-specific parameters for the XmlCollector

Paramete r	Description	Requir ed	Default value
collection	The name of the <i>XML Collection</i> to use.	requir ed	-
handler- class	Class that performs the collection.	option al	org.opennms.protocols.xml.collector.DefaultXml CollectionHandler

The available handlers include:

- org.opennms.protocols.xml.collector.DefaultXmlCollectionHandler
- org.opennms.protocols.xml.collector.Sftp3gppXmlCollectionHandler
- org.opennms.protocols.xml.vtdxml.DefaultVTDXmlCollectionHandler

- org.opennms.protocols.xml.vtdxml.Sftp3gppVTDXmlCollectionHandler
- org.opennms.protocols.json.collector.DefaultJsonCollectionHandler
- org.opennms.protocols.http.collector.HttpCollectionHandler

XML Collection Configuration



Understanding resource types helps when editing collector-specific configuration files.

XML Collections are defined in etc/xml-datacollection-config.xml and etc/xml-datacollection/.

This snippet provides a collection definition named xml-opennms-nodes:

The request element can have the following child elements:

Parameter	Description	Required	Default value
timeout	The connection and socket timeout in milliseconds	optional	
retries	How often should the request be repeated in case of an error?	optional	0
use-system-proxy	Should the system-wide proxy settings be used? Configure the system proxy settings via system properties	optional	false

The referenced opennms-nodes.xml file contains:

With the configuration in place, you can test it using the **collect** command available in the *Karaf Shell*:

```
opennms:collect -n 1 org.opennms.protocols.xml.collector.XmlCollector 127.0.0.1
collection=xml-opennms-nodes
```

Caveats

The org.opennms.protocols.json.collector.DefaultJsonCollectionHandler requires the fetched document to be single element of type object to make xpath query work. If the root element is an array, it will be wrapped in an object, whereas the original array is accessible as /elements.

6.2.13. XmpCollector

The *XmpCollector* collects peformance metrics via the X/Open Management Protocol API (XMP) protocol.

Collector Facts

Class Name	<pre>org.opennms.netmgt.protocols.xmp.collector.XmpCollector</pre>
Package	opennms-plugin-protocol-xmp
Supported on Minion	No

Collector Parameters

Use these parameters in the *collectd-configuration.xml* file.

Table 90. Collector-specific parameters for the XmpCollector

Paramete r	Description	Require d	Default value
collection	The name of the XMP Collection to use.	required	
port	The TCP port on which the agent communicates.	required	
authenUser	The username used for authenticating to the agent.	optional	(none)
timeout	The timeout used when communicating with the agent.	optional	3000
retry	The number of retries permitted when timeout expires.	optional	0

6.3. Resource Types

Resource types group sets of performance data measurements for persisting, indexing, and display in the web UI. Each resource type has a unique name, label definitions for display in the UI, and strategy definitions for archiving the measurements for long-term analysis.

There are two labels for a resource type. The first, label, defines a string to display in the UI. The second, resourceLabel, defines the template used when displaying each unique group of measurements name for the resource type.

There are two types of strategy definitions for resource types, persistence selector and storage strategies. The persistence selector strategy filters the group indexes down to a subset for storage on disk. The storage strategy is used to convert an index into a resource path label for persistence. There are two special resource types that do not have a resource-type definition. They are node and ifIndex.

Resource types can be defined inside files in either **\$OPENNMS_HOME/etc/resource-types.d** or **\$OPENNMS_HOME/etc/datacollection**, with the latter being specific for SNMP.

Here is the diskIOIndex resource type definition from
\$OPENNMS_HOME/etc/datacollection/netsnmp.xml:

Persistence Selector Strategies

Class	Description
org.opennms.netmgt.collection.support.PersistAllSelectorStr ategy	Persist All indexes
org.opennms.netmgt.collection.support.PersistRegexSelector Strategy	Persist indexes based on JEXL evaluation

Table 91. Persistence Selector Strategies

PersistRegexSelectorStrategy

The PersistRegexSelectorStrategy class takes a single parameter, match-expression, which defines a JEXL expressions. On evaulation, this expression should return either true, persist index to storage, or false, discard data.

Storage Strategies

Table 92. Storage Strategies

Class	Storage Path Value
org.opennms.netmgt.collection.support .IndexStorageStrategy	Index
org.opennms.netmgt.collection.support .JexlIndexStorageStrategy	Value after JexlExpression evaluation
org.opennms.netmgt.collection.support .ObjectNameStorageStrategy	Value after JexlExpression evaluation
org.opennms.netmgt.dao.support.Fram eRelayStorageStrategy	interface label + '.' + dlci
org.opennms.netmgt.dao.support.HostF ileSystemStorageStrategy	Uses the value from the hrStorageDescr column in the hrStorageTable, cleaned up for unix filesystems.
org.opennms.netmgt.dao.support.Siblin gColumnStorageStrategy	Uses the value from an SNMP lookup of OID in sibling- column-name parameter, cleaned up for unix filesystems.
org.opennms.protocols.xml.collector.X mlStorageStrategy	Index, but cleaned up for unix filesystems.

IndexStorageStrategy

The IndexStorageStrategy takes no parameters.

JexlIndexStorageStrategy

The JexlIndexStorageStrategy takes two parameters, index-format which is required, and cleanoutput which is optional.

Parameter	Description		
index-format	The JexlExpression to evaluate		
clean-output	Boolean to indicate whether the index value is cleaned up.		

If the index value will be cleaned up, then it will have all whitespace, colons, forward and back slashes, and vertical bars replaced with underscores. All equal signs are removed.

This class can be extended to create custom storage strategies by overriding the updateContext method to set additional key/value pairs to use in your index-format template.

```
public class ExampleStorageStrategy extends JexlIndexStorageStrategy {
    private static final Logger LOG = LoggerFactory.getLogger(ExampleStorageStrategy
.class);
    public ExampleStorageStrategy() {
        super();
    }
    @Override
    public void updateContext(JexlContext context, CollectionResource resource) {
        context.set("Example", resource.getInstance());
    }
}
```

ObjectNameStorageStrategy

The ObjectNameStorageStrategy extends the JexlIndexStorageStrategy, so its requirements are the same. Extra key/values pairs are added to the JexlContext which can then be used in the index-format template. The original index string is converted to an ObjectName and can be referenced as \${ObjectName}. The *domain* from the ObjectName can be referenced as \${domain}. All *key properties* from the ObjectName can also be referenced by \${key}.

This storage strategy is meant to be used with JMX MBean datacollections where multiple MBeans can return the same set of attributes. As of OpenNMS Horizon 20, this is only supported using a HTTP to JMX proxy and using the XmlCollector as the JmxCollector does not yet support indexed groups.

Given an MBean like java.lang:type=MemoryPool,name=Survivor Space, and a storage strategy like this:

```
<storageStrategy class=
"org.opennms.netmgt.collection.support.ObjectNameStorageStragegy">
<parameter key="index-format" value="${domain}_${type}_${name}" />
<parameter key="clean-output" value="true" />
</storageStrategy>
```

Then the index value would be java_lang_MemoryPool_Survivor_Space.

FrameRelayStorageStrategy

The FrameRelayStorageStrategy takes no parameters.

HostFileSystemStorageStrategy

The HostFileSystemStorageStrategy takes no parameters. This class is marked as deprecated, and can be replaced with:

```
<storageStrategy class="org.opennms.netmgt.dao.support.SiblingColumnStorageStrategy">
    <parameter key="sibling-column-name" value="hrStorageDescr" />
    <parameter key="replace-first" value="s/^-$/_root_fs/" />
    <parameter key="replace-all" value="s/^-//" />
    <parameter key="replace-all" value="s/\\s//" />
    <parameter key="replace-all" value="s/\\\.*//" />
    <parameter key="replace-all" value="s/:\\\\.*//" />
    <parameter key="replace-all" value="s/:\\\\.*//" />
```

SiblingColumnStorageStrategy

Parameter	Description		
sibling-column-name	Alternate string value to use for index		
replace-first	Regex Pattern, replaces only the first match		
replace-all	Regex Pattern, replaces all matches		

Values for replace-first, and replace-all must match the pattern *s/regex/replacement/* or an error will be thrown.

XmlStorageStrategy

This XmlStorageStrategy takes no parameters. The index value will have all whitespace, colons, forward and back slashes, and vertical bars replaced with underscores. All equal signs are removed.

6.4. SNMP Property Extenders

When collecting tabular numeric metrics from a given MIB table, it's helpful to include one or more string properties from each conceptual row of the table in question. These properties can be used in the resourceLabel attribute of the resourceType associated with the collected data. When the string property exists as a column in the same table that contains the numeric metrics, it's easy to associate the string to the correct resource by adding a mibObj with the same instance attribute and a type of string.

For example, the Cisco ENVMON MIB's temperature status table contains both a numeric gauge for the temperature value and a string describing the associated temperature sensor. A partial walk of this table illustrates this very direct relationship:

ciscoEnvMonTemperat ureStatusIndex	<pre>ciscoEnvMonTemperatureStatusDescr (.1.3.6.1.4.1.9.9.13.1.3.1.2)</pre>	<pre>ciscoEnvMonTemperatureStatusValue (.1.3.6.1.4.1.9.9.13.1.3.1.3)</pre>
1	I/O Cont Inlet	22
2	I/O Cont Outlet	23
3	NPE Inlet	22
4	NPE Outlet	24

To collect the ciscoEnvMonTemperatureStatusDescr and ciscoEnvMonTemperatureStatusValue columns within an SNMP data-collection group, all that's needed is a resourceType and a group to hold the two mibObj elements corresponding to these two columns. The mibObj aliases are shortened to maintain compatibility with storage engines that limit the length of column names to 19 characters.

Even in cases where the string property exists in a separate MIB table, it's straightforward to include it as long as the "source" table uses an identical set of index variables. For example, the ifXTable augments the ifTable, meaning the two tables use the same set of instance identifiers – namely ifIndex. Whether or not the MIB definition of the second table declares an AUGMENTS relationship to the first table, objects from tables with this kind of relationship can be mixed in the same group.

In this contrived configuration example, ifDescr (which is from ifTable) is freely mixed with ifName and ifAlias (from ifXTable):

Most SNMP property extenders make it possible to include string properties from a "source" MIB table that is indexed differently from the table containing most of the relevant data. For purposes of configuring property extenders, the table containing the majority of the data (and into which we want to include the string properties) is called the **target table**, and the table containing the string property is called the **source table**. Several different extenders are available; selecting the right one depends on the relationship between the target table and the source table.

A few property extenders also exist whose effect is strictly local to the "target" resource. These extenders are useful for dealing in partial indices and other similar operations that do not involve

looking outside the target MIB table.

SNMP Property Extenders are used in the context of a property element inside an SNMP datacollection group parent element. The property element, when it appears, is a sibling of any mibObj elements beneath the same parent group. The instance and alias attributes of the property element are both required, and serve the same purpose as the same attributes of mibObj. The class-name attribute of the property element contains the full class name (including package) of the Property Extender class needed to join the source and target tables. The property element takes a number of parameter child elements; these parameters are used to configure the property extender class named in class-name. Each extender class recognizes a different set of parameters.

6.4.1. Cisco CBQoS Property Extender

This property extender is used only in very specific circumstances.

When to Use Cisco CBQoS Property Extender

The Cisco CBQoS Property Extender is designed specifically and exclusively for the purpose of including string properties across ifXTable and the several MIB tables that make up the Cisco Class-Based QoS MIB. It is not useful for any other sets of target and source tables.

Configuring Cisco CBQoS Extended Properties

The complex relationships among the various Cisco CBQoS tables are encapsulated in the code of this property extender class. As a result, this extender takes only a single parameter, target-property, whose value must be one of policyName, classMapName, interfaceAlias, or interfaceName.

6.4.2. Enum Lookup Property Extender

The Enum Lookup property extender provides a mechanism that works like a lookup table for values of a local MIB table column.

When to use the Enum Lookup Property Extender

The Enum Lookup property extender may be used to map an enumerated set of integer values to a corresponding set of human-sensible textual values. For example, the dot1dStpPortTable contains two integer columns whose values reflect attributes of a port.

```
dot1dStpPortState OBJECT-TYPE ①
                INTEGER {
    SYNTAX
                    disabled(1),
                    blocking(2),
                    listening(3),
                    learning(4),
                    forwarding(5),
                    broken(6)
                }
 . . .
dot1dStpPortEnable OBJECT-TYPE (2)
    SYNTAX
                INTEGER {
                    enabled(1),
                    disabled(2)
                }
```

① Port STP state enumerated type

2 Port enablement status enumerated type

This extender enables persisting the values of these enumerated integer columns as text that an operator can easily recognize.



While this extender is intended primarily for translating integer values to more descriptive ones as shown in the example below, it could also be used to translate from one set of alphanumeric values to another set.

Configuring the Enum Lookup Property Extender

The Enum Lookup property extender expects zero or more parameters. Only the default-value parameter has a fixed name; if it is present, its value is used any time a lookup cannot be completed. If default-value is not provided and a lookup fails, no value will be returned for the property. The remaining parameters are named for the input values, and their values represent the output values.

This example shows how to map values of dot1dStpPortState and dot1dStpPortEnable to their textual equivalents.

```
<resourceType name="dot1dStpPortEntry" label="dot1d STP Port" resourceLabel="${index}
">
 <persistenceSelectorStrategy class=</pre>
"org.opennms.netmgt.collection.support.PersistAllSelectorStrategy" />
 <storageStrategy class="org.opennms.netmgt.collection.support.IndexStorageStrategy"</pre>
/>
</resourceType>
. . .
<groups>
 <group name="dot1dStpPortTable" ifType="all">
    <mibObj oid=".1.3.6.1.2.1.17.2.15.1.3" instance="dot1dStpPortEntry" alias=</pre>
"dot1dStpPortState" type="string"/> ①
    <mibObj oid=".1.3.6.1.2.1.17.2.15.1.4" instance="dot1dStpPortEntry" alias=</pre>
"dot1dStpPortEnable" type="string"/> ②
    <mibObj oid=".1.3.6.1.2.1.17.2.15.1.10" instance="dot1dStpPortEntry" alias=</pre>
"dot1dStpPortFwTrans" type="counter" />
    <property instance="dot1dStpPortEntry" alias="dot1dStpPortStateText" class-name=</pre>
"org.opennms.netmgt.collectd.EnumLookupPropertyExtender"> ③
      <parameter key="enum-attribute" value="dot1dStpPortState"/>
      <parameter key="1" value="disabled(1)"/>
      <parameter key="2" value="blocking(2)"/>
      <parameter key="3" value="listening(3)"/>
      <parameter key="4" value="learning(4)"/>
      <parameter key="5" value="forwarding(5)"/>
      <parameter key="6" value="broken(6)"/>
    </property>
    <property instance="dot1dStpPortEntry" alias="dot1dStpPortEnableText" class-name=</pre>
"org.opennms.netmgt.collectd.EnumLookupPropertyExtender"> ④
      <!-- Note absence of parenthetical numeric values; they are entirely optional</pre>
-->
      <parameter key="1" value="enabled"/>
      <parameter key="2" value="disabled"/>
    </property>
 </group>
</groups>
```

1 Port STP state enumerated integer attribute

2 Port enablement status enumerated integer attribute

③ Derived port STP state textual attribute dot1dStpPortStateText

④ Derived port enablement status textual attribute dot1dStpPortEnableText

6.4.3. Index Split Property Extender

The Index Split property extender enables extraction of part of a resource's local instance identifier.

When to use the Index Split Property Extender

The Index Split property extender is useful when collecting data from tables with compound indices, because it enables extraction of a single index component. For example, the Cisco Airespace bsnAPIfLoadParametersTable is indexed using the tuple of bsnAPDot3MacAdddress and bsnAPIfSlotId.

```
bsnAPIfLoadParametersEntry OBJECT-TYPE
-- ...
DESCRIPTION
    "An entry (conceptual row) in the Table.
    Entries in this MIB are indexed by
    bsnAPDot3MacAddress and bsnAPIfSlotId"
INDEX {
        bsnAPDot3MacAddress,
        bsnAPIfSlotId
    } ①
```

① bsnAPDot3MacAddress is the first component of the compound index for the entry type for bsnAPIfLoadParametersTable

This extender enables extraction of just the bsnAPIfSlotId component for use in a resource label.

Configuring the Index Split Property Extender

The Index Split property extender expects a single parameter, index-pattern, whose value is a regular expression. The expression must be general enough to match all possible index values for the table at hand, and should include one capturing group. The subpattern matched by the expression's first capturing group will be returned; any further groups are ignored.

This example shows how to extract just the bsnAPIfSlotId index component as a string property.

```
<proup name="bsnAPIfLoadParametersTable" ifType="all">
    <mibObj oid=".1.3.6.1.4.1.14179.2.2.13.1.4" instance="bsnAPIfLoadParametersEntry"
    alias="bsnAPIfLoadNumOfCli" type="integer" />
        <property instance="bsnAPIfLoadParametersEntry" alias="slotNumber" class-name=
"org.opennms.netmgt.collectd.IndexSplitPropertyExtender"> ①
        <property instance="bsnAPIfLoadParametersEntry" alias="slotNumber" class-name=
"org.opennms.netmgt.collectd.IndexSplitPropertyExtender"> ①
        <property instance="bsnAPIfLoadParametersEntry" alias="slotNumber" class-name=
"org.opennms.netmgt.collectd.IndexSplitPropertyExtender"> ①
        <property="slotNumber" class-name="slotNumber" class-name="slo
```

- ① Derived string property slotNumber
- ② Regular expression; the portion in parentheses is what gets extracted. \d+ means "one or more decimal digit characters".

6.4.4. Regex Property Extender

The Regex property extender works similarly to the Index Split property extender, with the added

capability of importing a string property from a source table.

When to Use the Regex Property Extender

The Regex property extender is useful when some portion of the target MIB table's index can be used as an index to the source MIB table. For example, the Cisco Airespace bsnAPIfLoadParametersTable is indexed using the tuple of bsnAPDot3MacAdddress and bsnAPIfSlotId, whereas the bsnAPTable is indexed on bsnAPDot3MacAddress alone.

```
bsnAPIfLoadParametersEntry OBJECT-TYPE
    -- ...
    DESCRIPTION
        "An entry (conceptual row) in the Table.
        Entries in this MIB are indexed by
        bsnAPDot3MacAddress and bsnAPIfSlotId"
    INDEX
                    {
                        bsnAPDot3MacAddress,
                        bsnAPIfSlotId
                    } ①
    -- ...
bsnAPEntry OBJECT-TYPE
    -- ...
    DESCRIPTION
        "An entry in the bsnAPTable."
                   { bsnAPDot3MacAddress } (2)
    INDEX
    -- ...
```

- ① bsnAPDot3MacAddress is the first component of the compound index for the entry type for bsnAPIfLoadParametersTable
- ② bsnAPDot3MacAddress is the sole index for the entry type for bsnAPTable

By extracting just the first index component and using the result as an index into the source MIB table, it's possible to import the human-sensible bsnAPName string property from the source MIB table.

Configuring the Regex Property Extender

The Regex property extender expects three parameters, all of which are required:

Table 93. Regex Property Extender Parameters

Name	Description
source-type	The name of the resourceType associated with the source MIB table
source-alias	The alias name of the string property to be imported from the source MIB table
index-pattern	A regular expression containing one matching group

The index-pattern expression must meet the same criteria as for the Index Split property extender. The subpattern matched by its first capturing group will be used as an index into the source MIB table; any further groups are ignored.

This example shows how to use the value of bsnAPDot3MacAddress as an index into the bsnAPTable.

```
<resourceType name="bsnAPEntry" label="Cisco Wireless AP" resourceLabel="${bsnAPName}}
(index ${index})">
    <persistenceSelectorStrategy class=</pre>
"org.opennms.netmgt.collection.support.PersistAllSelectorStrategy" />
    <storageStrategy class="org.opennms.netmgt.collection.support.IndexStorageStrategy"</pre>
/>
</resourceType>
<resourceType name="bsnAPIfLoadParametersEntry" label="Cisco Wireless AP Resources"
resourceLabel="${bsnAPName} (index ${index})">
    <persistenceSelectorStrategy class=</pre>
"org.opennms.netmgt.collection.support.PersistAllSelectorStrategy" />
    <storageStrategy class="org.opennms.netmgt.collection.support.IndexStorageStrategy"</pre>
/>
</resourceType>
<groups>
    <proup name="bsnAPTable" ifType="all">
          <mibObj oid=".1.3.6.1.4.1.14179.2.2.1.1.3" instance="bsnAPEntry" alias="bsnAPName"
type="string" /> ①
    </group>
    <group name="bsnAPIfLoadParametersTable" ifType="all">
          <mibObj oid=".1.3.6.1.4.1.14179.2.2.13.1.4" instance="bsnAPIfLoadParametersEntry"</pre>
alias="bsnAPIfLoadNumOfCli" type="integer" />
          <property instance="bsnAPIfLoadParametersEntry" alias="bsnAPName" class-name="bsnAPName" class-name="bsnAPName"" class-name="bsnAPName""" class-name="bsnAPName"" class-name="bsnAPName"" class-nam
"org.opennms.netmgt.collectd.RegexPropertyExtender"> ②
               <parameter key="source-type" value="bsnAPEntry" />
              <parameter key="source-alias" value="bsnAPName" />
              <parameter key="index-pattern" value="^(.+)\.\d+$" /> ③
          </property>
    </group>
</groups>
```

- ① Regular string property bsnAPName on the source table
- ② Extended string property bsnAPName on the target table
- ③ Regular expression; the portion in parentheses is what gets extracted. \d+ means "one or more decimal digit characters".

6.4.5. Pointer-Like Index Property Extender

The Pointer-Like Index property extender makes it possible to use the value of an attribute from the target MIB table as the index into the source MIB table. Unlike the Index Split and Regex extenders,

this extender class does not require the target and source MIB tables to share any index components.

When to Use the Pointer-Like Index Property Extender

The Pointer-Like Index property extender is useful when the target MIB table contains a column whose value can be used as an index into the source MIB table. For example, the Cisco Process MIB's cpmCPUTotalTable has its own index that is not shared with any other tables, but its cpmCPUTotalPhysicalIndex column contains an integer which can be used as an index into the entPhysicalTable.

```
cpmCPUTotalEntry OBJECT-TYPE
    -- ...
    DESCRIPTION
        "Overall information about the CPU load. Entries in this
        table come and go as CPUs are added and removed from the
        system."
                    { cpmCPUTotalIndex } ①
    INDEX
    -- ...
cpmCPUTotalPhysicalIndex OBJECT-TYPE (2)
    -- ...
    DESCRIPTION
        "The entPhysicalIndex of the physical entity for which
        the CPU statistics in this entry are maintained.
        The physical entity can be a CPU chip, a group of CPUs,
        a CPU card etc. The exact type of this entity is described by
        its entPhysicalVendorType value. If the CPU statistics
        in this entry correspond to more than one physical entity
        (or to no physical entity), or if the entPhysicalTable is
        not supported on the SNMP agent, the value of this object
       must be zero."
    -- ...
entPhysicalEntry OBJECT-TYPE
    -- ...
    DESCRIPTION
            "Information about a particular physical entity.
            Each entry provides objects (entPhysicalDescr,
            entPhysicalVendorType, and entPhysicalClass) to help an NMS
            identify and characterize the entry, and objects
            (entPhysicalContainedIn and entPhysicalParentRelPos) to help
            an NMS relate the particular entry to other entries in this
            table."
           { entPhysicalIndex } 3
   INDEX
    -- ...
```

① The cpmCPUTotalTable entry type is indexed on cpmCPUTotalIndex, which has no meaning outside this table

- ② The cpmCPUTotalPhysicalIndex column contains a value of entPhysicalIndex corresponding to the CPU referenced in a given row
- ③ The entPhysicalTable entry type is indexed on entPhysicalIndex and provides many useful textual columns.

By treating cpmCPUTotalPhysicalIndex somewhat like a pointer, it's possible to import string properties from the entPhysicalTable for use in the resource-label.



Some combinations of Cisco hardware and software appear to use values of cpmCPUTotalIndex that are directly interchangeable with entPhysicalIndex. This relationship does not hold across all product lines or software revisions.

Configuring the Pointer-Like Index Property Extender

The Pointer-Like Index property extender expects three parameters, all of which are required:

Name	Description
source-type	The name of the resourceType associated with the source MIB table
source-attribute	The alias name of the string property to be imported from the source MIB table
target-index- pointer-column	The alias name of the column in the target MIB table whose value may be used as an index into the source MIB table

Table 94. Pointer-Like Index Property Extender Parameters

This example shows how to use cpmCPUTotalPhysicalIndex as a pointer-like index into the entPhysicalTable. The target resource gains a pair of string properties, which we will call cpmCPUTotalName and cpmCPUTotalDescr.

```
<resourceType name="entPhysicalEntry" label="Physical Entity" resourceLabel=
"${entPhysicalName} (${entPhysicalDescr}))">
  <persistenceSelectorStrategy class=</pre>
"org.opennms.netmgt.collection.support.PersistAllSelectorStrategy"/>
  <storageStrategy class="org.opennms.netmgt.collection.support.IndexStorageStrategy</pre>
"/>
</resourceType>
<resourceType name="cpmCPUTotalEntry" label="Cisco CPU Total" resourceLabel=
"${cpmCPUTotalName} (${cpmCPUTotalDescr})">
<persistenceSelectorStrategy class=</pre>
"org.opennms.netmgt.collection.support.PersistAllSelectorStrategy" />
<storageStrategy class="org.opennms.netmgt.collection.support.IndexStorageStrategy"</pre>
/>
</resourceType>
<groups>
 <group name="entity-physical-table" ifType="all">
    <mibObj oid=".1.3.6.1.2.1.47.1.1.1.2" instance="entPhysicalEntry" alias=
"entPhysicalDescr" type="string"/> ①
    <mibObj oid=".1.3.6.1.2.1.47.1.1.1.7" instance="entPhysicalEntry" alias=
"entPhysicalName" type="string"/> ②
 </group>
 <proup name="cpm-cpu-total" ifType="all">
    <mibObj oid=".1.3.6.1.4.1.9.9.109.1.1.1.1.2"</pre>
                                                   instance="cpmCPUTotalEntry" alias=
"cpmCPUTotalPhysicalIndex" type="string" /> ③
    <mibObj oid=".1.3.6.1.4.1.9.9.109.1.1.1.1.8"
                                                  instance="cpmCPUTotalEntry" alias=
"cpmCPUTotal5minRev"
                            type="gauge" />
    <property instance="cpmCPUTotalEntry" alias="cpmCPUTotalName" class-name=</pre>
"org.opennms.netmgt.collectd.PointerLikeIndexPropertyExtender"> ④
      <parameter key="source-type" value="entPhysicalEntry"/>
      <parameter key="source-attribute" value="entPhysicalName"/> (5)
      <parameter key="target-index-pointer-column" value="cpmCPUTotalPhysicalIndex"/>
    </property>
    <property instance="cpmCPUTotalEntry" alias="cpmCPUTotalDescr" class-name=</pre>
"org.opennms.netmgt.collectd.PointerLikeIndexPropertyExtender"> 6
      <parameter key="source-type" value="entPhysicalEntry"/>
      <parameter key="source-attribute" value="entPhysicalDescr"/> ⑦
      <parameter key="target-index-pointer-column" value="cpmCPUTotalPhysicalIndex"/>
    </property>
 </group>
</groups>
```

<1>, <2> First we collect entPhysicalDescr and entPhysicalName in the source group, which uses a resource-type associated with the entPhysicalTable <3> Then we collect the pointer-like cpmCPUTotalPhysicalIndex in the target group, whose resource-type is associated with the cpmCPUTotalTable <4> We derive cpmCPUTotalName in the target group telling the extender to use the pointer-like property's value as an index into the source table, and specify that we want to "pull

over" the source attribute entPhysicalName <5> <6> Deriving cpmCPUTotalDescr is almost identical, except that this time we are pulling over the value of entPhysicalDescr <7>

6.4.6. SNMP Interface Property Extender

The SNMP Interface property extender does much the same job as the Pointer-Like Index property extender, but it is specialized for importing properties from the *ifTable*. Resources representing rows in the *ifTable* are modeled differently in *OpenNMS Meridian* compared to other tabular resource types, and this extender accounts for those differences.

When to Use the SNMP Interface Property Extender

Use the SNMP Interface property extender when the string property you want to import is associated with a network interface which is represented by a row in the ifTable. For example, the dot1dBasePortTable has its own index which does not share any components with any other table, but its dot1dBasePortIfIndex column contains a value that is a valid ifIndex.

```
dot1dBasePortEntry OBJECT-TYPE
       -- ...
       DESCRIPTION
           "A list of information for each port of the bridge."
       -- ...
      INDEX { dot1dBasePort } ①
 -- ...
  dot1dBasePortIfIndex OBJECT-TYPE (2)
       -- ...
       DESCRIPTION
           "The value of the instance of the ifIndex object,
           defined in IF-MIB, for the interface corresponding
           to this port."
      ::= { dot1dBasePortEntry 2 }
  -- ...
ifEntry OBJECT-TYPE
   -- ...
    DESCRIPTION
            "An entry containing management information applicable to a
            particular interface."
   INDEX { ifIndex } 3
    ::= { ifTable 1 }
```

- ① The entry type for dot1dBasePortTable is indexed on dot1dBasePort, which has no significance outside this table
- ② But dot1dBasePortTable contains column dot1dBasePortIfIndex, which tells us the ifIndex corresponding to the physical port underlying to the associated bridge base port
- ③ ifIndex is the index of the ifTable entry type (and also of the ifXTable entry type)

By using this extender, it's possible to import string attributes from the ifTable, ifXTable, or

another table that augments the *ifTable*.

Configuring the SNMP Interface Property Extender

The SNMP Interface property extender expects two or three parameters:

Table 95.	SNMP	Interface	Property	Extender	Parameters

Name	Description	Requi red	Default value
source-attribute	The alias name of the string property to be imported from the source MIB table	requir ed	_
source-ifindex- attribute	The name of the column in the source MIB table that contains a value of <code>ifIndex</code>	option al	ifIndex
target-ifindex- pointer-column	The name of the column in the target MIB table that contains a value of <code>ifIndex</code>	requir ed	-

This example shows how to use dot1dBasePortIfIndex as a pointer-like index to import ifDescr from the ifTable, and ifName and ifAlias from the ifXTable, into a trio of new string properties in the target resource.

```
<resourceType name="dot1dBasePortEntry" label="dot1d Base Port" resourceLabel=
"${index}">
 <persistenceSelectorStrategy class=</pre>
"org.opennms.netmgt.collection.support.PersistAllSelectorStrategy" />
 <storageStrategy class="org.opennms.netmgt.collection.support.IndexStorageStrategy"</pre>
/>
</resourceType>
<groups>
 <proup name="ifTable" ifType="all">
    <mibObj oid=".1.3.6.1.2.1.2.2.1.1"
                                          instance="ifIndex" alias="interfaceIndex"
type="string" /> ①
    <mibObj oid=".1.3.6.1.2.1.2.2.1.2"
                                         instance="ifIndex" alias="interfaceDescr"
type="string" />
    <mibObj oid=".1.3.6.1.2.1.31.1.1.1.1" instance="ifIndex" alias="interfaceName"
type="string" />
    <mibObj oid=".1.3.6.1.2.1.31.1.1.1.18" instance="ifIndex" alias="interfaceAlias"</pre>
type="string" />
 </group>
 <group name="dot1dBasePortTable" ifType="all">
    <mibObj oid=" .1.3.6.1.2.1.17.1.4.1.1" instance="dot1dBasePortEntry" alias=
"dot1dBasePort"
                       type="string" />
    <mibObj oid=" .1.3.6.1.2.1.17.1.4.1.2" instance="dot1dBasePortEntry" alias=
"dot1dBasePortIfIndex" type="string" /> ②
    <mibObj oid=" .1.3.6.1.2.1.17.1.4.1.4" instance="dot1dBasePortEntry" alias=
"d1dBPDelayExDiscard" type="counter" />
    <mibObj oid=" .1.3.6.1.2.1.17.1.4.1.5" instance="dot1dBasePortEntry" alias=
"d1dBPMtuExDiscard"
                     type="counter" />
    <property instance="dot1dBasePortEntry" alias="dot1dBasePortIfDescr" class-name=</pre>
"org.opennms.netmgt.collectd.InterfaceSnmpPropertyExtender"> ③
     <parameter key="source-ifindex-attribute" value="interfaceIndex"/>
     <parameter key="source-attribute" value="interfaceDescr"/> ④
      <parameter key="target-ifindex-pointer-column" value="dot1dBasePortIfIndex"/>
    </property>
    <property instance="dot1dBasePortEntry" alias="dot1dBasePortIfName" class-name=</pre>
"org.opennms.netmqt.collectd.InterfaceSnmpPropertyExtender"> (5)
     <parameter key="source-ifindex-attribute" value="interfaceIndex"/>
     <parameter key="source-attribute" value="interfaceName"/> ⑥
     <parameter key="target-ifindex-pointer-column" value="dot1dBasePortIfIndex"/>
    </property>
    <property instance="dot1dBasePortEntry" alias="dot1dBasePortIfAlias" class-name=</pre>
"org.opennms.netmgt.collectd.InterfaceSnmpPropertyExtender"> ⑦
     <parameter key="source-ifindex-attribute" value="interfaceIndex"/>
     <parameter key="source-attribute" value="interfaceAlias"/> ⑧
     <parameter key="target-ifindex-pointer-column" value="dot1dBasePortIfIndex"/>
    </property>
 </group>
</groups>
```

- ① First we collect all of ifIndex, ifDescr, ifName, and ifAlias in a group associated with the ifIndex source resource-type, using modified names to avoid collisions with internal workings (the ifIndex type is built in, so we do not need a custom resource-type definition for it)
- ② Then we collect the pointer-like column dot1dBasePortIfIndex in the target group
- ③ To derive the dot1dBasePortIfDescr string property, we tell the extender which target attribute contains the pointer-like value, which source column needs to have a matching value, and that we want to "pull over" the interfaceDescr property <4> from the source group
- ④ Deriving dot1dBasePortIfName is almost identical, except that we want the property interfaceName <6> from the source group instead
- ⑤ Again with dot1dBasePortIfAlias, we repeat ourselves except that our desired property from the source group is interfaceAlias <8>

6.5. Administration and Troubleshooting

6.5.1. Collectd Administration

This section describes reference and administrative information associated with collectd.

File	Description
<pre>\$OPENNMS_HOME/etc/collectd- configuration.xml</pre>	Configuration file for global collectd daemon and collectors configuration. (See Configuring Collectd.)
<pre>\$OPENNMS_HOME/logs/collectd.l og</pre>	Log file for all collectors and the global collectd daemon.
<pre>\$OPENNMS_HOME/etc/snmp- graph.properties</pre>	RRD graph definitions to render performance data measurements in the UI.
<pre>\$OPENNMS_HOME/etc/snmp- graph.properties.d</pre>	Directory with RRD graph definitions for devices and applications to render performance data measurements in the UI.
<pre>\$OPENNMS_HOME/etc/events/open nms.events.xml</pre>	Event definitions for collectd, i.e., <i>dataCollectionSucceeded</i> , and <i>dataCollectionFailed</i> .
<pre>\$OPENNMS_HOME/etc/resource- types.d</pre>	Directory to store generic resource type definitions. (See Resource Types.)

Table 96. Configuration and log files related to Collectd

6.5.2. Shell Commands

A number of *Karaf Shell* commands are made available to help administer and diagnose issues related to performance data collection.

To use the commands, log into the Karaf Shell on your system using:

```
ssh -p 8101 admin@localhost
```



The Karaf shell uses the same credential as the web interface. Users must be associated with the ADMIN role to access the shell.



In order to keep the session open while executing long-running tasks without any user input add -o ServerAliveInterval=10 to your ssh command.

Ad hoc collection

The opennms:collect *Karaf Shell* command can be used to trigger and perform a collection on any of the available collectors.

The results of the collection (also referred to as the "collection set") will be displayed in the console after a successful collection. The resulting collection set will not be persisted, nor will any thresholding be applied.

List all of the available collectors:

opennms:list-collectors

Invoke the SnmpCollector against interface 127.0.0.1 on NODES:n1.

opennms:collect -n NODES:n1 org.opennms.netmgt.collectd.SnmpCollector 127.0.0.1

Invoke the SnmpCollector against interface 127.0.0.1 on NODES:n1 via the MINION location.

opennms:collect -1 MINION -n NODES:n1 org.opennms.netmgt.collectd.SnmpCollector 127.0.0.1



Setting the location on the command line will override the node's location.



If you see errors caused by RequestTimedOutException's when invoking a collector at a remote location, consider increasing the time to live. By default, 'collectd will use the service interval as the time to live.

Invoke the JdbcCollector against 127.0.0.1 while specifying some of the collector parameters.

opennms:collect org.opennms.netmgt.collectd.JdbcCollector 127.0.0.1 collection=PostgreSQL driver=org.postgresql.Driver url=jdbc:postgresql://OPENNMS_JDBC_HOSTNAME/postgres user=postgres



Some collectors, such as the JdbcCollector, can be invoked without specifying a node.

Persist a collection :

```
opennms:collect -1 MINION -n NODES=n1 -p org.opennms.netmgt.collectd.SnmpCollector
127.0.0.1
```



-p/--persist option will persist collection set there by introducing an extra datapoint other than data collected during already configured collection interval.

A complete list of options is available using:

```
opennms:collect --help
```

Interpreting the output

After a successful collection, the collection set will be displayed in the following format:

resource a group 1 attribute attribute group 2 attribute resource b group 1 attribute

The description of the resources, groups and attribute may differ between collectors. This output is independent of the persistence strategy that is being used.

Measurements & Resources

The following *Karaf Shell* commands are made available to help enumerate, view and manage measurement related resources.

The opennms: show-measurement-resources command can be used to enumerate or lookup resources:

admin@opennms> opennms:show-measurement-resources --node NODES:node --no-children TD: node[NODES:node] Name: NODES:node Label: node Type: Node element/node.jsp?node=NODES:node Link: Children: node[NODES:node].nodeSnmp[] node[NODES:node].interfaceSnmp[lo] node[NODES:node].interfaceSnmp[opennms-jvm] node[NODES:node].responseTime[192.168.238.140] node[NODES:node].responseTime[192.168.39.1] node[NODES:node].responseTime[172.17.0.1] node[NODES:node].responseTime[127.0.0.1]

The opennms:delete-measurement-resources command can be used to delete resources, and all of the associated metrics:

```
admin@opennms> opennms:delete-measurement-resources
"node[NODES:node].responseTime[127.0.0.1]"
Deleting measurements and meta-data associated with resource ID
'node[NODES:node].responseTime[127.0.0.1]'...
Done.
```

The opennms:show-measurements command can be used to render the values of the attributes (measurements) associated with a particular resource:

```
admin@opennms> opennms:show-measurements -a ifHCInOctets
"node[NODES:node].interfaceSnmp[lo]"
Resource with ID 'node[NODES:node].interfaceSnmp[lo]' has attributes:
[ifHCOutUcastPkts, ifInDiscards, ifHCInBroadcastPkts, ifHCInOctets, ifHCOutOctets,
ifOutErrors, ifHCOutMulticastPkt, ifHCInUcastPkts, ifInErrors, ifHCInMulticastPkts,
ifHCOutBroadcastPkt, ifOutDiscards]
Limiting attributes to: [ifHCInOctets]
timestamp,ifHCInOctets
Fri Sep 13 13:30:00 EDT 2019,NaN
Fri Sep 13 13:40:00 EDT 2019,NaN
```

The opennms: show-newts-samples command can be used to view the raw samples (collected values) associated with a particular resource.

admin@opennms> opennms:show-newts-samples -a ifHCInOctets
"node[NODES:node].interfaceSnmp[lo]"
Resource with ID 'node[NODES:node].interfaceSnmp[lo]' has attributes:
[ifHCOutUcastPkts, ifInDiscards, ifHCInBroadcastPkts, ifOutErrors, ifHCInOctets,
ifHCOutMulticastPkt, ifHCOutOctets, ifHCInUcastPkts, ifInErrors, ifHCInMulticastPkts,
ifOutDiscards, ifHCOutBroadcastPkt]
Limiting attributes to: [ifHCInOctets]
Fetching samples for Newts resource ID 'snmp:2:lo:mib2-X-interfaces'...
Fri Sep 13 14:31:05 EDT 2019,ifHCInOctets,1271178704.0000

Stress Testing

The opennms:stress-metrics *Karaf Shell* command can be used to simulate load on the active persistence strategy, whether it be RRDtool, JRobin, or Newts.

The tool works by generating collection sets, similar to those built when performing data collection, and sending these to the active persistence layer. By using the active persistence layer, we ensure that we use the same write path which is used by the actual data collection services.

Generate samples for **10 nodes** every **15 seconds** and printing the statistic report every **30 seconds**:

```
opennms:stress-metrics -n 10 -i 15 -r 30
```

While active, the command will continue to generate and persist collection sets. During this time you can monitor the system I/O and other relevant statistics.

When your done, use **CTRL+C** to stop the stress tool.

A complete list of options is available using:

```
opennms:stress-metrics --help
```

Interpreting the output

The statistics output by the tool can be be interpreted as follows:

numeric-attributes-generated

The number of numeric attributes that were sent to the persistence layer. We have no guarantee as to whether or not these were actually persisted.

string-attributes-generated

The number of string attributes that were sent to the persistence layer. We have no guarantee as to whether or not these were actually persisted.

batches

The count is used to indicate how many batches of collection sets (one at every interval) were sent to the persistence layer. The timers show how much time was spent generating the batch, and sending the batch to the persistence layer.

Chapter 7. Thresholding


Thresholding allows you to define limits against network performance metrics of a managed entity to trigger an event when a value goes above or below the specified limit.

- High
- Low
- Absolute Value
- Relative Change

7.1. How Thresholding Works in OpenNMS Meridian

OpenNMS Meridian uses *collectors* to implement data collection for a particular protocol or family of protocols (SNMP, JMX, HTTP, XML/JSON, WS-Management/WinRM, JDBC, etc.). You can specify configuration for a particular collector in a *collection package*: essentially the set of instructions that drives the behavior of the collector.

The *collectd* daemon gathers and stores performance data from these collectors. This is the data against which OpenNMS Meridian applies thresholds. Thresholds trigger events when a specified threshold value is met. You can further create notifications and alarms for threshold events.



7.2. What Triggers a Thresholding Event?

OpenNMS Meridian uses four thresholding algorithms that trigger an event when the datasource value:

- Low equals or drops below the threshold value and re-arms when it equals or comes back up above the re-arm value (e.g., available disk space falls under the specified value)
- **High** equals or exceeds the threshold value, and re-arms when it equals or drops below the rearm value (e.g., bandwidth use exceeds the specified amount)
- Absolute changes by the specified amount (e.g., on a fiber-optic link, a change in loss of anything greater than 3 dB is a problem regardless of what the original or final value is)
- **Relative** changes by percent (e.g., available disk space changes more than 5% from the last poll)

These thresholds can be **basic** (tested against a single value) or an **expression** (evaluated against multiple values in an expression).

OpenNMS Meridian applies these algorithms against any performance data (telemetry) collected by collected or pushed to telemetryd. This includes, but is not limited to, metrics such as CPU load, bandwidth, disk space, etc.



The basic walkthrough focuses on how to set simple thresholds using default values in the OpenNMS Meridian setup. For information on setting and configuring collectors, collectd, and the *collectd-configuration.xml* file, see Performance Management.

7.3. Basic Walk-through – Thresholding

This section describes how to create a basic threshold for a single, system-wide variable: the number of logged-in users. Our threshold will tell OpenNMS Meridian to create an event when the number of logged-in users on the device exceeds two, and re-arm when it falls below two.

Before creating a threshold, you need to make sure you are collecting the metric against which you want to threshold.

7.3.1. Determine You are Collecting Metric

In this case, we have chosen a metric (number of logged-in users) that is collected by default. We are also using data collected via SNMP. (For information on other collectors, see <u>Collectors</u>.)

- 1. In the OpenNMS Meridian UI, choose Reports>Resource Graphs.
- 2. Select one of the listed resources.
- 3. Under SNMP Node Data, select Node-level Performance Data and choose Graph Selection.
- 4. Scroll to find the Number of Users graph.
 - a. You can click the binoculars icon to display only this graph.

7.3.2. Create a Threshold

- 1. Select <User_Name>>Configure OpenNMS from the top-right menu.
- 2. Under Performance Measurement, choose Configure Thresholds.
 - a. A screen with a list of preconfigured threshold groups appears. We will work with netsnmp. For information on how to create a threshold group, see Creating a Threshold Group.
- 3. Click Edit beside the netsnmp group.
- 4. Click Create New Threshold at the bottom of the Basic Thresholds area of the screen.
- 5. Set the following information and click Save:

Field	Value	Description
-------	-------	-------------

Туре	high	Triggers an event when the datasource value equals or exceeds the threshold value, and re-arms when it equals or drops below the re-arm value
Datasource	hrSystemNumUsers	Name of the datasource you want to threshold against. For this tutorial, we have provided the datasource for logged-in users.
		For information on how to determine a metric's datasource, see Determine the Datasource.
Datasource label	leave blank	Optional text label. Not required for this tutorial.
Value	2	The value above which we want to trigger an event. In this case, we want to trigger an event when the number of logged-in users exceeds two.
Re-arm	2	The value below which we want the system to re-arm. In this case, once the number of logged-in users falls below two.
Trigger	3	The number of consecutive times the threshold value can occur before the system triggers an event. Since our default polling period is 5 minutes, a value of 3 means OpenNMS Meridian would create a threshold event if there are more than 2 users for 15 minutes.
Description	leave blank	Optional text to describe your threshold.

Triggered UEI	leave blank	A custom uniform event identifier (UEI) sent into the events system when the threshold is triggered. A custom UEI for each threshold makes it easier to create notifications. If left blank, it defaults to the standard thresholds UEIs.
Re-armed UEI	leave blank	A custom uniform event identifier (UEI) sent into the events system when the threshold is re-armed.

7.3.3. Testing the Threshold

To test the threshold we just created, log a second person into the node you are monitoring. Navigate to the Events page. You should see an event that indicates your threshold triggered when more than one user logged in.

Log out the second user. The **Events** page should indicate that the system has re-armed.

7.3.4. Creating a Threshold for CPU Usage

This procedure describes how to create an expression-based threshold when the five-minute CPU load average metric reaches or goes above 70% for two consecutive measurement intervals. Expression-based thresholds are useful when you need to threshold on a percentage, not the actual value of the data collected.



Expression-based thresholds work only if the data sources in question lie in the same directory.

- 1. Select <<u>User_Name</u>>>Configure OpenNMS from the top-right menu.
- 2. Under Performance Measurement, choose Configure Thresholds.
- 3. Click Edit beside the netsnmp group.
- 4. Click Create New Expression-based Threshold.
- 5. Fill in the following information:

Field	Value	Description
Туре	high	Triggers an event when the datasource value equals or exceeds the threshold value, and re-arms when it equals or drops below the re-arm value

Expression	((loadavg5 / 100) / CpuNumCpus) * 100	Divides the five-minute CPU load average by 100 (to obtain the effective load average ^{), which} is then divided by the number of CPUs. This value is then multiplied by 100 to provide a percentage.
Datasource type	node	The type of datasource from which you are collecting data.
Datasource label	leave blank	Optional text label. Not required for this tutorial.
Value	70	Trigger an event when the five-minute CPU load average goes above 70%.
Re-arm	50	Re-arm the system when the five-minute CPU load average drops below 50%
Trigger	2	The number of consecutive times the threshold value can occur before the system triggers an event. In this case, when the five-minute CPU load average goes above 70% for two consecutive polling periods.
Description	Trigger an alert when the five- minute CPU load average metric reaches or goes above 70% for two consecutive measurement intervals	Optional text to describe your threshold.
Triggered UEI	leave blank	See the table in Create a Threshold for details.
Re-armed UEI	leave blank	See the table in Create a Threshold for details.


6. Click Save.

7.3.5. Determining the Datasource

Creating a threshold requires the name of the datasource generating the metrics on which you want to threshold. Datasource names for the SNMP protocol appear in etc/snmp-

graph.properties.d/.

- 1. To determine the name of the datasource, navigate to the Resource Graphs screen. For example,
 - a. Reports>Resource Graphs.
 - b. Select one of the listed resources.
 - c. Under SNMP Node Data, select Node-level Performance Data and choose Graph Selection.
- 2. Scroll through the graphs to find the title of the graph that displays the metric on which you want to threshold. For example, "Number of Processes" or "System Uptime":



- 3. Go to etc/snmp-graph.properties.d/ and search for the title of the graph (for example, "System Uptime").
- 4. Note the name of the datasource, and enter it in the Datasource field when you create your threshold.

7.3.6. Create a Threshold Group

A threshold group associates a set of thresholds to a service (e.g., thresholds that apply to all Cisco devices). *OpenNMS Meridian* includes seven preconfigured, editable threshold groups:

• mib2

- cisco
- hrstorage
- netsnmp
- juniper-srx
- netsnmp-memory-linux
- netsnmp-memory-nonlinux

You can edit an existing group (through the UI) or create a new one (in the *thresholds.xml* file located in **\$OPENNMS_HOME/etc/thresholds.xml**). Once you create the group, you can then define it in the *thresholds.xml* file or define it in the UI.

We will create a threshold group called "demo_group".

1. Type the following in the *thresholds.xml* file.

```
<proup name="demo_group" rrdRepository="/opt/opennms/share/rrd/snmp/">
</group>
```

- 2. Once you have created the group in the *thresholds.xml* file, switch to the UI, go to the threshold screen and click Request a reload threshold packages configuration.
 - a. The group you created should appear in the UI.
- 3. Click Edit to edit it.

The following is a sample of how the threshold appears in the *thresholds.xml* file:

```
<group name="demo_group" rrdRepository="/opt/opennms/share/rrd/snmp/"> 1
        <expression type="high" ds-type="hrStorageIndex" value="90.0"
        rearm="75.0" trigger="2" ds-label="hrStorageDescr"
        filterOperator="or" expression="hrStorageUsed / hrStorageSize * 100.0">
            <resource-filter
field="hrStorageType">^\.1\.3\.6\.1\.2\.1\.25\.2\.1\.4$</resource-filter> (2)
        </expression>
</group>
```

① The name of the group and the directory of the stored data.

② The details of the threshold including type, datasource type, threshold value, rearm value, etc.

7.3.7. Create a Notification on a Threshold Event

A custom UEI for each threshold makes it easier to create notifications.

7.4. Thresholding Service

The Thresholding Service is the component responsible for maintaining the state of the performance metrics and for generating alarms from these when thresholds are triggered (armed)

or cleared (unarmed).

The thresholding service listens for and visits performance metrics *after* they are persisted to the time series database.

The state of the thresholds are held in memory and pushed to persistent storage only when they are changed.

7.4.1. Distributed Thresholding with Sentinel

Thresholding for streaming telemetry with telemetryd is supported on Sentinel when using Newts. When running on Sentinel, the thresholding state can be stored in either Cassandra or PostgreSQL. Given that Newts already requires Cassandra, we recommend using Casssandra in order to help minimize the load on PostgreSQL.

Thresholding on Sentinel uses the same configuration files as *OpenNMS Meridian* and operates similarly. When a thresholding changes to/from trigger or cleared, and event is published which is processed by *OpenNMS Meridian* and the alarm is created or updated.

7.5. Shell Commands

The following shell commands are made available to help debug and manage thresholding.

Enumerate the persisted threshold states using opennms:threshold-enumerate:

```
admin@opennms> opennms:threshold-enumerate
Index State Key
1 23-127.0.0.1-hrStorageIndex-hrStorageUsed / hrStorageSize * 100.0-
/opt/opennms/share/rrd/snmp-RELATIVE_CHANGE
2 23-127.0.0.1-if-ifHCInOctets * 8 / 1000000 / ifHighSpeed * 100-
/opt/opennms/share/rrd/snmp-HIGH
3 23-127.0.0.1-node-((loadavg5 / 100) / CpuNumCpus) * 100.0-
/opt/opennms/share/rrd/snmp-HIGH
4 23-127.0.0.1-if-ifInDiscards + ifOutDiscards-/opt/opennms/share/rrd/snmp-HIGH
```

Each state is uniquely identified by a state key and aliased by the given index. Indexes are scoped to the particular shell session and provided as an alternative to specifying the complete state key in subsequent commands.

Display state details using opennms:threshold-details:

```
admin@opennms> opennms:threshold-details 1
multiplier=1.333
lastSample=64.77758166043765
previousTriggeringSample=28.862826722171075
interpolatedExpression='hrStorageUsed / hrStorageSize * 100.0'
```

```
admin@opennms> opennms:threshold-details 2
exceededCount=0
armed=true
interpolatedExpression='ifHCInOctets * 8 / 1000000 / ifHighSpeed * 100'
```



Different types of thresholds will display different properties.

Clear a particular persisted state using opennms:threshold-clear:

admin@opennms> opennms:threshold-clear 2

Or clear all the persisted states with opennms: threshold-clear-all:

admin@opennms> opennms:threshold-clear-all
Clearing all thresholding states....done

Chapter 8. Events

Events are central to the operation of the OpenNMS Meridian platform, so it's critical to have a firm grasp of this topic.



Whenever something in OpenNMS Meridian appears to work by magic, it's probably events working behind the curtain.

8.1. Anatomy of an Event

Events are structured historical records of things that happen in OpenNMS Meridian and the nodes, interfaces, and services it manages. Every event has a number of fixed **fields** and zero or more **parameters**.

Mandatory Fields

UEI (Universal Event Identifier)

A string uniquely identifying the event's type. UEIs are typically formatted in the style of a URI, but the only requirement is that they start with the string uei.

Event Label

A short, static label summarizing the gist of all instances of this event.

Description

A long-form description describing all instances of this event.

Log Message

A long-form log message describing this event, optionally including expansions of fields and parameters so that the value is tailored to the event at hand.

Severity

A severity for this event type. Possible values range from Cleared to Critical.

Event ID

A numeric identifier used to look up a specific event in the OpenNMS Meridian system.

Notable Optional Fields

Operator Instruction

A set of instructions for an operator to respond appropriately to an event of this type.

Alarm Data

If this field is provided for an event, OpenNMS Meridian will create, update, or clear **alarms** for events of that type according to the alarm-data specifics.

8.2. Sources of Events

Events may originate within OpenNMS Meridian itself or from outside.

Internally-generated events can be the result of the platform's monitoring and management functions (*e.g.* a monitored node becoming totally unavailable results in an event with the UEI uei.opennms.org/nodes/nodeDown) or they may act as inputs or outputs of housekeeping processes.

The following subsections summarize the mechanisms by which externally-created events can arrive.

8.2.1. SNMP Traps

If SNMP-capable devices in the network are configured to send **traps** to OpenNMS Meridian, these traps are transformed into events according to pre-configured rules. The **Trapd** service daemon, which enables OpenNMS Meridian to receive SNMP traps, is enabled by default.



Disabling the Trapd service daemon will render OpenNMS Meridian **incapable** of receiving SNMP traps.

Event definitions are included with OpenNMS Meridian for traps from many vendors' equipment.

Traps forwarded via proxy

When SNMP traps are forwarded through a proxy using SNMPv2c or SNMPv3, preserving the original source IP address is a challenge due to the lack of an agent-addr field in the TRAP-V2 PDU used in those protocol versions. RFC 3584 defines an optional varbind snmpTrapAddress (.1.3.6.1.6.3.18.1.3.0) which can be added to forwarded traps to convey the original source IP address.

To configure OpenNMS Meridian to honor snmpTrapAddress when present, set use-address-fromvarbind="true" in the top-level element of \${OPENNMS_HOME}/etc/trapd-configuration.xml and restart OpenNMS Meridian.

Configuration example for using RFC 3584 helper varbinds in forwarded traps

```
<trapd-configuration<1> snmp-trap-port="162" new-suspect-on-trap="false" use-address-
from-varbind="true"<2>/>
```

① Top-level trapd-configuration element

② New attribute to enable use of snmpTrapAddress varbind, when present

8.2.2. Syslog Messages

Syslog messages sent over the network to OpenNMS Meridian can be transformed into events according to pre-configured rules.



The Syslogd service daemon, which enables OpenNMS Meridian to receive syslog messages over the network, must be enabled for this functionality to work. This service daemon is **disabled** by default.

Parsers

Different parsers can be used to convert the syslog message fields into OpenNMS Meridian event fields.

Parser	Description
org.opennms.netmgt.syslogd.CustomSy slogParser	Parser that uses a regex statement to parse the syslog header.
org.opennms.netmgt.syslogd.RadixTre eSyslogParser	Parser that uses an internal list of <i>grok</i> -style statements to parse the syslog header.
org.opennms.netmgt.syslogd.SyslogNG Parser	Parser that strictly parses messages in the default pattern of syslog-ng.
org.opennms.netmgt.syslogd.Rfc5424S yslogParser	Parser that strictly parses the RFC 5424 format for syslog messages.

RadixTreeSyslogParser

The RadixTreeSyslogParser normally uses a set of internally-defined patterns to parse multiple syslog message formats. If you wish to customize the set of patterns, you can put a new set of patterns into a syslog-grok-patterns.txt in the etc directory for OpenNMS Meridian.

The patterns are defined in *grok*-style statements where each token is defined by a **%{PATTERN:semantic**} clause. Whitespace in the pattern will match 0...n whitespace characters and character literals in the pattern will match the corresponding characters. The '%' character literal must be escaped by using a backslash, ie. '\%'.

i

The RadixTreeSyslogParser's *grok* implementation only supports a limited number of pattern types. However, these patterns should be sufficient to parse any syslog message format.

The patterns should be arranged in the file from most specific to least specific since the first pattern to successfully match the syslog message will be used to construct the OpenNMS Meridian event.

Pattern	Description
HOSTNAME	String containing only valid hostname characters (alphanumeric plus '.', '-' and '_').
`HOSTNAMEO RIP	String containing only valid hostname characters or IP address characters (IPv4 or IPv6).
INT	Positive integer.
`IPADDRESS	String containing only valid IP address characters (IPv4 or IPv6).
MONTH	3-character English month abbreviation.
NOSPACE	String that contains no whitespace.

Pattern	Description
STRING	String. Because this matches any character, it must be followed by a delimiter in the pattern string.
WHITESPACE	String that contains only whitespace (spaces and or tabs).

Semantic Token	Description
day	2-digit day of month (1-31).
facilityPrior ity	Facility-priority integer.
hostname	String hostname (unqualified or FQDN), IPv4 address, or IPv6 address.
hour	2-digit hour of day (0-23).
message	Remaining string message.
messageId	String message ID.
minute	2-digit minute (0-59).
month	2-digit month (1-12).
parm*	String generic parameter where the parameter's key is the identifier following "parm" in the semantic token (e.x. parmComponentId maps to a string parameter with key "ComponentId").
processId	String process ID.
processName	String process name.
second	2-digit second (0-59).
secondFractio n	1- to 6-digit fractional second value as a string.
timezone	String timezone value.
version	Version.
year	4-digit year.

8.2.3. ReST

Posting an event in XML format to the appropriate endpoint in the OpenNMS Meridian ReST API will cause the creation of a corresponding event, just as with the XML-TCP interface.

8.2.4. XML-TCP

Any application or script can create custom events in OpenNMS Meridian by sending properly-formatted XML data over a TCP socket.

8.2.5. Receiving IBM Tivoli Event Integration Facility Events

OpenNMS can be configured to receive *Events* sent using the <u>Tivoli Event Integration Facility</u>. These EIF events are translated into OpenNMS events using preconfigured rules. The resulting UEI are anchored in the <u>uei.opennms.org/vendor/IBM/EIF/</u> namespace, with the name of the EIF event class appended.

A sample event configuration for the OMEGAMON_BASE class is included with OpenNMS.

Configuring the EIF Adapter

Once *OpenNMS* is started and the *Karaf* shell is accessible, you can install the *EIF Adapter* feature and configure it to listen on a specific interface and port.

•

By default the EIF Adapter is configured to listen on TCP port 1828 on all interfaces.

OSGi login, installation, and configuration of the EIF Adapter

```
[root@localhost /root]# $ ssh -p 8101 admin@localhost
...
opennms> feature:install eif-adapter
opennms> config:edit org.opennms.features.eifadapter
opennms> config:property-set interface 0.0.0.0
opennms> config:property-set port 1828
opennms> config:update
```

You can check the routes status with the camel:* commands and/or inspect the log with log:tail for any obvious errors. The feature has a debug level logging that can be used to debug operations.

Documentation on using the *OSGi* console embedded in *OpenNMS* and the related camel commands.

Features installed through the Karaf shell persist only as long as the \${OPENNMS_HOME}/data directory remains intact. To enable the feature more permanently, add it to the featuresBoot list in \${OPENNMS_HOME}/etc/org.apache.karaf.features.cfg.

You should now be able to configure your EIF forwarders to send to this destination, and their events will be translated into OpenNMS Events and written to the *event bus*.

Troubleshooting

i

1

If events are not reaching *OpenNMS*, check whether the event source (*EIF Forwarder*) is correctly configured. Check your event destination configuration. In particular review the HOSTNAME and PORT parameters. Also check that your situations are configured to forward to that EIF destination.

If those appear to be correct verify that the *EIF Forwarder* can communicate with *OpenNMS* over the configured port (default 1828).

Review the OSGi log with log:tail or the camel:* commands.

8.2.6. TL1 Autonomous Messages

Autonomous messages can be retrieved from certain TL1-enabled equipment and transformed into events.



The Tl1d service daemon, which enables OpenNMS Meridian to receive TL1 autonomous messages, must be enabled for this functionality to work. This service daemon is **disabled** by default. :imagesdir: ../../../images

8.2.7. Sink

Events can also be created by routing them to a specific topic on *Kafka / ActiveMQ*.

The topic name should be of the form OpenNMS.Sink.Events where OpenNMS is default instance id of OpenNMS Meridian. The instance id is configurable through a system property org.opennms.instance.id.

8.3. The Event Bus

At the heart of OpenNMS Meridian lies an **event bus**. Any OpenNMS Meridian component can *publish* events to the bus, and any component can *subscribe* to receive events of interest that have been published on the bus. This publish-subscribe model enables components to use events as a mechanism to send messages to each other. For example, the provisioning subsystem of OpenNMS Meridian publishes a *node-added* event whenever a new node is added to the system. Other subsystems with an interest in new nodes subscribe to the *node-added* event and automatically receive these events, so they know to start monitoring and managing the new node if their configuration dictates. The publisher and subscriber components do not need to have any knowledge of each other, allowing for a clean division of labor and lessening the programming burden to add entirely new OpenNMS Meridian subsystems or modify the behavior of existing ones.

8.3.1. Associate an Event to a given node

There are 2 ways to associate an existing node to a given event prior sending it to the Event Bus:

- Set the **nodeId** of the node in question to the event.
- For requisitioned nodes, set the **_foreignSource** and **_foreignId** as parameters to the event. Then, any incoming event without a **nodeId** and these 2 parameters will trigger a lookup on the DB; if a node is found, the **nodeId** attribute will be dynamically set into the event, regardless which method has been used to send it to the **Event Bus**. :imagesdir: ../../images

8.4. Event Configuration

The back-end configuration surrounding events is broken into two areas: the configuration of **Eventd** itself, and the configuration of all types of events known to OpenNMS Meridian.

8.4.1. The eventd-configuration.xml file

The overall behavior of Eventd is configured in the file OPENNMS_HOME/etc/eventd-configuration.xml. This file does not need to be changed in most installations. The configurable items include:

TCPAddress

The IP address to which the Eventd XML/TCP listener will bind. Defaults to 127.0.0.1.

TCPPort

The TCP port number on TCPAddress to which the Eventd XML/TCP listener will bind. Defaults to 5817.

UDPAddress

The IP address to which the Eventd XML/UDP listener will bind. Defaults to 127.0.0.1.

UDPPort

The UDP port number on TCPAddress to which the Eventd XML/UDP listener will bind. Defaults to 5817.

receivers

The number of threads allocated to service the event intake work done by Eventd.

queueLength

The maximum number of events that may be queued for processing. Additional events will be dropped. Defaults to unlimited.

getNextEventID

An SQL query statement used to retrieve the ID of the next new event. Changing this setting is not recommended.

socketSoTimeoutRequired

Whether to set a timeout value on the **Eventd** receiver socket.

socketSoTimeoutPeriod

The socket timeout, in milliseconds, to set if socketSoTimeoutRequired is set to yes.

logEventSummaries

Whether to log a simple (terse) summary of every event at level INFO. Useful when troubleshooting event processing on busy systems where DEBUG logging is not practical.

8.4.2. The eventconf.xml file and its tributaries

The set of known events is configured in OPENNMS_HOME/etc/eventconf.xml. This file opens with a <global> element, whose <security> child element defines which event fields may not be overridden in the body of an event submitted via any Eventd listener. This mechanism stops a mailicious actor from, for instance, sending an event whose operator-action field amounts to a phishing attack.

After the <global> element, this file consists of a series of <event-file> elements. The content of

each <event-file> element specifies the path of a **tributary file** whose contents will be read and incorporated into the event configuration. These paths are resolved relative to the OPENNMS_HOME/etc directory; absolute paths are not allowed.

Each **tributary file** contains a top-level <<u>events</u>> element with one or more <<u>event</u>> child elements. Consider the following event definition:

```
<event>
     <uei>uei.opennms.org/nodes/nodeLostService</uei>
     <event-label>OpenNMS-defined node event: nodeLostService</event-label>
     <descr>&lt;p>A %service% outage was identified on interface
            %interface% because of the following condition: %parm[eventReason]%.8lt;
/p> <p>
            A new Outage record has been created and service level
            availability calculations will be impacted until this outage is
            resolved.</p></descr>
     <logmsg dest="logndisplay">
            %service% outage identified on interface %interface%.
       </logmsg>
     <severity>Minor</severity>
     <alarm-data reduction-key="%uei%:%dpname%:%nodeid%:%interface%:%service%" alarm-
type="1" auto-clean="false"/>
  </event>
```

Every event definition has this same basic structure. See Anatomy of an Event for a discussion of the structural elements.

A word about severities

When setting severities of events, it's important to consider each event in the context of your infrastructure as a whole. Events whose severity is critical at the zoomed-in level of a single device may not merit a Critical severity in the zoomed-out view of your entire enterprise. Since an event with Critical severity can never have its alarms escalated, this severity level should usually be reserved for events that unequivocally indicate a truly critical impact to the business. Rock legend Nigel Tufnel offered some wisdom on the subject.

Replacement tokens

Various tokens can be included in the description, log message, operator instruction and automatic actions for each event. These tokens will be replaced by values from the current event when the text for the event is constructed. Not all events will have values for all tokens, and some refer specifically to information available only in events derived from SNMP traps.

%eventid%

The event's numeric database ID

%uei%

The Universal Event Identifier for the event.

%source%

The source of the event (which OpenNMS Meridian service daemon created it).

%descr%

The event description.

%logmsg%

The event logmsg.

%time%

The time of the event.

%shorttime%

The time of the event formatted using DateFormat.SHORT for a completely numeric date/time.

%dpname%

The ID of the Minion (formerly distributed poller) that the event was received on.

%nodeid%

The numeric node ID of the device that caused the event, if any.

%nodelabel%

The node label for the node given in **%nodeid%** if available.

%nodelocation%

The node location for the node given in **%nodeid%** if available.

%host%

The host at which the event was generated.

%interface%

The IP interface associated with the event, if any.

%foreignsource%

The Requisition name for the node given in **%nodeid** if available.

%foreignid%

The Requisition ID for the node given in **%nodeid** if available.

%ifindex%

The interface's SNMP ifIndex.

%interfaceresolv%

Does a reverse lookup on the *interface* and returns its name if available.

%service%

The service associated with the event, if any.

%severity%

The severity of the event.

%snmphost%

The host of the SNMP agent that generated the event.

%id%

The SNMP Enterprise OID for the event.

%idtext%

The decoded (human-readable) SNMP Enterprise OID for the event (?).

%ifalias%

The interface's SNMP ifAlias.

%generic%

The Generic trap-type number for the event.

%specific%

The Specific trap-type number for the event.

%community%

The community string for the trap.

%version%

The SNMP version of the trap.

%snmp%

The SNMP information associated with the event.

%operinstruct%

The operator instructions for the event.

%mouseovertext%

The mouse over text for the event.

%tticketid%

The trouble ticket id associated with the event if available.

%primaryinterface%

The primary interface IP address for the node given in **%nodeid%** if available.



The use of multiple *Minions* in one location can break the alarm life-cycle for a some *OpenNMS* features. To avoid this problem, the %dpname% value can always be replaced by an empty string by setting org.opennms.netmgt.eventd.cleardpname to true in the file opennms.properties.

Asset tokens

A node may have additional asset records stored for it. You can access these records using the asset replacement token, which takes the form:

%asset[<token>]%

The asset field <token>'s value, or "Unknown" if it does not exist.

Hardware tokens

A node may have additional hardware details stored for it. You can access these details using the hardware replacement token, which takes the form:

%hardware[<token>]%

The hardware field <token>'s value.

Parameter tokens

Many events carry additional information in **parameters** (see Anatomy of an Event). These parameters may start life as SNMP trap **variable bindings**, or **varbinds** for short. You can access event parameters using the parm replacement token, which takes several forms:

%parm[all]%

Space-separated list of all parameter values in the form parmName1="parmValue1"parmName2="parmValue2" and so on.

%parm[values-all]%

Space-separated list of all parameter values (without their names) associated with the event.

%parm[names-all]%

Space-separated list of all parameter names (without their values) associated with the event.

%parm[<name>]%

Will return the value of the parameter named <name> if it exists.

%parm[##]%

Will return the total number of parameters as an integer.

%parm[#<num>]%

Will return the value of parameter number <num> (one-indexed).

%parm[name-#<num>]%

Will return the name of parameter number <num> (one-indexed).

The structure of the eventconf.xml tributary files

The ordering of event definitions is very important, as an incoming event is matched against them in order. It is possible and often useful to have several event definitions which could match variant forms of a given event, for example based on the values of SNMP trap variable bindings.

The tributary files included via the <event-file> tag have been broken up by vendor. When OpenNMS Meridian starts, each tributary file is loaded in order. The ordering of events inside each tributary file is also preserved.

The tributary files listed at the very end of eventconf.xml contain catch-all event definitions. When slotting your own event definitions, take care not to place them below these catch-all files; otherwise your definitions will be effectively unreachable.

A few tips

- To save memory and shorten startup times, you may wish to remove event definition files that you know you do not need.
- If you need to customize some events in one of the default tributary files, you may wish to make a copy of the file containing only the customized events, and slot the copy above the original; this practice will make it easier to maintain your customizations in case the default file changes in a future release of OpenNMS Meridian.

8.4.3. Reloading the event configuration

After making manual changes to OPENNMS_HOME/etc/eventconf.xml or any of its tributary files, you can trigger a reload of the event configuration by issuing the following command on the OpenNMS Meridian server:

```
OPENNMS_HOME/bin/send-event.pl uei.opennms.org/internal/reloadDaemonConfig -p
'daemonName Eventd'
```

8.5. Debugging

When debugging events, it may be helpful to lower the minimum severity at which Eventd will log from the default level of WARN. To change this setting, edit OPENNMS_HOME/etc/log4j2.xml and locate the following line:

<KeyValuePair key="eventd"

value="WARN" />

Changes to log42.xml will be take effect within 60 seconds with no extra action needed. At level DEBUG, Eventd will log a verbose description of every event it handles to OPENNMS_HOME/logs/eventd.log. On busy systems, this setting may create so much noise as to be impractical. In these cases, you can get terse event summaries by setting Eventd to log at level INFO and setting logEventSummaries="yes" in OPENNMS_HOME/etc/eventd-configuration.xml. Note that changes to eventd-configuration.xml require a full restart of OpenNMS Meridian.

8.5.1. Karaf Shell

The opennms:show-event-config command can be used to render the event definition for one or more event UEIs (matching a substring) to *XML*. This command is useful for displaying event definitions which may not be easily accessible on disk, or verifying that particular events were actually loaded.

\$ ssh -p 8101 admin@localhost

...
admin@opennms()> opennms:show-event-config -u uei.opennms.org/alarms

Chapter 9. Alarms

OpenNMS Meridian has the ability to monitor the state of problems with its managed entities (ME), their resources, the services they provide, as well as the applications they host; or more simply, *the Network*. In *OpenNMS Meridian*, the state of these problems are characterized as *Alarms*.

In the beginning, there were Events

Before Alarmd was created, OpenNMS' Events (or messages) were used not only as interprocess communication messages (IPC), but also as indications of problems in *the network*. Even today, OpenNMS Events still carry problem state attributes such as: Acknowledgement and Severity. However, these attributes have long since been functionally deprecated now that Alarms are used as *the* indicator for problems in the network, (see also Situations and Business Services).



A significant change occurred with the release of Horizon 23.0.0 (H23). Prior to H23 and since the introduction of Alarms in OpenNMS, Alarmd was designed and configured to track the state of a problem using two Alarms; a *Down* and an *Up* Alarm. Now, OpenNMS is designed with the intention to use a single Alarm to track the state of a problem. The old behavior can be re-enabled by setting the system property org.opennms.alarmd.legacyAlarmState = true.

9.1. Single Alarm Tracking Problem States

First occurrence of a Service Down problem (SNMP), Alarm instantiated

Results 1-1 of	Results 1-1 of 1									
Ack TID Se	everity	Node	Count	Last	Log Msg					
69	Minor 🕀 🗆	p-brane	1	2018-08-03T15:15:07-04:00 🕢 🗈	SNMP outage identified on interface 127.0.0.1.					

The Service Down Event from the Poller (via clicking on Alarm count)

▼ ID	Severity	Time	Source Location	System-ID	Node	Node Location	Interface	Service	Alarm ID	
2280	Minor 🕀 🗆	2018-08-03T15:15:07-04:00 ()	Default 🕀 🗆	0000000-0000-0000-0000-000000000000000	p-brane 🕀 🕀	Default 🕀 🕀	127.0.0.1 🕀 🖂	SNMP ⊞ ⊟	69	
		uel.opennms.org/nodes/nodeLostService 🗄 🖯 Edit notifications for event								
		SNMP outage identified on interfac	e 127.0.0.1.							

Alarm is cleared immediately (no longer creating separate Alarm for Normal state)

Res	Results 1-1 of 1								
Acl	Ack TID Severity		Node	C	Count Last	Log Msg			
	69	Cleared 🕀 🕀	p-brane	1	2018-08-03T15:16:22-04:00 🕢 🕨	The SNMP outage on interface 127.0.0.1 has been cleared. Service is restored.			

Both Service Down and Service restored Events from the Poller

▼ ID	Severity	Time	Source Location	System-ID	Node	Node Location	Interface	Service	Alarm ID		
2295	Normal 🕀 🕀	2018-08-03T15:16:22-04:00 ① Default ⊕ 00000000-0000-0000-0000-00000000000 p-brane Default ⊕ 127.0.0.1 ⊕ 500000000000000000000000000000000000									
		uel.opennms.org/nodes/nodeRegainedService 🕀 🖯 Edit notifications for event									
		The SNMP outage on interface 127.0.0.1 has been cleared. Service is restored.									
2280	Minor 🕀 🗆	2018-08-03T15:15:07-04:00 I	Default 🕀 🗆	0000000-0000-0000-0000-0000000000000000	p-brane	Default 🕀 🗆	127.0.0.1 🕀 🖯	SNMP ⊞ ⊟	69		
		uel.opennms.org/nodes/nodeLostService 🗄 🖯 Edit notifications for event									
		SNMP outage identified on interfac	e 127.0.0.1.								

The Second occurence of the Service Down problem (SNMP), Alarm reduced

Hesuits 1-1 of 1									
Ack VID Severity Node	Count Last	Log Msg							
☐ 69 Minor ⊕ ⊖ p-brane	2 2018-08-03T15:17:07-04:00 I	SNMP outage identified on interface 127.0.0.1.							

Both Service Down Events and the previous Service restored Event from the Poller

▼ ID	Severity	Time	Source Location	System-ID	Node	Node Location	Interface	Service	Alarm ID			
2296	Minor 🕀 🗆	2018-08-03T15:17:07-04:00 ()	Default 🕀 🗆	0000000-0000-0000-0000-00000000000000	p-brane	Default 🕀 🗆	127.0.0.1 🕀 🖂	SNMP 🕀 🕀	69			
		uel.opennms.org/nodes/nodeLostService 🕀 🗅 Edit notifications for event										
		SNMP outage identified on interfac	e 127.0.0.1.									
2295	Normal 🕀 🕀	2018-08-03T15:16:22-04:00 ()	Default 🕀 🗆	0000000-0000-0000-0000-000000000000000	p-brane	Default 🕀 🖂	127.0.0.1 🕀 🖂	SNMP 🕀 🕀	69			
		uei.opennms.org/nodes/nodeRega	inedService 🕀 🖂 Ec	lit notifications for event								
		The SNMP outage on interface 127.0.0.1 has been cleared. Service is restored.										
2280	Minor 🕀 🗆	2018-08-03T15:15:07-04:00 ()	Default 🕀 🗆	0000000-0000-0000-0000-000000000000000	p-brane	Default 🕀 🗆	127.0.0.1 🕀 🖂	SNMP 🕀 🕀	69			
		uei.opennms.org/nodes/nodeLost	Service 🕀 🗆 Edit not	lifications for event								
		SNMP outage identified on interfac	e 127.0.0.1.									

The Alarm is again cleared immediately (notice counter doesn't increment)

Results 1-	Results 1-1 of 1								
Ack VID Severity Node		Node	Count Last	Log Msg					
69	Cleared 🕀 🕀	p-brane	2 2018-08-03T15:17:54-04:00 G D	The SNMP outage on interface 127.0.0.1 has been cleared. Service is restored.					

Both Service Down and restored Events

▼ ID	Severity	Time	Source Location	System-ID	Node	Node Location	Interface	Service	Alarm ID		
2297	Normal 🕀 🗆	2018-08-03T15:17:54-04:00 ()	Default 🕀 🖯	00000000-0000-0000-0000-00000000000000	p-brane	Default 🕀 🖯	127.0.0.1 🕀 🖂	SNMP ⊞ ⊟	69		
		uei.opennms.org/nodes/nodeRega	ainedService 🕀 🕀 Ec	lit notifications for event							
		The SNMP outage on interface 12	7.0.0.1 has been cle	ared. Service is restored.							
2296	Minor 🕀 🖃	2018-08-03T15:17:07-04:00 ৰ 🕨	Default 🕀 🖯	0000000-0000-0000-0000-000000000000000	p-brane	Default 🕀 🖯	127.0.0.1 🕀 🖂	SNMP ⊞ ⊟	69		
		uei.opennms.org/nodes/nodeLost	Service 🕀 🗆 Edit not	tifications for event							
		SNMP outage identified on interface 127.0.0.1.									
2295	Normal 🕀 🖃	2018-08-03T15:16:22-04:00 < >	Default 🕀 🖯	0000000-0000-0000-0000-000000000000000	p-brane	Default 🕀 🕀	127.0.0.1 🕀 🖂	SNMP ⊞ ⊟	69		
		uel.opennms.org/nodes/nodeRegainedService 🕀 E tdit notifications for event									
		The SNMP outage on interface 127.0.0.1 has been cleared. Service is restored,									
2280	Minor 🕀 🗆	2018-08-03T15:15:07-04:00 ()	Default 🕀 🖂	0000000-0000-0000-0000-00000000000	p-brane	Default 🕀 🖯	127.0.0.1 🕀 🖂	SNMP ⊞ ⊟	69		
		uei.opennms.org/nodes/nodeLost	Service 🕀 🗆 Edit no	tifications for event							
		SNMP outage identified on interfac	ce 127.0.0.1.								

9.2. Alarm Service Daemon

Alarmd, the Alarm Service Daemon, has the very simple task of processing Events representing problems in the Network. It either instantiates a new alarm for tracking a problem's state or reducing a reoccurring Event of an existing problem into the same Alarm. (*Also known as Alarm de-duplication*)

Prior to OpenNMS Horizon version 23.0.0 (H23), Alarmd had no configuration. With the release of H23, Drools is now imbedded directly inline with Alarmd's Event processing function. This provides users with a more robust infrastructure for the effective management of workflow and problem states in the Network. Business rules now replace the function of the "Automations" that were previously defined in Vacuumd's configuration. You will find these new business rules in the etc/alarmd/drools-rules.d/ folder.

\$OPENNMS_ETC/.drools-rules.d/

alarmd.drl

9.3. Configuring Alarms

Since Alarmd instantiates Alarms from Events, defining Alarms in *OpenNMS Meridian* entails defining an additional XML element of an Event indicating a problem or resolution in the Network. This additional element is the "alarm-data" element.



Any Event that is marked as "donotpersist" in the logmsg element's "dest" attribute, will not be processed as an Alarm.

```
<element name="alarm-data">
 <annotation>
    <documentation>This element is used for converting events into
alarms.</documentation>
 </annotation>
 <complexType>
    <sequence>
     <element ref="this:update-field" minOccurs="0" maxOccurs="unbounded" />
    </sequence>
    <attribute name="reduction-key" type="string" use="required" />
    <attribute name="alarm-type" use="required" >
     <simpleType>
       <restriction base="int">
          <minInclusive value="1"/>
        </restriction>
     </simpleType>
    </attribute>
    <attribute name="clear-key" type="string" use="optional" />
    <attribute name="auto-clean" type="boolean" use="optional" default="false" />
    <attribute name="x733-alarm-type" type="this:x733-alarm-type" use="optional" />
    <attribute name="x733-probable-cause" type="int" use="optional" />
 </complexType>
</element>
<element name="update-field">
 <complexType>
    <attribute name="field-name" type="string" use="required" />
    <attribute name="update-on-reduction" type="boolean" use="optional" default="true"
/>
    <attribute name="value-expression" type="string" use="optional" default="" />
 </complexType>
</element>
<simpleType name="x733-alarm-type">
 <restriction base="string" >
    <pattern value=
"CommunicationsAlarm|ProcessingErrorAlarm|EnvironmentalAlarm|QualityOfServiceAlarm|Equ
ipmentAlarm|IntegrityViolation|SecurityViolation|TimeDomainViolation|OperationalViolat
ion | Physical Violation" />
 </restriction>
</simpleType>
```

NOTE See also: Anatomy of an Event

The reduction-key

The critical attribute when defining the alarm-data of an Event, is the *reduction-key*. This attribute can contain literal strings as well as references to properties (fields and parameters) of the Event. The purpose of the reduction-key is to uniquely identify the signature of a problem and, as such, is

used to reduce (de-duplicate) Events so that only one problem is instantiated. Most commonly, the event's identifier (UEI) is used as the left most (least significant) portion of the reduction-key, followed by other properties of the Event from least to most significant and, traditionally, separated with the literal ':'.

Example 1. Multi-part reduction-key

Example 2. Least Significant reduction-key Attribute

Decreasing the significance of the reduction-key is a way to aggregate, for example, all nodes down in to a single alarm. However, there are caveats:

```
<event>
    <uei>uei.opennms.org/nodes/nodeDown</uei>
        <alarm-data reduction-key="%uei%" alarm-type="1"/>
</event>
```

With this reduction-key, a single alarm would be instantiated for all nodes that were determined by the Poller to be down. There would be a single alarm with the count representing the number of nodes down. However, the UEI uei.opennms.org/nodes/nodeUp would **not** be a good "pair wise" reduction-key for resolving this alarm as it would take only a single "node up" to clear all nodes down tracked with this single alarm configuration.

The alarm-type attribute

 \bigcirc

The second most critical attribute is the alarm-type. There are currently three types of alarms: problem (1), resolution (2), and notification (3). The alarm-type attribute helps Alarmd with pairwise resolution... the matching of resolution events to problem events.

The clear-key attribute

This attribute is used in the pair-wise correlation feature of Alarmd. When configuring a resolution Alarm, set this attribute to match the reduction-key of a the corresponding problem Alarm.

The auto-clean attribute

This attribute instructs Alarmd to only retain the most recent Event reduced into an alarm. For alarms that are super chatty, this is a way to reduce the size of the most recent Events in the database.



Do not use this feature with Alarms that have pair-wise correlation (matching problems with resolutions).

The update-field element

Use this element to override Alarmd's default behavior for which some fields are updated during reduction. The Alarm fields that are currently allowed to be controlled this way are: .Bulleted * distpoller * ipaddr * mouseover * operinstruct * severity * descr * acktime * ackuser



With the new single alarm behavior in H23, if an Alarm transitions from an alarm-type 2 back to alarm-type 1 the Severity will be set to the most Event's value.

Reduction (de-duplication) of Alarms

Alarmd is designed to reduce multiple occurrences of an Alarm into a single alarm.

Pairwise Correlation

Alarmd is also intrinsically designed to automatically match resolving events with an existing Alarm. Alarms with matching resolutions with problems (Ups with Downs), should be indicated with the alarm-type attribute. Bulleted * alarm-type="1" (problem alarm) * alarm-type="2" (resolving alarm) * alarm-type="3" (notification alarm... alarm with no resolution such as SNMP Authentication Failures)



Instantiate new Alarms for existing cleared problem

Also new in H23, a global property setting that controls behavior of alarm reduction of currently cleared Alarms.

Create a properties file called alarmd.properties in the \$OPENNMS_ETC/opennms.properties.d/ folder and add the following property set to true:

```
###### Alarmd Properties ######
#
#
# Enable this property to force Alarmd to create new alarms when an problem re-occurs
and the
# existing Alarm is in a "Cleared" state.
#
# Default: false
#org.opennms.alarmd.newIfClearedAlarmExists = false
org.opennms.alarmd.newIfClearedAlarmExists = true
```

Now, with this property set, when a repeat incident occurs and the current state of the Alarm tracking the problem is "Cleared", instead of restating the current Alarm to it's default severity and incrementing the counter, a new instance of the Alarm will be created. New node down Alarm with existing cleared Alarm

VVI					CAISting		cicuicu	maim
Resu	ts 1-2 (of 2						
Ack	▼ID \$	Severity	Node	Count	Last	Log Msg		
	164	Major 🕀 🗆	p-brane	1	2018-08-24T09:48:01-04:00 🛾 🕨	Node is down.		
	163	Cleared 🕀 🗆	p-brane	1	2018-08-24T09:47:47-04:00 🖪 🗈	Node is up.		

What happens is that Alarmd will alter the existing Alarm's reductionKey to be unique. Thus preventing it from ever again being reused for a reoccurring problem in the Network (the literal ":ID:" and the alarm ID is appended to the reductionKey).

Altered reductionKey

Alarm 163								
Severity	Cleared	Node	p-brane					
Last Event	2018-08-24T09:47:47-04:00	Interface						
First Event	2018-08-24T09:44:33-04:00	Service						
Event Source Location	Default	Node Location	Default					
Count	1	UEI	uei.opennms.org/nodes/nodeDown					
Ticket ID		Ticket State						
Reduction Key	uei.opennms.org/nodes/nodeDown::1:ID:163							
Log Message								



Re-enable legacy dual Alarm state behavior

Now in H23, a global property setting can set to re-enable the legacy dual Alarm behavior.

Create a properties file called alarmd.properties in the \$OPENNMS_ETC/opennms.properties.d/ folder and add the following property set to true:

```
###### Alarmd Properties ######
# Enable this property to have the traditional dual alarm handling of alarms state
# for Alarm pairwise correlation.
# Default: false
#org.opennms.alarmd.legacyAlarmState = false
org.opennms.alarmd.legacyAlarmState = true
```

8

Setting legacyAlarmState will nullify newIfClearedAlarmExists

9.4. Alarm Notes

OpenNMS Meridian creates an *Alarm* for issues in the network. Working with a few people in a team, it is helpful to share information about a current *Alarm. Alarm Notes* can be used to assign comments to a specific *Alarm* or a whole class of *Alarms.*. The figure Alarm Detail View shows the component to add these information in *Memos* to the *Alarm*.

Alarm Detail View

Home / Alarms / Alarm 1436							
Alarm 1436							
Severity	Minor		Node				
Last Event	Apr 28, 2016 1:52:14 PM		Interface	Interface			
First Event	Apr 25, 2016 10:25:53 PM		Service				
Count	4		UEI	uei.opennms.org/bsm/serviceProblem			
Ticket ID			Ticket State				
Reduction Key	uei.opennms.org/bsm/serviceProblem:145	i					
Log Message							
	affecting business service 'Shop'.						
Description							
There are currently one or	more problems affecting business service 'S	Shop'. args(2): businessServiceId="145	" businessServiceName="Shop	ס"			
Sticky Memo			Journal Memo				
I have to fix the load bala	ncer which provides the service. This message	ge is only for this specific alarm.		ervice has a problem. Please check the followin restart services. This text will appear on every in			
Save Delete			Save Delete				
Author:	Updated:	Created:	Author:	Updated:	Created:		
admin	Apr 29, 2016 3:53:41 PM	Apr 29, 2016 3:53:41 PM	admin	Apr 29, 2016 3:55:07 PM	Apr 29, 2016 3:55:07 PM		
Operator Instructions							
No instructions available.							

The Alarm Notes allows to add two types of notes on an existing Alarm or Alarm Class:

- *Sticky Memo*: A user defined note for a specific instance of an *Alarm*. Deleting the *Alarm* will also delete the sticky memo.
- *Journal Memo*: A user defined note for a whole class of alarms based on the resolved reduction key. The *Journal Memo* will be shown for all *Alarms* matching a specific reduction key. Deleting an *Alarm* doesn't remove the *Journal Memo*, they can be removed by pressing the "Clear" button on an *Alarm* with the existing *Journal Memo*.

If an *Alarm* has a sticky and/or a *Journal Memo* it is indicated with two icons on the "Alarm list Summary" and "Alarm List Detail".

9.5. Alarm Sounds

Often users want an audible indication of a change in alarm state. The *OpenNMS Meridian* alarm list page has the optional ability to generate a sound either on each new alarm or (more annoyingly) on each change to an alarm event count on the page.

The figure Alarm Sounds View shows the alarm list page when alarms sounds are enabled.

Alarm Sounds View

Home / Alarms / List							
View all ala	arms Advanced Search Lo	ng Listin	g Severity Legend	Sound on new alarm 🗸 50 🗸			
🟠 Uns	aved filter •						
Results 1-3 (Ack? v ID		Count	Last	Log Msg			
100	Minor 🖽 🖂	5	29-May-2017 22:43:50 🗉 🗈	Generic AlarmChangeNotifier Alarm Raise 1			
99	Warning ⊞ 🖂 2101-0601 ⊞ 🖂	1	29-May-2017 22:39:46 🛾 🗈	A10 trap received Description=			
98 🗸	Major ⊞ ⊟ 2101-0601 ⊞ ⊟	1	28-May-2017 08:02:28 @ D	A10 trap received Description=			
3 alarms	alarms Reset Select All Acknowledge Alarms V Go						
Results 1-3	of 3						
	OpenNMS Copyright @ 2002-2017 The OpenNMS Group, Inc. OpenNMS@ is a registered trademark of The OpenNMS Group, Inc.						

By default the alarm sound feature is disabled. System Administrators must activate the sound feature and also set the default sound setting for all users. However users can modify the default sound setting for the duration of their logged-in session using a drop down menu with the following options:

- Sound off: no sounds generated by the page.
- Sound on new alarm: sounds generated for every new alarm on the page.
- Sound on new alarm count: sounds generated for every increase in alarm event count for alarms on the page.

9.6. Flashing Unacknowledged Alarms

By default *OpenNMS Meridian* displays the alarm list page with acknowledged and unacknowledged alarms listed in separate search tabs. In a number of operational environments it is useful to see all of the alarms on the same page with unacknowledged alarms flashing to indicate that they haven't yet been noticed by one of the team. This allows everyone to see at a glance the real time status of all alarms and which alarms still need attention.

The figure Alarm Sounds View also shows the alarm list page when flashing unacknowledged alarms are enabled. Alarms which are unacknowledged flash steadily. Alarms which have been acknowledged do not flash and also have a small tick beside the selection check box. All alarms can be selected to be escalated, cleared, acknowledged and unacknowledged.

9.7. Configuring Alarm Sounds and Flashing

By default *OpenNMS Meridian* does not enable alarm sounds or flashing alarms. The default settings are included in opennms.properties. However rather than editing the default opennms.properties file, the system administrator should enable these features by creating a new file in opennms.properties.d and applying the following settings;

\${OPENNMS_HOME}/etc/opennms.properties.d/alarm.listpage.properties

```
# ###### Alarm List Page Options ######
# Several options are available to change the default behaviour of the Alarm List
Page.
# <opennms url>/opennms/alarm/list.htm
#
# The alarm list page has the ability to generate a sound either on each new alarm
# or (more annoyingly) on each change to an alarm event count on the page.
#
# Turn on the sound feature. Set true and Alarm List Pages can generate sounds in the
web browser.
opennms.alarmlist.sound.enable=true
#
# Set the default setting for how the Alarm List Pages generates sounds. The default
setting can be
# modified by users for the duration of their logged-in session using a drop down menu
#
    off = no sounds generated by the page.
#
    newalarm = sounds generated for every new alarm in the page
#
    newalarmcount = sounds generated for every increase in alarm event count for
alarms on the page
#
opennms.alarmlist.sound.status=off
# By default the alarm list page displays acknowledged and unacknowledged alarms in
separate search tabs
# Some users have asked to be able to see both on the same page. This option allows
the alarm list page
# to display acknowledged and unacknowledged alarms on the same list but
unacknowledged alarms
# flash until they are acknowledged.
#
opennms.alarmlist.unackflash=true
```

The sound played is determined by the contents of the following file \${OPENNMS_HOME}/jettywebapps/opennms/sounds/alert.wav

If you want to change the sound, create a new wav file with your desired sound, name it alert.wav and replace the default file in the same directory.

9.8. Alarm History

The *Alarm History* feature integrates with *Elasticsearch* to provide long term storage and maintain a history of alarm state changes.

When enabled, alarms are indexed in *Elasticsearch* when they are created, deleted, or when any of the "interesting" fields on the alarm are updated (more on this below.)

Alarms are indexed in such a fashion that allows operators to answer the following questions:

- 1. What were all the state changes of a particular alarm?
- 2. What was the last known state of an alarm at a given point in time?
- 3. Which alarms were present (i.e. not deleted) on the system at a given point in time?
- 4. Which alarms are currently present on the system?

A simple *REST* API is also made available for the purposes of evaluating the results, verifying the data that is stored and providing examples on how to query the data.

9.8.1. Requirements

This feature requires *Elasticsearch* 7.x.

9.8.2. Setup

Alarm history indexing can be enabled as follows:

First, login to the *Karaf* shell of your *OpenNMS Meridian* instance and configure the *Elasticsearch* client settings to point to your *Elasticsearch* cluster. See <u>Elasticsearch</u> Integration Configuration for a complete list of available options.

```
$ ssh -p 8101 admin@localhost
...
admin@opennms()> config:edit org.opennms.features.alarms.history.elastic
admin@opennms()> config:property-set elasticUrl http://es:9200
admin@opennms()> config:update
```

Next, install the opennms-alarm-history-elastic feature from that same shell using:

admin@opennms()> feature:install opennms-alarm-history-elastic

In order to ensure that the feature continues to be installed as subsequent restarts, add opennmsalarm-history-elastic to the featuresBoot property in the \${OPENNMS_HOME}/etc/org.apache.karaf.features.cfg.

9.8.3. Alarm indexing

When alarms are initially created, we push a document to *Elasticsearch* that includes all of the alarm fields as well as additional details on some of the related objects (i.e. the node.)

In order to avoid pushing a new document every time a new event is reduced on to an existing alarm, we only push a new document when (at least) one of these conditions are met:

- 1. We have not recently pushed a document for that alarm. (See alarmReindexDurationMs.)
- 2. The severity of the alarm has changed.
- 3. The alarm has been acknowledged or unacknowledged.

- 4. Either of the associated sticky or journal memos have changed.
- 5. The state of the associated ticket has changed.
- 6. The alarm has been associated with, or removed, from a situation.
- 7. A related alarm has been added or removed from the situation.



To change this behaviour and push a new document for **every** change, you can set **indexAllUpdates** to true.

When alarms are deleted, we push a new document that contains the alarm id, reduction key, and deletion time.

Field	Description
@first_event_tim e	Timestamp in milliseconds associated with the first event that triggered this alarm.
@first_event_tim e	Timestamp in milliseconds associated with the last event that triggered this alarm.
<pre>@update_time</pre>	Timestamp in milliseconds at which the document was created.
@deleted_time	Timestamp in milliseconds when the alarm was deleted.
id	Database ID associated with the alarm.
reduction_key	Key used to reduce events on to the alarm.
severity_label	Severity of the alarm.
severity_id	Numerical ID used to represent the severity.

The following table describes a subset of the fields in the alarm document:

9.8.4. Options

In addition to those mentioned in Elasticsearch Integration Configuration, the following properties can be set in $fOPENNMS_HOME/etc/org.opennms.features.alarms.history.elastic.cfg:$

Property	Description	Requi red	defaul t
indexAllUpdates	Index every alarm update, including simple event reductions.	option al	false
alarmReindexDur	Number of milliseconds to wait before re-indexing an alarm if nothing "interesting" has changed.	option	360000
ationMs		al	0
lookbackPeriodM	Number of milliseconds to go back when searching for alarms.	option	604800
s		al	000

Property	Description	Requi red	defaul t
batchIndexSize	Maximum number of records inserted in a single batch insert.	option al	200
bulkRetryCount	Number of retries until a bulk operation is considered failed.	option al	3
taskQueueCapaci ty	Maximum number of tasks to hold in memory.	option al	5000

Chapter 10. Notifications

10.1. Introduction

OpenNMS Meridian uses notifications to make users aware of an event. Common notification methods are email and paging, but notification mechanisms also exist for:

- Browser based desktop notifications
- Arbitrary HTTP GET and POST operations
- Arbitrary external commands
- Asterisk call origination
- IRCcat Internet Relay Chat bot
- SNMP Traps
- Slack, Mattermost, and other API-compatible team chat platforms
- Twitter, GNU Social, and other API-compatible microblog services
- User-provided scripts in any JSR-223 compatible language
- XMPP

The notification daemon *Notifd* creates and sends notifications according to configured rules when selected events occur in *OpenNMS Meridian*.

10.2. Getting Started

The status of notifications is indicated by an icon at the top right of the web UI's navigation bar. *OpenNMS Meridian* installs with notifications globally disabled by default.

10.2.1. Enabling Notifications

To enable notifications in *OpenNMS Meridian*, log in to the web UI as a user with administrator privileges. Hover over the user icon and click the *Configure OpenNMS* link. The controls for global notification status appear in the top-level configuration menu as *Notification Status*. Click the *On* radio button and then the *Update* button. Notifications are now globally enabled.

i

The web workflow above is functionally equivalent to editing the notifdconfiguration.xml file and setting status="on" in the top-level notifd-configuration element. This configuration file change is picked up on the fly with no need to restart or send an event.

10.2.2. Configuring Destination Paths

To configure notification destination paths in *OpenNMS Meridian*, navigate to *Configure OpenNMS* and, in the *Event Management* section, choose *Configure Notifications*. In the resulting dialog choose *Configure Destination Paths*.



The destination paths configuration is stored in the destinationPaths.xml file. Changes to this file are picked up on the fly with no need to restart or send an event.

10.2.3. Configuring Event Notifications

To configure notifications for individual events in *OpenNMS Meridian*, navigate to *Configure OpenNMS* and, in the *Event Management section*, *choose _Configure Notifications*. Then choose *Configure Event Notifications*.



i

The event notification configuration is stored in the notifications.xml file. Changes to this file are picked up on the fly with no need to restart or send an event.

The filter rule configured in notifications.xml, for ex: <rule>IPADDR != '0.0.0.0'</rule> is not strict by default. That means if there is any event that is not associated with any node/interface, it would not validate rule and by default notification would be saved. The rule can be changed to be strict i.e. <rule strict="true">IPADDR != '0.0.0.0'</rule> then the rule will always be evaluated and if there is no node/interface associated with event, notification wouldn't be saved.



By default, OpenNMS executes the destination path of all notifications matching the event's uei. You can configure OpenNMS to only execute the destination path of the first matching notification by editing the notifd-configuration.xml file and setting match-all="false" in the top-level notifd-configuration element. This configuration file change is picked up on the fly with no need to restart or send an event.

10.3. Concepts

Notifications are how *OpenNMS Meridian* informs users about an event that happened in the network, without the users having to log in and look at the UI. The core concepts required to understand notifications are:

- Events and UEIs
- Users, Groups, and On-Call Roles
- Duty Schedules
- Destination Paths
- Notification Commands

These concepts fit together to form an *Event Notification Definition*. Also related, but presently only loosely coupled to notifications, are *Alarms* and *Acknowledgments*.

10.3.1. Events and UEIs

As discussed in the chapter on Events, events are central to the operation of *OpenNMS Meridian*. Almost everything that happens in the system is the result of, or the cause of, one or more events; Every notification is triggered by exactly one event. A good understanding of events is therefore essential to a working knowledge of notifications.

Every event has a *UEI* (Uniform Event Identifier), a string uniquely identifying the event's type. UEIs are typically formatted in the style of a URI, but the only requirement is that they start with the string uei.. Most notifications are triggered by an exact UEI match (though they may also be triggered with partial UEI matches using regular expression syntax).

10.3.2. Users, Groups, and On-Call Roles

Users are entities with login accounts in the *OpenNMS Meridian* system. Ideally each user corresponds to a person. They are used to control access to the web UI, but also carry contact information (e-mail addresses, phone numbers, etc.) for the people they represent. A user may receive a notification either individually or as part of a *Group* or *On-Call Role*. Each user has several technology-specific contact fields, which must be filled if the user is to receive notifications by the associated method.

Groups are lists of users. In large systems with many users it is helpful to organize them into *Groups*. A group may receive a notification, which is often a more convenient way to operate than on individual user. *Groups* allow to assign a set of users to *On Call Roles* to build more complex notification workflows.

How to create or modify membership of Users in a Group

- 1. Login as a **User** with administrative permissions
- 2. Choose **Configure OpenNMS** from the user specific main navigation which is named as your login user name
- 3. Choose Configure Users, Groups and On-Call roles and select Configure Groups
- 4. Create a new **Group** with **Add new group** or modify an existing **Group** by clicking the **Modify** icon next to the **Group**
- 5. Select **User** from **Available Users** and use the >> to add them to the **Currently in Group** or select the users in the **Currently in Group** list and use << to remove them from the list.
- 6. Click **Finish** to persist and apply the changes



The order of the *Users* in the group is relevant and is used as the order for *Notifications* when this group is used as *Target* in a *Destination Path*.

How to delete a Group

- 1. Login as a **User** with administrative permissions
- 2. Choose **Configure OpenNMS** from the user specific main navigation which is named as your login user name
- 3. Choose Configure Users, Groups and On-Call roles and select Configure Groups

- 4. Use the trash bin icon next to the *Group* to delete
- 5. Confirm delete request with **OK**

On-Call Roles are an overlay on top of groups, designed to enable *OpenNMS Meridian* to target the appropriate user or users according to a calendar configuration. A common use case is to have System Engineers in *On-Call* rotations with a given schedule. The *On-Call Roles* allow to assign a predefined *Duty Schedule* to an existing *Group* with *Users*. For each *On-Call Role* a *User* is assigned as a *Supervisor* to be responsible for the group of people in this *On-Call Role*.

How to assign a Group to an On-Call Role

- 1. Login as a **User** with administrative permissions
- 2. Choose **Configure OpenNMS** from the user specific main navigation which is named as your login user name
- 3. Choose Configure Users, Groups and On-Call roles and select Configure On-Call Roles
- 4. Use **Add New On-Call Role** and set a **Name** for this *On-Call Role*, assign an existing **Group** and give a meaningful description
- 5. Click **Save** to persist
- 6. Define a *Duty Schedule* in the calendar for the given date by click on the **Plus (+)** icon of the day and provide a notification time for a specific *User* from the associated *Group*
- 7. Click **Save** to persist the *Schedule*
- 8. Click **Done** to apply the changes

10.3.3. Duty Schedules

Every *User* and *Group* may have a *Duty Schedule*, which specifies that user's (or group's) weekly schedule for receiving notifications. If a notification should be delivered to an individual user, but that user is not on duty at the time, the notification will never be delivered to that user. In the case of notifications targeting a user via a group, the logic differs slightly. If the group is on duty at the time the notification is created, then all users who are also on duty will be notified. If the group is on duty, but no member user is currently on duty, then the notification will be queued and sent to the next user who comes on duty. If the group is off duty at the time the notification is created, then

10.3.4. Destination Paths

A *Destination Path* is a named, reusable set of rules for sending notifications. Every destination path has an initial step and zero or more escalation steps.

Each step in a destination path has an associated delay which defaults to zero seconds. The initial step's delay is called the *initial delay*, while an escalation step's delay is simply called its *delay*.

Each step has one or more *targets*. A target may be a user, a group, an on-call role, or a one-off e-mail address.



While it may be tempting to use one-off e-mail addresses any time an individual user is to be targeted, it's a good idea to reserve one-off e-mail addresses for special cases. If a user changes her e-mail address, for instance, you'll need to update in every destination path where it appears. The use of one-off e-mail addresses is meant for situations where a vendor or other external entity is assisting with troubleshooting in the short term.

When a step targets one or more groups, a delay may also be specified for each group. The default is zero seconds, in which case all group members are notified simultaneously. If a longer delay is set, the group members will be notified in alphabetical order of their usernames.



Avoid using the same name for a group and a user. The destination path configuration does not distinguish between users and groups at the step level, so the behavior is undefined if you have both a user and a group named admin. It is for this reason that the default administrators group is called Admin (with a capital A) — case matters.

Within a step, each target is associated with one or more notification commands. If multiple commands are selected, they will execute simultaneously.

Each step also has an *auto-notify* switch, which may be set to off, on, or auto. This switch specifies the logic used when deciding whether or not to send a notice for an auto-acknowledged notification to a target that was not on duty at the time the notification was first created. If off, notices will never be sent to such a target; if on, they will always be sent; if auto, the system employs heuristics aimed at "doing the right thing".

10.3.5. Notification Commands

A *Notification Command* is a named, reusable execution profile for a Java class or external program command used to convey notices to targets. The following notification commands are included in the default configuration:

callHomePhone, callMobilePhone, *and* callWorkPhone

Ring one of the phone numbers configured in the user's contact information. All three are implemented using the in-process Asterisk notification strategy, and differ only in which contact field is used.

ircCat

Conveys a notice to an instance of the *IRCcat* Internet Relay Chat bot. Implemented by the inprocess IRCcat notification strategy.

javaEmail *and* javaPagerEmail

By far the most commonly used commands, these deliver a notice to a user's email or pagerEmail contact field value. By configuring a user's pagerEmail contact field value to target an email-to-SMS gateway, SMS notifications are trivially easy to configure. Both are implemented using the in-process JavaMail notification strategy.

microblogDM, microblogReply, *and* microblogUpdate

Sends a notice to a user as a direct message, at a user via an at-reply, or to everybody as an update via a microblog service with a Twitter v1-compatible API. Each command is implemented with a separate, in-process notification strategy.

numericPage *and* textPage

Sends a notice to a user's numeric or alphanumeric pager. Implemented as an external command using the **qpage** utility.

xmppGroupMessage and xmppMessage

Sends a message to an XMPP group or user. Implemented with the in-process XMPP notification strategy.

Notification commands are customizable and extensible by editing the notificationCommands.xml file.



Use external binary notification commands sparingly to avoid fork-bombing your *OpenNMS Meridian* system. Originally, all notification commands were external. Today only the numericPage and textPage commands use external programs to do their work.

10.4. Bonus Notification Methods

A handful of newer notification methods are included in *OpenNMS Meridian* but currently require manual steps to activate.

10.4.1. Mattermost

If your organization uses the Mattermost team communications platform, you can configure *OpenNMS Meridian* to send notices to any Mattermost channel via an incoming webhook. You must configure an incoming webhook in your Mattermost team and do a bit of manual configuration to your *OpenNMS Meridian* instance.

First, add the following bit of XML to the notificationCommands.xml configuration file (no customization should be needed):

```
<command binary="false">
  <name>mattermost</name>
  <execute>org.opennms.netmgt.notifd.MattermostNotificationStrategy</execute>
  <comment>class for sending messages to a Mattermost team channel for
notifications</comment>
  <argument streamed="false">
    <switch>-subject</switch>
    </argument streamed="false">
    <switch>-subject</switch>
    </argument streamed="false">
    <switch>-tm</switch>
    </argument>
    </argument>
    </argument>
    </argument>
    </argument>
    </argument>
    <//argument>
    <//arg
```

Then create a new file called mattermost.properties in the opennms.properties.d directory with the following contents (customizing values as appropriate):

org.opennms.netmgt.notifd.mattermost.webhookURL=https://mattermost.example.com/hooks/b
f980352b5f7232efe721dbf0626bee1

Restart OpenNMS so that the mattermost.properties file will be loaded. Your new mattermost notification command is now available for use in a destination path.

Additional Options

The following table lists optional properties that you may use in mattermost.properties to customize your Mattermost notifications.

To improve the layout, the property names have been shortened to their final component; you must prepend org.opennms.netmgt.notifd.mattermost. when using them.

Parame ter	Description	Requ ired	Default value	Example
channel	Specify a channel or private group other than the one targeted by the webhook	optio nal	Webhook default	NetOps
username	The username to associate with the notification posts	optio nal	None	OpenNMS_Bot
iconEmoj i	An emoji sequence to use as the icon for the notification posts	optio nal	No icon	:metal:
iconURL	The URL of an image to use as the icon for the notification posts	optio nal	No icon	https://example.or g/assets/icon.png

Parame ter	Description	Requ ired	Default value	Example
D	Should the system wide proxy settings be used? The system proxy settings can be configured via system properties	optio nal	true	true



Some of the optional configuration parameters are incompatible with some versions of Mattermost. For instance, the channel option is known not to work with Mattermost 3.7.0.

For more information on incoming webhooks in Mattermost, see Mattermost Integration Guide.

10.4.2. Slack Notifications

If your organization uses the Slack team communications platform, you can configure *OpenNMS Meridian* to send notices to any Slack channel via an incoming webhook. You must configure an incoming webhook in your Slack team and do a bit of manual configuration to your *OpenNMS Meridian* instance.

First, add the following bit of XML to the notificationCommands.xml configuration file (no customization should be needed):

```
<command binary="false">
  <name>slack</name>
  <execute>org.opennms.netmgt.notifd.SlackNotificationStrategy</execute>
  <comment>class for sending messages to a Slack team channel for
notifications</comment>
  <argument streamed="false">
    <switch>-subject</switch>
    </argument>
    <argument streamed="false">
    <switch>-subject</switch>
    </argument>
    <switch>-tm</switch>
    </argument>
    </argument>
    </argument>
    </argument>
    </argument>
    </argument>
    </argument>
    <//argument>
    </argument>
    <//argument>
    <//argum
```

Then create a new file called slack.properties in the opennms.properties.d directory with the following contents (customizing values as appropriate):

org.opennms.netmgt.notifd.slack.webhookURL=https://hooks.slack.com/services/AEJ7IIYAI/ X00TH3EOD/c3fc4a662c8e07fe072aeeec

Restart OpenNMS so that the slack.properties file will be loaded. Your new slack notification command is now available for use in a destination path.

Additional Options

The following table lists optional properties that you may use in *slack.properties* to customize your Slack notifications.



To improve the layout, the property names have been shortened to their final component; you must prepend org.opennms.netmgt.notifd.slack. when using them.

Table 00 Additional	a an area at area	fortha	Clast not	figation stratem.
Table 98. Additional	parameters	jor ine	Slack noll	lication strategy

Parame ter	Description	Requ ired	Default value	Example
channel	Specify a channel or private group other than the one targeted by the webhook	optio nal	Webhook default	NetOps
username	The username to associate with the notification posts	optio nal	None	OpenNMS_Bot
iconEmoj i	An emoji sequence to use as the icon for the notification posts	optio nal	No icon	:metal:
iconURL	The URL of an image to use as the icon for the notification posts	optio nal	No icon	https://example.or g/assets/icon.png
useSyste mProxy	Should the system wide proxy settings be used? The system proxy settings can be configured via system properties	optio nal	true	true

For more information on incoming webhooks in Slack, see Slack API.

Chapter 11. Provisioning

11.1. Introduction

The introduction of OpenNMS version 1.8 empowers enterprises and services providers like never before with a new service daemon for maintaining the managed entity inventory in OpenNMS. This new daemon, *Provisiond*, unifies all previous entity control mechanisms available in 1.6 (*Capsd* and the *Importer*), into a new and improved, massively parallel, policy based provisioning system. System integrators should note, *Provisiond* comes complete with a *RESTFul Web Service API* for easy integration with external systems such as CRM or external inventory systems as well as an adapter API for interfacing with other management systems such as configuration management.

OpenNMS 1.0, introduced almost a decade ago now, provided a capabilities scanning daemon, Capsd, as the mechanism for provisioning managed entities. *Capsd*, deprecated with the release of 1.8.0, provided a rich automatic provisioning mechanism that simply required an IP address to seed its algorithm for creating and maintaining the managed entities (nodes, interfaces, and IP based services). Version 1.2 added and *XML-RPC API* as a more controlled (directed) strategy for provisioning services that was mainly used by non telco based service providers (i.e. managed hosting companies). Version 1.6 followed this up with yet another and more advanced mechanism called the *Importer service daemon*. The *Importer* provided large service providers with the ability to strictly control the OpenNMS entity provisioning with an XML based API for completely defining and controlling the entities where no discovery and service scanning scanning was feasible.

The Importer service improved OpenNMS' scalability for maintaining managed entity databases by an order of magnitude. This daemon, while very simple in concept and yet extremely powerful and flexible provisioning improvement, has blazed the trail for Provisiond. The Importer service has been in production for 3 years in service provider networks maintaining entity counts of more than 50,000 node level entities on a single instances of OpenNMS. It is a rock solid provisioning tool.

Provisiond begins a new era of managed entity provisioning in OpenNMS.

11.2. Concepts

Provisioning is a term that is familiar to service providers (a.k.a. operators, a.k.a. telephone companies) and OSS systems but not so much in the non OSS enterprises.

Provisiond receives "requests" for adding managed entities via 2 basic mechanisms, the OpenNMS Meridian traditional "New Suspect" event, typically via the *Discovery daemon*, and the import requisition (XML definition of node entities) typically via the Provisioning Groups UI. If you are familiar with all previous releases of OpenNMS, you will recognize the *New Suspect Event* based *Discovery* to be what was previously the *Capsd* component of the auto discovery behavior. You will also recognize the import requisition to be of the *Model Importer* component of OpenNMS. *Provisiond* now unifies these two separate components into a massively parallel advanced policy based provisioning service.

11.2.1. Terminology

The following terms are used with respect to the OpenNMS Meridian provisioning system and are essential for understanding the material presented in this guide.

Entity

Entities are managed objects in OpenNMS Meridian such as Nodes, IP interfaces, SNMP Interfaces, and Services.

Foreign Source and Foreign ID

The *Importer* service from 1.6 introduced the idea of foreign sources and foreign IDs. The *Foreign Source* uniquely identifies a provisioning source and is still a basic attribute of importing node entities into OpenNMS Meridian. The concept is to provide an external (foreign) system with a way to uniquely identify itself and any node entities that it is requesting (via a requisition) to be provisioned into OpenNMS Meridian.

The *Foreign ID* is the unique node ID maintained in foreign system and the foreign source uniquely identifies the external system in OpenNMS Meridian.

OpenNMS Meridian uses the combination of the foreign source and foreign ID become the unique foreign key when synchronizing the set of nodes from each source with the nodes in the OpenNMS Meridian DB. This way the foreign system doesn't have to keep track of the OpenNMS Meridian node IDs that are assigned when a node is first created. This is how *Provisiond* can decided if a node entity from an import requisition is new, has been changed, or needs to be deleted.

Foreign Source Definition

Additionally, the foreign source has been extended to also contain specifications for how entities should be discovered and managed on the nodes from each foreign source. The name of the foreign source has become pervasive within the provisioning system and is used to simply some of the complexities by weaving this name into:

- the name of the provisioning group in the Web-UI
- the name of the file containing the persisted requisition (as well as the pending requisition if it is in this state)
- the foreign-source attribute value inside the requisition (obviously, but, this is pointed out to indicate that the file name doesn't necessarily have to equal the value of this attribute but is highly recommended as an OpenNMS Meridian best practice)
- the building attribute of the node defined in the requisition (this value is called "site" in the Web-UI and is assigned to the building column of the node's asset record by Provisiond and is the default value used in the Site Status View feature)

Import Requisition

Import requisition is the terminology OpenNMS Meridian uses to represent the set of nodes, specified in XML, to be provisioned from a foreign source into OpenNMS Meridian. The requisition schema (XSD) can be found at the following location. http://xmlns.opennms.org/xsd/config/model-

import

Auto Discovery

Auto discovery is the term used by OpenNMS Meridian to characterize the automatic provisioning of nodes entities. Currently, OpenNMS Meridian uses an ICMP ping sweep to find IP address on the network. Auto-discovery-with-detectors will allow defining specific detectors for auto discovery to succeed. For the IPs that succeed and that are not currently in the DB, OpenNMS Meridian generates a new suspect event. When this event is received by Provisiond, it creates a node and it begins a node scan based on the default foreign source definition.

Directed Discovery

Provisiond takes over for the Model Importer found in version 1.6 which implemented a unique, first of its kind, controlled mechanism for specifying managed entities directly into OpenNMS Meridian from one or more data sources. These data sources often were in the form of an in-house developed inventory or stand-alone provisioning system or even a set of element management systems. Using this mechanism, OpenNMS Meridian is directed to add, update, or delete a node entity exactly as defined by the external source. No discovery process is used for finding more interfaces or services.

Enhanced Directed Discovery

Directed discovery is enhanced with the capability to scan nodes that have been directed nodes for entities (interfaces.

Policy-Based Discovery

The phrase policy-based directed discovery, is a term that represents the latest step in OpenNMS Meridian provisioning evolution and best describes the new provisioning architecture now in OpenNMS Meridian for maintaining its inventory of managed entities. This term describes the control that is given over the Provisioning system to OpenNMS Meridian users for managing the behavior of the NMS with respect to the new entities that are being discovered. Current behaviors include persistence, data collection, service monitoring, and categorization policies.

11.2.2. Addressing Scalability

The explosive growth and density of the IT systems being deployed today to support not traditional IP services is impacting management systems like never before and is demanding from them tremendous amounts of scalability. The scalability of a management system is defined by its capacity for maintaining large numbers of managing entities coupled with its efficiency of managing the entities.

Today, It is not uncommon for OpenNMS Meridian deployments to find node entities with tens of thousands of physical interfaces being reported by SNMP agents due to virtualization (virtual hosts, interfaces, as well as networks). An NMS must be capable of using the full capacity every resource of its computing platform (hardware and OS) as effectively as possible in order to manage these environments. The days of writing scripts or single threaded applications will just no longer be able to do the work required an NMS when dealing with the scalability challenges facing systems and

systems administrators working in this domain.

Parallelization and Non-Blocking I/O

Squeezing out every ounce of power from a management system's platform (hardware and OS) is absolutely required to complete all the work of a fully functional NMS such as OpenNMS Meridian. Fortunately, the hardware and CPU architecture of a modern computing platform provides multiple CPUs with multiple cores having instruction sets that include support for atomic operations. While these very powerful resources are being provided by commodity systems, it makes the complexity of developing applications to use them vs. not using them, orders of magnitude more complex. However, because of scalability demands of our complex IT environments, multi-threaded NMS applications are now essential and this has fully exposed the complex issues of concurrency in software development.

OpenNMS Meridian has stepped up to this challenge with its new concurrency strategy. This strategy is based on a technique that combines the efficiency of parallel (asynchronous) operations (traditionally used by most effectively by single threaded applications) with the power of a fully current, non-blocking, multi-threaded design. The non-blocking component of this new concurrency strategy added greater complexity but OpenNMS Meridian gained orders of magnitude in increased scalability.



Java Runtimes, based on the Sun JVM, have provided implementations for processor based atomic operations and is the basis for OpenNMS Meridian' nonblocking concurrency algorithms.

Provisioning Policies

Just because you can, doesn't mean you should! Because the massively parallel operations being created for *Provisiond* allows tremendous numbers of nodes, interfaces, and services to be very rapidly discovered and persisted, doesn't mean it should. A *policy API* was created for *Provisiond* that allows implementations to be developed that can be applied to control the behavior of *Provisiond*. The 1.8 release includes a set of flexible provisioning policies that control the persistence of entities and their attributes constrain monitoring behavior.

When nodes are imported or re-scanned, there is, potentially, a set of zero or more provisioning policies that are applied. The policies are defined in the foreign source's definition. The policies for an auto-discovered node or nodes from provisioning groups that don't have a foreign source definition, are the policies defined in the default foreign source definition.

The Default Foreign Source Definition

Contained in the libraries of the Provisioning service is the "template" or default foreign source. The template stored in the library is used until the OpenNMS Meridian admin user alters the default from the *Provisioning Groups* WebUI. Upon edit, this template is exported to the OpenNMS Meridian etc/ directory with the file name: default-foreign-source.xml.

```
<?xml version="1.0" encoding="UTF-8" standalone="yes"?>
<foreign-source date-stamp="2009-10-16T18:04:12.844-05:00"</pre>
                 name="default"
                 xmlns=
"http://xmlns.opennms.org/[http://xmlns.opennms.org/xsd/config/foreign-source">
    <scan-interval>1d</scan-interval>
    <detectors>
      <detector class="org.opennms.netmgt.provision.detector.datagram.DnsDetector"</pre>
name="DNS"/>
      <detector class="org.opennms.netmgt.provision.detector.simple.FtpDetector" name</pre>
="FTP"/>
      <detector class="org.opennms.netmgt.provision.detector.simple.HttpDetector"</pre>
name="HTTP"/>
      <detector class="org.opennms.netmgt.provision.detector.simple.HttpsDetector"</pre>
name="HTTPS"/>
      <detector class="org.opennms.netmgt.provision.detector.icmp.IcmpDetector" name=</pre>
"ICMP"/>
      <detector class="org.opennms.netmgt.provision.detector.simple.ImapDetector"</pre>
name="IMAP"/>
      <detector class="org.opennms.netmgt.provision.detector.simple.LdapDetector"</pre>
name="LDAP"/>
      <detector class="org.opennms.netmgt.provision.detector.simple.NrpeDetector"</pre>
name="NRPF"/>
      <detector class="org.opennms.netmgt.provision.detector.simple.Pop3Detector"</pre>
name="POP3"/>
      <detector class="
org.opennms.netmgt.provision.detector.radius.RadiusAuthDetector" name="Radius"/>
      <detector class="org.opennms.netmgt.provision.detector.simple.SmtpDetector"</pre>
name="SMTP"/>
      <detector class="org.opennms.netmgt.provision.detector.snmp.SnmpDetector" name=</pre>
"SNMP"/>
      <detector class="org.opennms.netmgt.provision.detector.ssh.SshDetector" name=</pre>
"SSH"/>
 </detectors>
 <policies/>
</foreign-source>
```

Automatic Rescanning

The default foreign source defines a scan-interval of 1d, which will cause all nodes in the requisition to be scanned daily. You may set the scan interval using any combination of the following signifiers:

- w: Weeks
- d: Days
- h: Hours
- m: Minutes
- s: Seconds

• ms: Milliseconds

For example, to rescan every 6 days and 53 minutes, you would set the scan-interval to 6d 53m.

Don't forget, for the new scan interval to take effect, you will need to import the requisition one more time so that the foreign source becomes active.

Disabling Rescan

For a large number of devices, you may want to set the scan-interval to 0 to disable automatic rescan altogether. OpenNMS Meridian will not attempt to rescan the nodes in the requisition unless you trigger a manual (forced) rescan through the web UI or Provisioning ReST API.

11.3. Getting Started

An NMS is of no use until it is setup for monitoring and entities are added to the system. OpenNMS Meridian installs with a base configuration with a configuration that is sufficient get service level monitoring and performance management quickly up and running. As soon as managed entities are provisioned, the base configuration will automatically begin monitoring and reporting.

Generally speaking, there are two methods of provisioning in OpenNMS Meridian: *Auto Discovery* and *Directed Discovery*. We'll start with *Auto Discovery*, but first, we should quickly review the configuration of SNMP so that newly discovered devices can be immediately scanned for entities as well as have reporting and thresholding available.

11.3.1. Provisioning the SNMP Configuration

OpenNMS Meridian requires SNMP configuration to be properly setup for your network in order to properly understand Network and Node topology as well as to automatically enable performance data collection. Network topology is updated as nodes (a.k.a. devices or hosts) are provisioned. Navigate to the *Admin/Configure SNMP Community Names by IP address* as shown below.

HORIZON			Search	Info 👻	Status 👻	Reports 🗸	(Dashboards 🗸		9:54 CEST 🜘
Home / Admin / Configure SNMP	by IP								
SNMP Config Lookup		Descriptions							
IP Address		SNMP Config Lookup: You can look box and press "Look up". The config						te SNMP Cor	nfig Lookup
Look up		Updating SNMP Configuration: In the boxes on the left, enter in a specific IP address and community string, or a range of IP addresses and a community string, and other SNMP parameters.						es and a	
		OpenNMS will optimize this list, so added that includes a specific IP ac							a range is
		For devices that have already been changed, it may be necessary to up these changes to take effect.							
Updating SNMP Configuration		v1/v2c specific parameters							
General Parameters		Read Community String:	YrusoNoz						
			Default: public						
Version:	v2c •	Write Community String:							
	Default: v2c		Default: private						
First IP Address:	10.1.1.1								
Last IP Address:	10.254.254.254								
Timeout:	2000								
	Default: 3000 ms								
Retries:									
	Default: 1								

Configuring SNMP community names



Provisiond includes an option to add community information in the *Single Node* provisioning interface. This, is equivalent of entering a single IP address in the screen with the convenience of setting the community string at the same time a node is provisioned. See the *Quick Node Add* feature below for more details about this capability.

This screen sets up SNMP within OpenNMS Meridian for agents listening on IP addresses 10.1.1.1 through 10.254.254.254. These settings are optimized into the snmp-configuration.xml file. Optimization means that the minimal configuration possible will be written. Any IP addresses already configured that are eclipsed by this range will be removed. Here is the resulting configuration.

Sample snmp-config.xml

```
<?xml version="1.0" encoding="UTF-8"?>

<snmp-config

xmlns="http://xmlns.opennms.org/xsd/config/snmp[http://xmlns.opennms.org/xsd/config/sn

mp]"

port="161" retry="3" timeout="800" read-community="public"

version="v1" max-vars-per-pdu="10">

<definition retry="1" timeout="2000"

read-community="public" version="v2c">

<specific>10.12.23.32</specific>

</definition>

</snmp-config>
```

However, If an IP address is then configured that is within the range, the range will be split into two separate ranges and a specific entry will be added. For example, if a configuration was added through the same UI for the IP: 10.12.23.32 having the community name public, then the resulting configuration will be:

```
<?xml version="1.0" encoding="UTF-8"?>
<snmp-config xmlns="http://xmlns.opennms.org/xsd/config/snmp"</pre>
             port="161"
             retry="3"
             timeout="800"
             read-community="public"
             version="v1"
             max-vars-per-pdu="10">
    <definition retry="1" timeout="2000" read-community="YrusoNoz" version="v2c">
        <range begin="10.1.1.1" end="10.12.23.31"/>
        <range begin="10.12.23.33" end="10.254.254.254"/>
    </definition>
    <definition retry="1" timeout="2000" read-community="public" version="v2c">
        <specific>10.12.23.32</specific>
    </definition>
</snmp-config>
```



the bold IP addresses show where the range was split and the specific with community name "public" was added.

Now, with SNMP configuration provisioned for our 10 networks, we are ready to begin adding nodes. Our first example will be to automatically discover and add all managed entities (nodes, IP interfaces, SNMP Interfaces, and Monitored IP based Services). We will then give an example of how to be more *directed* and deliberate about your discovery by using *Provisioning Groups*.

Automatically discovered entities are analyzed, persisted to the relational data store, and then managed based on the policies defined in the default foreign source definition. This is very similar to the way that entities were previously handled by the (now obsolete) Capsd daemon but with finer grained sense of control.

11.3.2. Automatic Discovery

Currently in OpenNMS Meridian, the ICMP is used to automatically provision node entities into OpenNMS Meridian. This functionality has been in OpenNMS since its 1.0 release, however, in 1.8, a few of the use cases have been updated with *Provisiond's* replacement of *Capsd*.

Separation of Concerns

Version 1.8 *Provisiond* separates what was called *Capsd* scanning in to 3 distinct phases: entity scanning, service detection, and node merging. These phases are now managed separately by Provisiond. Immediately following the import of a node entity, tasks are created for scanning a node to discover the node entity's interfaces (SNMP and IP). As interfaces are found, they are persisted and tasks are scheduled for service detection of each IP interface.

For auto discovered nodes, a node merging phase is scheduled; Nodes that have been directly provisioned will not be included in the node merging process. Merging will only occur when 2

automatically discovered nodes appear to be the same node.



the use case and redesign of node merging is still an outstanding issue with the 1.8.0 release

11.3.3. Enhanced Directed Discovery

This new form of provisioning first appears in OpenNMS with version 1.8 and the new Provisiond service. It combines the benefits of the Importer's strictly controlled methodology of directed provisioning (from version 1.6) with OpenNMS' robustly flexible auto discovery. *Enhanced Directed discovery* begins with an enhanced version of the same import requisition used in directed provisioning and completes with a policy influenced persistence phase that sorts though the details of all the entities and services found during the entity and service scanning phase.

If you are planning to use this form of provisioning, it important to understand the conceptual details of how *Provisiond* manages entities it is *directed* to provision. This knowledge will enable administrators and systems integrators to better plan, implement, and resolve any issues involved with this provisioning strategy.

Understanding the Process

There are 3 phases involved with directing entities to be discovered: import, node scan, and service scan. The import phase also has sub phases: marshal, audit, limited SNMP scan, and re-parent.

Marshal and Audit Phases

It is important to understand that the nodes requisitioned from each foreign source are managed as a complete set. Nodes defined in a requisition from the foreign source *CRM* and *CMDB*, for example, will be managed separately from each other even if they should contain exactly the same node definitions. To OpenNMS Meridian, these are individual entities and they are managed as a set.

Requisitions are referenced via a URL. Currently, the URL can be specified as one of the following protocols: FILE, HTTP, HTTPS, and DNS. Each protocol has a protocol handler that is used to stream the XML from a *foreign source*, i.e. http://inv.corp.org/import.cgi?customer=acme or file:/opt/opennms/etc/imports/acme.xml. The DNS protocol is a special handler developed for Provisioning sets of nodes as a *foreign-source* from a corporate DNS server. See DNS Protocol Handler for details.

Upon the import request (either on schedule or on demand via an Event) the requisition is marshaled into Java objects for processing. The nodes defined in the requisition represent what OpenNMS Meridian should have as the current set of managed entities from that foreign source. The audit phase determines for each node defined (or not defined) in the requisition which are to be processed as an *Add*, *Update*, or *Delete* operation during the *Import Phase*. This determination is made by comparing the set foreign IDs of each node in the requisition set with the set of foreign IDs of currently managed entities in OpenNMS Meridian.

The intersection of the IDs from each set will become the Update operations, the extra set of foreign IDs that are in the requisition become the Add operations, and the extra set of foreign IDs from the managed entities become the Delete operations. This implies that the foreign IDs from each foreign

source must be unique.

Naturally, the first time an import request is processed from a foreign source there will be zero (0) node entities from the set of nodes currently being managed and each node defined in the requisition will become an Add Operation. If a requisition is processed with zero (0) node definitions, all the currently managed nodes from that foreign source will become Delete operations (all the nodes, interfaces, outages, alarms, etc. will be removed from OpenNMS Meridian).

When nodes are provisioned using the Provisioning Groups Web-UI, the requisitions are stored on the local file system and the file protocol handler is used to reference the requisition. Each Provisioning Group is a separate foreign source and unique foreign IDs are generated by the Web-UI. An MSP might use Provisioning Groups to define the set of nodes to be managed by customer name where each customer's set of nodes are maintained in a separate Provisioning Group.

Import Phase

The import phase begins when Provisiond receives a request to import a requisition from a URL. The first step in this phase is to load the requisition and marshal all the node entities defined in the requisition into Java objects.

If any syntactical or XML structural problems occur in the requisition, the entire import is abandoned and no import operations are completed.

Once the requisition is marshaled, the requisition nodes are audited against the persisted node entities. The set of requisitioned nodes are compared with a subset of persisted nodes and this subset is generated from a database query using the foreign source defined in the requisition. The audit generates one of three operations for each requisition node: *insert, update, delete* based on each requisitioned node's foreign ID. Delete operations are created for any nodes that are not in the requisition but are in the DB subset, update operations are created for requisition nodes that match a persisted node from the subset (the intersection), and insert operations are created from the remaining requisition nodes (nodes in the requisition that are not in the DB subset).

If a requisition node has an interface defined as the Primary SNMP interface, then during the update and insert operations the node will be scanned for minimal SNMP attribute information. This scan find the required node and SNMP interface details required for complete SNMP support of the node and only the IP interfaces defined in the requisition.



this not the same as Provisiond SNMP discovery scan phases: node scan and interface scan.

Node Scan Phase

Where directed discovery leaves off and enhanced directed discovery begins is that after all the operations have completed, directed discovery is finished and enhanced directed discovery takes off. The requisitioned nodes are scheduled for node scans where details about the node are discovered and interfaces that were not directly provisioned are also discovered. All physical (SNMP) and logical (IP) interfaces are discovered and persisted based on any *Provisioning Policies* that may have been defined for the foreign source associated with the import requisition.

Additionally, the new Provisiond enhanced directed discovery mechanism follows interface discovery with service detection on each IP interface entity. This is very similar to the Capsd plugin scanning found in all former releases of OpenNMS except that the foreign source definition is used to define what services should be detected on these interfaces found for nodes in the import requisition.

11.4. Import Handlers

The new Provisioning service in OpenNMS Meridian is continuously improving and adapting to the needs of the community.

One of the most recent enhancements to the system is built upon the very flexible and extensible API of referencing an import requisition's location via a URL. Most commonly, these URLs are files on the file system (i.e. file:/opt/opennms/etc/imports/<my-provisioning-group.xml>) as requisitions created by the Provisioning Groups UI. However, these same requisitions for adding, updating, and deleting nodes (based on the original model importer) can also come from URLs. For example a requisition can be retrieving the using HTTP protocol: http://myinventory.server.org/nodes.cgi

In addition to the standard protocols supported by Java, we provide a series of custom URL handlers to help retrieve requisitions from external sources.

11.4.1. Generic Handler

The generic handler is made available using URLs of the form: requisition://type?param=1;param=2

Using these URLs various type handlers can be invoked, both locally and via a *Minion*.

In addition to the type specific parameters, the following parameters are supported:

Paramet er	Description	Requir ed	Default value
location	The name of location at which the handler should be run	optiona l	Default
ttl	The maximum number of miliseconds to wait for the handler when ran remotely	optiona l	20000

Table 99. General parameters

See the relevant sections bellow for additional details on the support types.

The opennms: show-import command available via the *Karaf Shell* can be used to show the results of an import (without persisting or triggering the import):

opennms:show-import -1 MINION http url=http://127.0.0.1:8000/req.xml

11.4.2. File Handler

Examples:

Simple

file:///path/to/my/requisition.xml

Using the generic handler

requisition://file?path=/path/to/my/requisition.xml;location=MINION

11.4.3. HTTP Handler

Examples:

Simple

http://myinventory.server.org/nodes.cgi

Using the generic handler

requisition://http?url=http%3A%2F%2Fmyinventory.server.org%2Fnodes.cgi



When using the generic handler, the URL should be "URL encoded".

11.4.4. DNS Handler

The DNS handler requests a *Zone Transfer (AXFR) request* from a DNS server. The A records are recorded and used to build an import requisition. This is handy for organizations that use DNS (possibly coupled with an IP management tool) as the data base of record for nodes in the network. So, rather than ping sweeping the network or entering the nodes manually into OpenNMS Meridian Provisioning UI, nodes can be managed via 1 or more DNS servers.

The format of the URL for this new protocol handler is: dns://<host>[:port]/<zone>[/<foreign-source>/][?expression=<regex>]

DNS Import Examples:

Simple

```
dns://my-dns-server/myzone.com
```

This URL will import all A records from the host my-dns-server on port 53 (default port) from zone "myzone.com" and since the foreign source (a.k.a. the provisioning group) is not specified it will default to the specified zone.

dns://my-dns-server/myzone.com/portland/?expression=^por-.*

This URL will import all nodes from the same server and zone but will only manage the nodes in the zone matching the regular expression <u>port-.</u>* and will and they will be assigned a unique foreign source (provisioning group) for managing these nodes as a subset of nodes from within the specified zone.

If your expression requires URL encoding (for example you need to use a ? in the expression) it must be properly encoded.

```
dns://my-dns-server/myzone.com/portland/?expression=^por[0-9]%3F
```

You can use the location parameter to assign a single location to all nodes in this requisition:

```
dns://my-dns-server/myzone.com/portland/?location=Raleigh
```

By preceding a ~ you can specify a properly encoded regular expression to determine the location based on the host entries. In the following, for example, we want to derive the location based on the subdomain. We use the regular expression (?:..)(.?).hs-fulda.de.\$ with exactly one capturing group:

```
dns://my-dns-server/hs-
fulda.de/?location=~%5E%28%3F%3A.%2A%5C.%7C%29%28.%2A%3F%29%5C.hs-fulda%5C.de%5C.%24
```

This will associate nodes for the host entries foo.e46.hs-fulda.de. and bar.e46.hs-fulda.de. to the location e46 while hosts like aaa.g51.hs-fulda.de and bbb.g51.hs-fulda.de will be assigned location g51.



You can use online tools like https://www.urlencoder.org to en- and decode your parameters.

DNS Setup

Currently, the DNS server requires to be setup to allow a zone transfer from the OpenNMS Meridian server. It is recommended that a secondary DNS server is running on OpenNMS Meridian and that the OpenNMS Meridian server be allowed to request a zone transfer. A quick way to test if zone transfers are working is:

```
dig -t AXFR @<dnsServer> <zone>
```

Configuration

The configuration of the Provisoning system has moved from a properties file (modelimporter.properties) to an XML based configuration container. The configuration is now extensible to allow the definition of 0 or more import requisitions each with their own cron based schedule for automatic importing from various sources (intended for integration with external URL such as http and this new dns protocol handler.

A default configuration is provided in the OpenNMS Meridian etc/ directory and is called: provisiond-configuration.xml. This default configuration has an example for scheduling an import from a DNS server running on the localhost requesting nodes from the zone, localhost and will be imported once per day at the stroke of midnight. Not very practical but is a good example.

```
<?xml version="1.0" encoding="UTF-8"?>
   configuration xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance"
xsi:schemaLocation="http://xmlns.opennms.org/xsd/config/provisiond-configuration"
                             foreign-source-dir="/opt/opennms/etc/foreign-sources"
                             requistion-dir="/opt/opennms/etc/imports"
                             importThreads="8"
                             scanThreads="10"
                             rescanThreads="10"
                             writeThreads="8" >
   <!--http://www.quartz-scheduler.org/documentation/quartz-1.x/tutorials/crontrigger
       Field Name Allowed Values Allowed Special Characters
       Seconds 0-59 , - * / Minutes 0-59 , - * / Hours 0-23 , - * /
       Day-of-month1-31, - * ? / L W C Month1-12 or JAN-DEC, - * /
       Day-of-Week1-7 or SUN-SAT, - * ? / L C # Year (Opt)empty, 1970-2099, - * /
   -->
   <requisition-def import-name="localhost"
                    import-url-resource="dns://localhost/localhost">
       <cron-schedule>0 0 0 * * ? *</cron-schedule> <!-- daily, at midnight -->
   </requisition-def>
</provisiond-configuration>
```

Configuration Reload

Like many of the daemon configuration in the 1.7 branch, the configurations are reloadable without having to restart OpenNMS Meridian, using the reloadDaemonConfig uei:

/opt/opennms/bin/send-event.pl
uei.opennms.org/internal/reloadDaemonConfig --parm 'daemonName Provisiond'

This means that you don't have to restart OpenNMS Meridian every time you update the configuration.

11.5. Provisioning Examples

Here are a few practical examples of enhanced directed discovery to help with your understanding of this feature.

11.5.1. Basic Provisioning

This example adds three nodes and requires no OpenNMS Meridian configuration other than specifying the node entities to be provisioned and managed in OpenNMS Meridian.

Defining the Nodes via the Web-UI

Using the Provisioning Groups Web-UI, three nodes are created given a single IP address. Navigate to the Admin Menu and click Provisioning Groups Menu from the list of Admin options and create the group *Bronze*.

Creating a new Provisioning Group

Home / Admin /	Provisioning Groups
Bronze	Add New Group (Edit Default Foreign Source) (Reset Default Foreign Source)

Clicking the *Add New Group* button will create the group and will redisplay the page including this new group among the list of any group(s) that have already been created.

Add New Group	Edit Default Foreign Source (Reset Default Foreign Source)
Bronze	
Requisition (Provisioning Group): Define node and interface data for import.	EDIT 0 nodes defined, 0 nodes in database last modified: 2009-10-17T21:37:06.543-04:00 last import requested: never
Foreign Source: Define scanning behavior for import.	EDIT CLONE



At this point, the XML structure for holding the new provisioning group (a.k.a. an import requisition) has been persisted to the '\$OPENNMS_ETC/imports/pending' directory.

Clicking the *Edit* link will bring you to the screen where you can begin the process of defining node entities that will be imported into OpenNMS Meridian. Click the Add Node button will begin the node entity creation process fill in the node label and click the *Save* button.

Creating a new Node definition in the Provisioning Group

Home / Admin / Provisioning Groups / Edit Requisition						
Manually Provisioned Nodes for Group: Bronze						
Done Add Node						
Node cartman.opennms.org	ForeignId	1255830454086	Site	Bronze	Save Cancel	

At this point, the provisioning group contains the basic structure of a node entity but it is not complete until the interface(s) and interface service(s) have been defined. After having clicked the *Save* button, as we did above presents, in the Web-UI, the options *Add Interface, Add Node Category,* and *Add Node Asset*. Click the *Add Interface* link to add an interface entity to the node.



Enter the IP address for this interface entity, a description, and specify the Primary attribute as P (Primary), S (Secondary), N (Not collected), or C (Collected) and click the save button. Now the node entity has an interface for which services can be defined for which the Web-UI now presents the *Add Service* link. Add two services (ICMP, SNMP) via this link.

A complete node definition with all required elements defined.



Now the node entity definition contains all the *required* elements necessary for importing this requisition into OpenNMS Meridian. At this point, all the interfaces that are required for the node should be added. For example, NAT interfaces should be specified there are services that they provide because they will not be discovered during the Scan Phase.

Two more node definitions will be added for the benefit of this example.

The completed requisition for the example Bronze Provisioning Group

anually Provisioned Nodes for Group: B	ronze						
Done Add Node							
• 🗊 🗹 Node timmy.opennms.org	ForeignId	1255831743007	Site	Bronze		[Add Int	erface] [Add Node Category] [Add Node Asset
。 🗓 🗹 IP Interface 10.1.1.3		Description timmy-if-	-1		Snmp Primary	Р	Add Service
 ICMP 							
• 🗊 🗹 Node barbrady.opennms.org	ForeignId	1255831696516	Site	Bronze		[Add Int	erface] [Add Node Category] [Add Node Asset
。 <u> </u>		Description barbrady-	if-1		Snmp Primary	Р	Add Service
 ICMP 							
 Image: Image: Ima							
• 🗊 🗹 Node cartman.opennms.org	ForeignId	1255830454086	Site	Bronze		[Add Int	erface] [Add Node Category] [Add Node Asset]
₀ 🗍 🗹 IP Interface 10.1.1.1		Description cartman-i	f-1		Snmp Primary	Р	Add Service
 Image: Image: Ima							
III Service SNMP							

This set of nodes represents an import requisition for the *Bronze* provisioning group. As this requisition is being edited via the WebUI, changes are being persisted into the OpenNMS Meridian configuration directory '\$OPENNMS_etc/imports/' pending as an XML file having the name bronze.xml.



The name of the XML file containing the import requisition is the same as the provisioning group name. Therefore naming your provisioning group without the use of spaces makes them easier to manage on the file system.

Click the *Done* button to return to the *Provisioning Groups* list screen. The details of the "Bronze" group now indicates that there are 3 nodes in the requisition and that there are no nodes in the DB from this group (a.k.a. foreign source). Additionally, you can see that time the requisition was last modified and the time it last imported are given (the time stamps are stored as attributes inside the requisition and are not the file system time stamps). These details are indicative of how well the DB represents what is in the requisition.

Home / Admin / Provisioning Groups

Add New Grou	p (Edit Default Foreign Source) (Reset Default Foreign Source)
Bronze	
Delete Group Import	
Requisition (Provisioning Group): Define node and interface data for import.	EDIT 3 nodes defined, 0 nodes in database last modified: 2009-10-17T22:10:29.654-04:00 last import requested: never
Foreign Source: Define scanning behavior for import.	EDIT CLONE



You can tell that this is a pending requisition for 2 reasons: 1) there are 3 nodes defined and 0 nodes in the DB, 2) the requisition has been modified since the last import (in this case *never*).

Import the Nodes

In this example, you see that there are 3 nodes in the pending requisition and 0 in the DB. Click the *Import* button to submit the requisition to the provisioning system (what actually happens is that the Web-UI sends an event to the Provisioner telling it to begin the Import Phase for this group).



Do not refresh this page to check the values of these details. To refresh the details to verify the import, click the *Provisioning Groups* bread crumb item.

You should be able to immediately verify the importation of this provisioning group because the import happens very quickly. Provisiond has several threads ready for processing the import operations of the nodes defined in this requisition.

A few SNMP packets are sent and received to get the SNMP details of the node and the interfaces defined in the requisition. Upon receipt of these packets (or not) each node is inserted as a DB transaction.

The nodes are now added to OpenNMS Meridian and are under management.

Home / Search / Node Li	st	
Nodes and their interfaces	;	
 barbrady.opennms.org 10.1.1.2 cartman.opennms.org 10.1.1.1 	timmy.opennms.org • 10.1.1.3	
3 Nodes, 3 Interfaces Hide in	iterfaces	

Following the import of a node with thousands of interfaces, you will be able to refresh the Interface table browser on the Node page and see that interfaces and services are being discovered and added in the background. This is the discovery component of directed discovery.

Adding a Node

To direct that another node be added from a foreign source (in this example the Bronze Provisioning Group) simply add a new node definition and re-import. It is important to remember that all the node definitions will be re-imported and the existing managed nodes will be updated, if necessary.

Changing a Node

To direct changes to an existing node, simply add, change, or delete elements or attributes of the node definition and re- import. This is a great feature of having directed specific elements of a node in the requisition because that attributes will simply be changed. For example, to change the IP address of the Primary SNMP interface for the node, *barbrady.opennms.org*, just change the requisition and re-import.


Each element in the Web-UI has an associated Edit icon Click this icon to change the IP address for barbrady.opennms.org, click save, and then Click the Done button.

Changing the IP address of barbrady.opennms.org from 10.1.1.2 to 192.168.1.1



The Web-UI will return you to the *Provisioning Groups* screen where you will see that there are the time stamp showing that the requisition's last modification is more recent that the last import time.

The Provisioning Group must be re-imported



This provides an indication that the group must be re-imported for the changes made to the

requisition to take effect. The IP Interface will be simply updated and all the required events (messages) will be sent to communicate this change within OpenNMS Meridian.

The IP interface for barbrady.opennms.org is immediately updated

Nodes and their interfaces		
barbrady.opennms.org	timmy.opennms.org	
 192.168.1.1 	 10.1.1.3 	
cartman.opennms.org		
 10.1.1.1 		

Deleting a Node

Barbrady has not been behaving, as one might expect, so it is time to remove him from the system. Edit the provisioning group, click the delete button next to the node *barbrady.opennms.org*, click the *Done* button.

Bronze Provisioning Group definition indicates a node has been removed and requires an import to delete the node entity from the OpenNMS Meridian system

EDIT
2 nodes defined, 3 nodes in database
last modified: 2009-10-20T17:34:33.337+01:00
last import requested: 2009-10-20T17:26:38.371+01:00
EDIT CLONE

Click the Import button for the Bronze group and the Barbrady node and its interfaces, services, and any other related data will be immediately deleted from the OpenNMS Meridian system. All the required Events (messages) will be sent by Provisiond to provide indication to the OpenNMS Meridian system that the node Barbrady has been deleted.

Barbrady has been deleted

Home / Search / Node List		
Nodes and their interfaces		
cartman.opennms.org	timmy.opennms.org	
• 10.1.1.1	• 10.1.1.3	
2 Nodes, 2 Interfaces Hide interface	15	

Deleting all the Nodes

There is a convenient way to delete all the nodes that have been provided from a specific foreign source. From the main *Admin/Provisioning Groups* screen in the Web-UI, click the *Delete Nodes* button. This button deletes all the nodes defined in the Bronze requisition. It is very important to note that once this is done, it cannot be undone! Well it can't be undone from the Web-UI and can only be undone if you've been good about keeping a backup copy of your '\$OPENMS_ETC/' directory

tree. If you've made a mistake, before you re-import the requisition, restore the Bronze.xml requisition from your backup copy to the '\$OPENNMS_ETC/imports' directory.

All node definitions have been removed from the Bronze requisition. The Web-UI indicates an import is now required to remove them from OpenNMS Meridian.



Clicking the *Import* button will cause the *Audit Phase* of *Provisiond* to determine that all the nodes from the *Bronze* group (foreign source) should be deleted from the DB and will create *Delete* operations. At this point, if you are satisfied that the nodes have been deleted and that you will no longer require nodes to be defined in this Group, you will see that the *Delete Nodes* button has now changed to the *Delete Group* button. The *Delete Group* button is displayed when there are no nodes entities from that group (foreign source) in OpenNMS Meridian.

When no node entities from the group exist in OpenNMS Meridian, then the *Delete Group* button is displayed.

11.5.2. Advanced Provisioning Example

In the previous example, we provisioned 3 nodes and let *Provisiond* complete all of its import phases using a default foreign source definition. Each Provisioning Group can have a separate foreign source definition that controls:

- The rescan interval
- The services to be detected
- The policies to be applied

This example will demonstrate how to create a foreign source definition and how it is used to control the behavior of Provisiond when importing a *Provisioning Group/foreign source requisition*.

First let's simply provision the node and let the default foreign source definition apply.

The node definition used for the Advanced Provisioning Example

Home / Admin / Provisioning Groups /	Edit Requis	ition				
Manually Provisioned Nodes for Group: N	MS					
Done Add Node						
• 🗊 🗹 Node p-brane	ForeignId 3	1	Site NMS		[Add Interfa	ce] [Add Node Category] [Add Node Asset]
•	roreignia .	Description loopback	Site Mins	Snmp Primary	and the second second	Add Service
■ Î Z Service SNMP		beschption hoppack		Junp Tunary		Add Sciffee
 ICMP 						
。 闻 🗹 Node Category Test						
。 🗊 🗹 Node Category Servers						

Following the import, All the IP and SNMP interfaces, in addition to the interface specified in the requisition, have been discovered and added to the node entity. The default foreign source definition has no polices for controlling which interfaces that are discovered either get persisted or managed by OpenNMS Meridian.

IP Interfaces	Physical Interfaces	
IP Address	IP Host Name	Managed
127.0.0.1	127.0.0.1	м
192.168.199.1		м
192.168.93.1		м
192.168.1.1		м
172.16.1.1		м
10.1.1.1		м
Page 1	of 1 🕨 🕅 🍣 🔍 Search	1 - 6 of 6
- L	of 1 🕨 🕅 🍣 🔍 Search gory Memberships (Edit)	1 - 6 of 6
- L		1 - 6 of 6

Logical and Physical interface and Service entities directed and discovered by Provisiond.

IP Interfaces Physical Interfaces					
Inde	SNMP ifDescr	SNMP IfN	SNMP IFA	SNMP if	IP Address
8	vmnet8	vmnet8		0	192.168.9
9	vmnet1	vmnet1		0	192.168.1
1	lo0	lo0		0	192.168.1.1
7	en2	en2		10000000	0.0.0.0
6	en1	en1		10000000	0.0.0.0
5	fw0	fw0		10000000	0.0.0.0
4	en0	en0		1000000	0.0.0.0
3	stf0	stf0		0	0.0.0.0
2	gif0	gif0		0	0.0.0.0
< < Page 1 of 1 < > < 2 < Search 1 - 9 of 9					
Sur	veillance Cate	gory Member	rships (Edit)		
Serv	/ers				
Test	t				

Home / Search / Node / Interface Interface: 10.1.1.1

View Events by Ip address View Events by ifIndex Response Time Graphs Delete Rescan

General				
Node	p-brane			
Polling Status	Managed			
Polling Package	example1			
Polling Package	strafer			
Interface Index	1			
Last Service Scan	10/22/09 11:42:24 AM			
Physical Address				
Link Node/Interface				
No link information has been collected for	this interface.			
Services				
SNMP				
SSH				
ICMP				
DNS				
Availability				
Overall Availability	100.000%			
DNS	100.000%			
ICMP	100.000%			
SNMP	100.000%			
SSH	100.000%			
	Percentage over last 24 hours			

Service Detection

As IP interfaces are found during the node scan process, service detection tasks are scheduled for each IP interface. The service detections defined in the foreign source determines which services are to be detected and how (i.e. the values of the parameters that parameters control how the service is detected, port, timeout, etc.).

Applying a New Foreign Source Definition

This example node has been provisioned using the Default foreign source definition. By navigating to the Provisioning Groups screen in the OpenNMS Meridian Web-UI and clicking the Edit Foreign Source link of a group, you can create a new foreign source definition that defines service detection and policies. The policies determine entity persistence and/or set attributes on the discovered entities that control OpenNMS Meridian management behaviors.

When creating a new foreign source definition, the default definition is used as a template.

Foreign Source: NMS		
Done		
🗹 Scan Interval 🛛 1d		
Detectors (Add Detector)		
🛯 🗊 🗹 name DNS	class org.opennms.netmgt.provision.detector.datagram.DnsDetector	[Add Parameter]
🔹 🗊 🗹 name 🛛 FTP	class org.opennms.netmgt.provision.detector.simple.FtpDetector	[Add Parameter]
🛛 🗊 🗹 name 🛛 HTTP	class org.opennms.netmgt.provision.detector.simple.HttpDetector	[Add Parameter]
🔹 <u> </u>	class org.opennms.netmgt.provision.detector.simple.HttpsDetector	[Add Parameter]
🔹 <u> </u>	class org.opennms.netmgt.provision.detector.icmp.lcmpDetector	[Add Parameter]
🛛 🗊 🗹 name IMAP	class org.opennms.netmgt.provision.detector.simple.ImapDetector	[Add Parameter]
🛛 🗍 🗹 name LDAP	class org.opennms.netmgt.provision.detector.simple.LdapDetector	[Add Parameter]
🛛 🗊 🗹 name 🛛 NRPE	class org.opennms.netmgt.provision.detector.simple.NrpeDetector	[Add Parameter]
🔹 <u> </u>	class org.opennms.netmgt.provision.detector.simple.Pop3Detector	[Add Parameter]
🛛 <u> </u>	class org.opennms.netmgt.provision.detector.radius.RadiusAuthDetector	[Add Parameter]
🛛 🗊 🗹 name SMTP	class org.opennms.netmgt.provision.detector.simple.SmtpDetector	[Add Parameter]
🛛 <u> </u>	class org.opennms.netmgt.provision.detector.snmp.SnmpDetector	[Add Parameter]
🔹 <u> </u>	class org.opennms.netmgt.provision.detector.ssh.SshDetector	[Add Parameter]
Policies (112 h)		
Policies Add Policy		

In this UI, new Detectors can be added, changed, and removed. For this example, we will remove detection of all services accept ICMP and DNS, change the timeout of ICMP detection, and a new Service detection for OpenNMS Meridian Web-UI.

Custom foreign source definition created for NMS Provisioning Group (foreign source).

Foreign Source: NMS				
🗹 Scan Interval 🛛 1d				
Detectors Add Detector				
• 🗊 🗹 name DNS		class	org.opennms.netmgt.provision.detector.datagram.DnsDetector	[Add Parameter]
• 🔟 🗹 name ICMP		class	org.opennms.netmgt.provision.detector.icmp.lcmpDetector	[Add Parameter]
o 闻 🗹 key timeout	value	1000		
🔹 🔟 🗹 name OpenNMS		class	org.opennms.netmgt.provision.detector.simple.HttpDetector	[Add Parameter]
o 🔟 🗹 key port	value	8980		
Policies (Add Policy)				

Click the Done button and re-import the NMS Provisioning Group. During this and any subsequent re-imports or re- scans, the OpenNMS Meridian detector will be active, and the detectors that have been removed will no longer test for the related services for the interfaces on nodes managed in the provisioning group (requisition), however, the currently detected services will not be removed. There are 2 ways to delete the previously detected services:

- 1. Delete the node in the provisioning group, re-import, define it again, and finally re-import again
- 2. Use the ReST API to delete unwanted services. Use this command to remove each unwanted service from each interface, iteratively:

curl -X DELETE -H "Content-Type: application/xml" -u admin:admin http://localhost:8980/opennms/rest/nodes/6/ipinterfaces/172.16.1.1/services/DNS

Q

There is a sneaky way to do #1. Edit the provisioning group and just change the foreign ID. That will make Provisiond think that a node was deleted and a new node was added in the same requisition! Use this hint with caution and an full understanding of the impact of deleting an existing node.

Provisioning with Policies

The Policy API in Provisiond allow you to control the persistence of discovered IP and SNMP Interface entities and Node Categories during the Scan phase.

Matching IP Interface Policy

The Matching IP Interface policy controls whether discovered interfaces are to be persisted and if they are to be persisted, whether or not they will be forced to be Managed or Unmanaged.

Continuing with this example Provisioning Group, we are going to define a few policies that:

- 1. Prevent discovered 10 network addresses from being persisted
- 2. Force 192.168 network addresses to be unmanaged

From the foreign source definition screen, click the Add Policy button and the definition of a new policy will begin with a field for naming the policy and a drop down list of the currently installed policies. Name the policy *no10s*, make sure that the *Match IP Interface policy* is specified in the class list and click the Save button. This action will automatically add all the parameters required for the policy.

The two required parameters for this policy are action and matchBehavior.

The action parameter can be set to DO_NOT_PERSIST, Manage, or UnManage.

Policies Add Policy		
• 🗊 🗹 name no10s	class org.opennms.netmgt.provision.persist.policies.MatchinglpInterfacePolicy	[Add Parameter]
• 🗹 key action	value DO_NOT_PERSIST	
• 🗹 key matchBehavior	value ALL_PARAMETERS	

Creating a policy to prevent persistence of 10 network IP interfaces.

The *DO_NOT_PERSIST* action does just what it indicates, it prevents discovered IP interface entities from being added to OpenNMS Meridian when the *matchBehavior* is satisfied. The Manage and UnManage values for this action allow the IP interface entity to be persisted by control whether or not that interface should be managed by OpenNMS Meridian.

The matchBehavior action is a boolean control that determines how the optional parameters will be evaluated. Setting this parameter's value to *ALL_PARAMETERS* causes *Provisiond* to evaluate each optional parameter with boolean *AND* logic and the value *ANY_PARAMETERS* will cause *OR* logic to be applied.

Now we will add one of the optional parameters to filter the 10 network addresses. The Matching IP Interface policy supports two additional parameters, *hostName* and *ipAddress*. Click the *Add Parameter* link and choose *ipAddress* as the *key*. The *value* for either of the optional parameters can be an exact or regular expression match. As in most configurations in OpenNMS Meridian where

regular expression matching can be optionally applied, prefix the value with the ~ character.

Example Matching IP Interface Policy to not Persist 10 Network addresses

Policies (Add Policy)		
• 🗊 🗹 name no10s • key action	class org.opennms.netmgt.provision.persist.policies.MatchinglpInterfacePolicy value DO_NOT_PERSIST Save Cancel	[Add Parameter]
o ☑ key matchBehavior o 🗊 🗹 key ipAddress	value ALL_PARAMETERS value ~10*	

Any subsequent scan of the node or re-imports of NMS provisioning group will force this policy to be applied. IP Interface entities that already exist that match this policy will not be deleted. Existing interfaces can be deleted by recreating the node in the *Provisioning Groups* screen (simply change the foreign ID and re-import the group) or by using the ReST API:

```
curl -X DELETE -H "Content-Type: application/xml" -u admin:admin
http://localhost:8980/opennms/rest/nodes/6/ipinterfaces/10.1.1.1
```

The next step in this example is to define a policy that sets discovered 192.168 network addresses to be unmanaged (not managed) in OpenNMS Meridian. Again, click the Add Policy button and let's call this policy *noMgt192168s*. Again, choose the Mach IP Interface policy and this time set the action to *UNMANAGE*.

Policy to not manage IP interfaces from 192.168 networks

class org.opennms.netmgt.provision.persist.policies.MatchinglpInterfacePo	olicy [Add Parameter]
value DO_NOT_PERSIST	
value ALL_PARAMETERS	
alue ~10*	
class org.opennms.netmgt.provision.persist.policies.MatchinglpInterfacePo	olicy [Add Parameter]
value UNMANAGE	
value ALL_PARAMETERS	
alue ~192\.168\.*	
	value DO_NOT_PERSIST value ALL_PARAMETERS value ~10* class org.opennms.netmgt.provision.persist.policies.MatchingIpInterfacePo value UNMANAGE

B

The UNMANAGE behavior will be applied to existing interfaces.

Matching SNMP Interface Policy

Like the Matching IP Interface Policy, this policy controls the whether discovered SNMP interface entities are to be persisted and whether or not OpenNMS Meridian should collect performance metrics from the SNMP agent for Interface's index (MIB2 IfIndex).

In this example, we are going to create a policy that doesn't persist interfaces that are *AAL5* over *ATM* or type 49 (*ifType*). Following the same steps as when creating an IP Management Policy, edit the foreign source definition and create a new policy. Let's call it: *noAAL5s*. We'll use Match SNMP Interface class for each policy and add a parameter with *ifType* as the key and 49 as the value.

Matching SNMP Interface Policy example for Persistence and Data Collection

Policies Add Policy		
• 🗊 🗹 name no10s	class org.opennms.netmgt.provision.persist.policies.MatchinglpInterfacePolicy	[Add Parameter]
• 🖾 key action	value UNMANAGE	
• 🗹 key matchBehavior	value ALL_PARAMETERS	
	ue ~10*	
• 🔟 🗹 name noAAL5s	class org.opennms.netmgt.provision.persist.policies.MatchingSnmpInterfacePolicy	[Add Parameter]
• 🗹 key action	value DO_NOT_PERSIST	
• 🗹 key matchBehavior	value ALL_PARAMETERS	
o 🗊 🗹 key ifType 🛛 vali	ue 49	



At the appropriate time during the scanning phase, Provisiond will evaluate the policies in the foreign source definition and take appropriate action. If during the policy evaluation process any policy matches for a "DO_NOT_PERSIST" action, no further policy evaluations will happen for that particular entity (IP Interface, SNMP Interface).

Node Categorization Policy

With this policy, nodes entities will automatically be assigned categories. The policy is defined in the same manner as the IP and SNMP interface polices. Click the Add Policy button and give the policy name, cisco and choose the *Set Node Category* class. Edit the required *category* key and set the value to Cisco. Add a policy parameter and choose the *sysObjectId* key with a value $\sim^{1}.1.3.6.1.4.1.9...*$.

Example: Node Category setting policy

Policies (Add Policy)		
• 🗊 🗹 name no10s	class org.opennms.netmgt.provision.persist.policies.MatchinglpInterfacePolicy	[Add Parameter]
• 🗹 key action	value UNMANAGE	
• 🗹 key matchBehavior	value ALL_PARAMETERS	
o 🔟 🗹 key ipAddress 🛛 value	~10*	
• 🗊 🗹 name noAAL5s	class org.opennms.netmgt.provision.persist.policies.MatchingSnmpInterfacePolicy	[Add Parameter]
• 🗹 key action	value DO_NOT_PERSIST	
• 🗹 key matchBehavior	value ALL_PARAMETERS	
o 🔟 🗹 key ifType 🛛 value	49	
• 🗊 🗹 name cisco	class org.opennms.netmgt.provision.persist.policies.NodeCategorySettingPolicy	[Add Parameter]
• 🗹 key category	value Cisco	
• 🖾 key matchBehavior		
o 🔟 🗹 key sysObjectId value	~^\.1\.3\.6\.1\.4\.1\.9\	

Script Policy

This policy allows to use *Groovy* scripts to modify provisioned node data. These scripts have to be placed in the OpenNMS Meridian etc/script-policies directory. An example would be the change of the node's primary interface or location. The script will be invoked for each matching node. The following example shows the source code for setting the 192.168.100.0/24 interface to PRIMARY while all remaining interfaces are set to SECONDARY. Furthermore the node's location is set to Minneapolis.

```
import org.opennms.netmgt.model.OnmsIpInterface;
import org.opennms.netmgt.model.monitoringLocations.OnmsMonitoringLocation;
import org.opennms.netmgt.model.PrimaryType;
for(OnmsIpInterface iface : node.getIpInterfaces()) {
    if (iface.getIpAddressAsString().matches("^192\\.168\\.100\\..*")) {
        LOG.warn(iface.getIpAddressAsString() + " set to PRIMARY")
        iface.setIsSnmpPrimary(PrimaryType.PRIMARY)
    } else {
        LOG.warn(iface.getIpAddressAsString() + " set to SECONDARY")
        iface.setIsSnmpPrimary(PrimaryType.SECONDARY)
    }
}
node.setLocation(new OnmsMonitoringLocation("Minneapolis", ""));
return node;
```

New Import Capabilities

Several new XML entities have been added to the import requisition since the introduction of the OpenNMS Importer service in version 1.6. So, in addition to provisioning the basic node, interface, service, and node categories, you can now also provision asset data.

Provisiond Configuration

The configuration of the Provisioning system has moved from a properties file (modelimporter.properties) to an XML based configuration container. The configuration is now extensible to allow the definition of 0 or more import requisitions each with their own *Cron* based schedule for automatic importing from various sources (intended for integration with external URL such as HTTP and this new DNS protocol handler.

A default configuration is provided in the OpenNMS Meridian etc/ directory and is called: provisiond-configuration.xml. This default configuration has an example for scheduling an import from a DNS server running on the localhost requesting nodes from the zone, localhost and will be imported once per day at the stroke of midnight. Not very practical but is a good example.

```
<?xml version="1.0" encoding="UTF-8"?>
    <provisiond-configuration xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance"</pre>
xsi:schemaLocation="http://xmlns.opennms.org/xsd/config/provisiond-configuration"
        foreign-source-dir="/opt/opennms/etc/foreign-sources"
        requistion-dir="/opt/opennms/etc/imports"
        importThreads="8"
        scanThreads="10"
        rescanThreads="10"
        writeThreads="8" >
    <!--
        http://www.quartz-scheduler.org/documentation/quartz-
1.x/tutorials/crontrigger[http://www.quartz-scheduler.org/documentation/quartz-
1.x/tutorials/crontrigger]
        Field Name Allowed Values Allowed Special Characters
        Seconds 0-59 , - * / Minutes 0-59 , - * / Hours 0-23 , - * /
        Day-of-month1-31, - * ? / L W C Month1-12 or JAN-DEC, - * /
       Day-of-Week1-7 or SUN-SAT, - * ? / L C # Year (Opt)empty, 1970-2099, - * /
    -->
    <requisition-def import-name="NMS"
                     import-url-resource="file://opt/opennms/etc/imports/NMS.xml">
        <cron-schedule>0 0 0 * * ? *</cron-schedule> <!-- daily, at midnight -->
    </requisition-def>
</provisiond-configuration>
```

Configuration Reload

Like many of the daemon configurations in the 1.7 branch, *Provisiond's* configuration is re-loadable without having to restart OpenNMS. Use the reloadDaemonConfig uei:

```
/opt/opennms/bin/send-event.pl uei.opennms.org/internal/reloadDaemonConfig --parm
'daemonName Provisiond'
```

This means that you don't have to restart OpenNMS Meridian every time you update the configuration!

Provisioning Asset Data

The Provisioning Groups Web-UI had been updated to expose the ability to add Node Asset data in an import requisition. Click the *Add Node Asset* link and you can select from a drop down list all the possible node asset attributes that can be defined.

Home / Admin / Provisioning Gro	•	n				
Manually Provisioned Nodes for Gro	up: NMS					
• 🗊 🗹 Node p-brane	ForeignId 1		Site NMS		[Add Interface	e) [Add Node Category] [Add Node Asset]
。 🗊 🗹 IP Interface 127.0		scription loopback		Snmp Primary		Add Service
🛛 🔟 🗹 Service SN	IMP					
🛛 <u> </u> Service IC						
。 🗊 🗹 Node Category Te	st					
。 🗊 🗹 Node Category Se						
o 🗊 🗹 asset rack	12					
o 🗊 🗹 asset room	equipment					
o 🗊 🗹 asset floor	G					
o 🗊 🗹 asset address1	220 Chatham Busines	ss Dri				
。 🗊 🗹 asset city	Raleigh					
o 🗊 🗹 asset state	NC					
。 🗊 🗹 asset zip	27312					

After an import, you can navigate to the *Node Page* and click the *Asset Info* link and see the asset data that was just provided in the requisition.

	1		'	1	1
Location					
Region		Division		Department	
Address 1	220 Chatham Business Drive, Suite 100				
Address 2					
City	Raleigh	State	NC	ZIP	27312
Building	NMS	Floor	G	Room	equipment
Rack	12	Slot		Port	
Circuit ID					

External Requisition Sources

Because Provisiond takes a *URL* as the location service for import requisitions, OpenNMS Meridian can be easily extended to support sources in addition to the native URL handling provided by Java: *file://, http://,* and *https://.* When you configure *Provisiond* to import requisitions on a schedule you specify using a *URL* Resource. For requisitions created by the *Provisioning Groups* WebUI, you can specify a file based URL.



<need further documentation>

Provisioning Nodes from DNS

The new Provisioning service in OpenNMS Meridian is continuously improving and adapting to the needs of the community. One of the most recent enhancements to the system is built upon the very flexible and extensible API of referencing an import requisition's location via a URL. Most commonly, these URLs are files on the file system (i.e. file:/opt/opennms/etc/imports/<my-provisioning-group.xml>) as requisitions created by the Provisioning Groups UI. However, these same requisitions for adding, updating, and deleting nodes (based on the original model importer) can also come from URLs specifying the HTTP protocol: http://myinventory.server.org/nodes.cgi)

Now, using Java's extensible protocol handling specification, a new protocol handler was created so that a URL can be specified for requesting a Zone Transfer (*AXFR*) request from a DNS server. The *A*

records are recorded and used to build an import requisition. This is handy for organizations that use DNS (possibly coupled with an IP management tool) as the data base of record for nodes in the network. So, rather than ping sweeping the network or entering the nodes manually into OpenNMS Meridian Provisioning UI, nodes can be managed via 1 or more DNS servers. The format of the URL for this new protocol handler is:

dns://<host>[:port]/<zone>[/<foreign-source>/][?expression=<regex>]

Simple Example

dns://my-dns-server/myzone.com

This will import all *A records* from the host *my-dns-server* on port 53 (default port) from zone *myzone.com* and since the foreign source (a.k.a. the provisioning group) is not specified it will default to the specified zone.

Using a Regular Expression Filter

You can also specify a subset of the *A records* from the zone transfer using a regular expression:

dns://my-dns-server/myzone.com/portland/?expression=^por-.*

This will import all nodes from the same server and zone but will only manage the nodes in the zone matching the regular expression ^port-.* and will and they will be assigned a unique foreign source (provisioning group) for managing these nodes as a subset of nodes from within the specified zone.

URL Encoding

If your expression requires URL encoding (for example you need to use a ? in the expression) it must be properly encoded.

```
dns://my-dns-server/myzone.com/portland/?expression=^por[0-9]%3F
```

DNS Setup

Currently, the DNS server requires to be setup to allow a zone transfer from the OpenNMS Meridian server. It is recommended that a secondary DNS server is running on OpenNMS Meridian and that the OpenNMS Meridian server be allowed to request a zone transfer. A quick way to test if zone transfers are working is:

```
dig -t AXFR @<dn5Server> <zone>
```

11.6. Adapters

The OpenNMS Meridian Provisiond API also supports Provisioning Adapters (plugins) for

integration with external systems during the provisioning Import phase. When node entities are added, updated, deleted, or receive a configuration management change event, OpenNMS Meridian will call the adapter for the provisioning activities with integrated systems.

Currently, OpenNMS Meridian supports the following adapters:

11.6.1. DDNS Adapter

The Opposite end of *Provisiond* integration from the DNS Requisition Import, is the *DDNS adapter*. This adapter uses the *dynamic DNS protocol* to update a DNS system as nodes are provisioned into OpenNMS Meridian. To configure this adapter, edit the opennms.properties file and set the importer.adapter.dns.server property:

```
importer.adapter.dns.server=192.168.1.1
```

11.6.2. RANCID Adapter

Integration has been integrated with RANCID though this new API.



11.7. Meta-Data assigned to Nodes

A requisition can contain arbitrary meta-data for each node, interface and service it contains. During provisioning, the meta-data is copied to the model and persisted in the database.

The Requisition UI allows to edit the meta-data defined in a requisition. The edit function in the Requisition UI is limited to only edit the context called requisition by intention. All other contexts are reserved for future use by other provisioning-adapters and similar applications like asset-data.

While provisioning a requisition, the meta-data from the requisition is transferred to the database and assigned to the nodes, interfaces and services accordingly.

11.7.1. User defined contexts

If there is a requirement to add more contexts not managed by OpenNMS Meridian, the context name must be prefixed by X-. Any third-party software must take care to choose a context name which is unique enough to not conflict with other software.

11.8. Integrating with Provisiond

The ReST API should be used for integration from other provisioning systems with OpenNMS

Meridian. The ReST API provides an interface for defining foreign sources and requisitions.

11.8.1. Provisioning Groups of Nodes

Just as with the WebUI, groups of nodes can be managed via the ReST API from an external system. The steps are:

- 1. Create a Foreign Source (if not using the default) for the group
- 2. Update the SNMP configuration for each node in the group
- 3. Create/Update the group of nodes

11.8.2. Example

Step 1 - Create a Foreign Source

If policies for this group of nodes are going to be specified differently than the default policy, then a foreign source should be created for the group. Using the ReST API, a foreign source can be provided. Here is an example:



The XML can be imbedded in the curl command option -d or be referenced from a file if the @ prefix is used with the file name as in this case.

The XML file: customer-a.foreign-source.xml:

```
<?xml version="1.0" encoding="UTF-8" standalone="yes"?>
<foreign-source date-stamp="2009-10-12T17:26:11.616-04:00" name="customer-a" xmlns=</pre>
"http://xmlns.opennms.org/xsd/config/foreign-source">
    <scan-interval>1d</scan-interval>
    <detectors>
        <detector class="org.opennms.netmgt.provision.detector.icmp.IcmpDetector"</pre>
name="ICMP"/>
        <detector class="org.opennms.netmgt.provision.detector.snmp.SnmpDetector"</pre>
name="SNMP"/>
   </detectors>
    <policies>
        <policy class=
"org.opennms.netmgt.provision.persist.policies.MatchingIpInterfacePolicy" name="no-
192-168">
            <parameter value="UNMANAGE" key="action"/>
            <parameter value="ALL_PARAMETERS" key="matchBehavior"/>
            <parameter value="~^192\.168\..*" key="ipAddress"/>
        </policy>
    </policies>
</foreign-source>
```

Here is an example curl command used to create the foreign source with the above foreign source specification above:

```
curl -v -u admin:admin -X POST -H 'Content-type: application/xml' -d '@customer-
a.foreign-source.xml' http://localhost:8980/opennms/rest/foreignSources
```

Now that you've created the foreign source, it needs to be deployed by Provisiond. Here an the example using the curl command to deploy the foreign source:

```
curl -v -u admin:admin
http://localhost:8980/opennms/rest/foreignSources/pending/customer-a/deploy -X PUT
```



The current API doesn't strictly follow the ReST design guidelines and will be updated in a later release.

Step 2 - Update the SNMP configuration

The implementation only supports a *PUT* request because it is an implied "Update" of the configuration since it requires an IP address and all IPs have a default configuration. This request is is passed to the SNMP configuration factory in OpenNMS Meridian for optimization of the configuration store snmp-config.xml. This example changes the community string for the IP address 10.1.1.1 to yRuSonoZ.

6

Community string is the only required element

```
curl -v -X PUT -H "Content-Type: application/xml" -H "Accept: application/xml" -d
<snmp-
info><community>yRuSonoZ</community><port>161</port><retries>1</retries><timeout>2000<
/timeout><version>v2c</version></snmp-info>" -u admin:admin
http://localhost:8980/opennms/rest/snmpConfig/10.1.1.1
```

Step 3 - Create/Update the Requisition

This example adds 2 nodes to the Provisioning Group, *customer-a*. Note that the foreign-source attribute typically has a 1 to 1 relationship to the name of the Provisioning Group requisition. There is a direct relationship between the foreign- source attribute in the requisition and the foreign source policy specification. Also, typically, the name of the provisioning group will also be the same. In the following example, the ReST API will automatically create a provisioning group based on the value foreign-source attribute specified in the XML requisition.

curl -X POST -H "Content-Type: application/xml" -d "<?xml version="1.0" encoding="UTF-8"?><model-import xmlns="http://xmlns.opennms.org/xsd/config/model-import" datestamp="2009-03-07T17:56:53.123-05:00" last-import="2009-03-07T17:56:53.117-05:00" foreign-source="customer-a"><node node-label="p-brane" foreign-id="1" ><interface ipaddr="10.0.1.3" descr="en1" status="1" snmp-primary="P"><monitored-service servicename="ICMP"/><monitored-service service-name="SNMP"/></interface><category name="Production"/><category name="Routers"/></node><node node-label="m-brane" foreign-id="1" ><interface ip-addr="10.0.1.4" descr="en1" status="1" snmpprimary="P"><monitored-service service-name="ICMP"/></monitored-service servicename="ICMP"/></note></model-import>" -u admin:admin http://localhost:8980/opennms/rest/requisitions

A provisioning group file called etc/imports/customer-a.xml will be found on the OpenNMS Meridian system following the successful completion of this curl command and will also be visible via the WebUI.



Add, Update, Delete operations are handled via the ReST API in the same manner as described in detailed specification.

11.9. Provisioning Single Nodes (Quick Add Node)

Adding a Node to a Current Requisition

Often, it is requested that a single node add/update be completed for an already defined provisioning group. There is a ReST API for the *Add Node* implementation found in the OpenNMS Meridian Web-UI. For this to work, the provisioning group must already exist in the system even if there are no nodes defined in the group.

- 1. Create a foreign source (if required)
- 2. Specify SNMP configuration
- 3. Provide a single node with the following specification

11.10. Fine Grained Provisioning Using provision.pl

provision.pl provides an example command-line interface to the provisioning-related OpenNMS Meridian REST API endpoints.

The script has many options but the first 3 optional parameters are described here:



You can use --help to the script to see all the available options.

```
--username (default: admin)
--password (default: admin)
--url (default: http://localhost:8980/opennms/rest)
```

11.10.1. Create a new requisition

provision.pl provides easy access to the requisition REST service using the *requisition* option:

```
${OPENNMS_HOME}/bin/provision.pl requisition customer1
```

This command will create a new, empty (containing no nodes) requisition in OpenNMS Meridian.

The new requisition starts life in the pending state. This allows you to iteratively build the requisition and then later actually import the nodes in the requisition into OpenNMS Meridian. This handles all adds/changes/deletes at once. So, you could be making changes all day and then at night either have a schedule in OpenNMS Meridian that imports the group automatically or you can send a command through the REST service from an outside system to have the pending requisition imported/reimported.

You can get a list of all existing requisitions with the list option of the provision.pl script:

\${OPENNMS_HOME}/bin/provision.pl list

Create a new Node

\${OPENNMS_HOME}/bin/provision.pl node add customer1 1 node-a

This command creates a node element in the requisition *customer1* called *node-a* using the script's *node* option. The node's foreign-ID is *1* but it can be any alphanumeric value as long as it is unique within the requisition. Note the node has no interfaces or services yet.

Add an Interface Element to that Node

\${OPENNMS_HOME}/bin/provision.pl interface add customer1 1 127.0.0.1

This command adds an interface element to the node element using the *interface* option to the provision.pl command and it can now be seen in the pending requisition by running provision.pl requisition list customer1.

Add a Couple of Services to that Interface

```
${OPENNMS_HOME}/bin/provision.pl service add customer1 1 127.0.0.1 ICMP
${OPENNMS_HOME}/bin/provision.pl service add customer1 1 127.0.0.1 SNMP
```

This adds the 2 services to the specified 127.0.0.1 interface and is now in the pending requisition.

\${OPENNMS_HOME}/bin/provision.pl interface set customer1 1 127.0.0.1 snmp-primary P

This sets the 127.0.0.1 interface to be the node's Primary SNMP interface.

Add a couple of Node Categories

```
${OPENNMS_HOME}/bin/provision.pl category add customer1 1 Routers
${OPENNMS_HOME}/bin/provision.pl category add customer1 1 Production
```

This adds the two categories to the node and is now in the pending requisition.

These categories are case-sensitive but do not have to be already defined in OpenNMS Meridian. They will be created on the fly during the import if they do not already exist.

Setting Asset Fields on a Node

\${OPENNMS_HOME}/bin/provision.pl asset add customer1 1 serialnumber 9999

This will add value of 9999 to the asset field: serialnumber.

Deploy the Import Requisition (Creating the Group)

\${OPENNMS_HOME}/bin/provision.pl requisition import customer1

This will cause OpenNMS Meridian Provisiond to import the pending customer1 requisition. The formerly pending requisition will move into the deployed state inside OpenNMS Meridian.

Deleting a Node from a Requisition

Very much the same as the add, except that a single delete command and a re-import is required. What happens is that the audit phase is run by Provisiond and it will be determined that a node has been removed from the requisition and the node will be deleted from the DB and all services will stop activities related to it.

```
${OPENNMS_HOME}/bin/provision.pl node delete customer1 1 node-a
${OPENNMS_HOME}/bin/provision.pl requisition import customer1
```

This completes the life cycle of managing a node element, iteratively, in a import requisition.

11.11. Yet Other API Examples

List the Nodes in a Provisioning Group

The provision.pl script doesn't supply this feature but you can get it via the REST API. Here is an

```
#!/bin/bash
REQ=$1
curl -X GET -H "Content-Type: application/xml" -u admin:admin
http://localhost:8980/opennms/rest/requisitions/$REQ 2>/dev/null | xmllint --format -
```

11.12. SNMP Profiles

SNMP Profiles are prefabricated sets of SNMP configuration which are automatically "fitted" against eligible IP addresses at provisioning time. Each profile may have a unique label and an optional filter expression. If the filter expression is present, it will be evaluated to check whether a given IP address or reverse-lookup hostname passes the filter. A profile with a filter expression will be fitted to a given IP address only if the filter expression evaluates true against that IP address.

SNMP profiles can be added to snmp-config.xml to enable automatic fitting of SNMP interfaces.

Sample snmp-config.xml with profiles

```
<snmp-config xmlns="http://xmlns.opennms.org/xsd/config/snmp" write-community="</pre>
private" read-community="public" timeout="800" retry="3">
  <definition version="v1" ttl="6000">
      <specific>127.0.0.1</specific>
  </definition>
  <profiles>
      <profile version="v1" read-community="horizon" timeout="10000">
         <label>profile1</label>
      </profile>
      <profile version="v1" ttl="6000">
         <label>profile2</label>
         <filter>iphostname LIKE '%opennms%'</filter>
      </profile>
      <profile version="v1" read-community="meridian">
         <label>profile3</label>
         <filter>IPADDR IPLIKE 172.1.*.*</filter>
      </profile>
  </profiles>
</snmp-config>
```

In the above config,

- 1. profile1 doesn't have a filter expression. This profile will be tried for every interface.
- profile2 has a filter expression that compares iphostname (the hostname resulting from a reverse DNS lookup of the IP address being fitted) against a preconfigured value. This profile's SNMP parameters will be fitted only against IP addresses whose hostname contains the string opennms.
- 3. profile3 has an IPLIKE expression that matches all interfaces in the range specified in the filter.

This profile's SNMP parameters will be fitted only against IP addresses in the range specified by the IPLIKE expression.



Profiles will be tried in the order they are configured. The first match that produces a successful SNMP GET-REQUEST on the scalar instance of sysObjectID will be saved by Provisiond as the SNMP configuration definition to use for all future SNMP operations against the fitted IP address.



default as profile label is reserved for default SNMP config.

Fit a SNMP profile

The opennms:snmp-fit Karaf shell command finds a matching profile for a given IP address and prints out the resulting config.

Matching or "fitting" an SNMP profile should be understood as passing the profile's filter expression *and* success in getting the scalar sysObjectID instance.

```
$ ssh -p 8101 admin@localhost
...
admin@opennms()> opennms:snmp-fit -l MINION -s 172.1.1.105 ①
admin@opennms()> opennms:snmp-fit 172.1.1.106 profile1 ②
```

- ① searches the profiles that fit the IP address 172.1.1.105 at location Minion and saves the resulting configuration as a definition for future use.
- (2) checks whether the profile with label profile1 is a fit for IP address 172.1.1.106. If it succeeds, it prints out the resulting agent config, but does not save any definition.

Remove an IP address from definition.

The opennms:snmp-remove-from-definition Karaf shell command removes an IP address from the system-wide SNMP configuration definitions.

```
$ ssh -p 8101 admin@localhost
...
admin@opennms()> opennms:snmp-remove-from-definition -l MINION 172.1.0.255
```

This removes IP address 172.1.0.255 at location MINION from the system-wide SNMP configuration so that this IP address can be fitted to a new profile. This command might be useful when an IP address formerly assigned to an SNMPv2c-capable switch is reassigned to an SNMPv3-capable load balancer.

Using SNMP profiles in Snmp Detector

By default SnmpDetector doesn't use SNMP profiles. Add property useSnmpProfiles and set it to true in order to use SNMP Profiles.

11.13. Auto Discovery with Detectors

Currently OpenNMS Meridian uses ICMP ping sweep to find IP address on the network. The IP Ranges and specifics can be defined in discovery-configuration.xml as shown below.

Sample discovery configuration

```
<discovery-configuration xmlns="http://xmlns.opennms.org/xsd/config/discovery"
packets-per-second="1"
initial-sleep-time="30000" restart-sleep-time="86400000" retries="1"
timeout="2000">
<!-- see examples/discovery-configuration.xml for options -->
<specific>10.0.0.5</specific>
<include-range>
<begin>192.168.0.1</begin>
<end>192.168.0.254</end>
</include-range>
<include-range>
<include-url>file:/opt/opennms/etc/include.txt</include-url>
</discovery-configuration>
```

Auto Discovery with Detectors allows users to specify the services that needs to be detected apart from ICMP ping for the IP Addresses to be discovered. Only when specified detectors succeeds, auto discovery will send new suspect event.

Sample Configuration with detectors is shown below.

```
<discovery-configuration xmlns="http://xmlns.opennms.org/xsd/config/discovery"</pre>
packets-per-second="1"
                  initial-sleep-time="30000" restart-sleep-time="86400000" retries="1"
timeout="2000">
 <definition location="MINION" foreign-source="ApexOffice">
        <detectors>
            <detector name="reverse-dns-lookup" class-name=</pre>
"org.opennms.netmgt.provision.detector.rdns.ReverseDNSLookupDetector"/>
            <detector name="SNMP" class-name=</pre>
"org.opennms.netmgt.provision.detector.snmp.SnmpDetector">
                <parameter key="timeout" value="5000"/>
                <parameter key="ttl" value="120000"/>
            </detector>
        </detectors>
        <specific>10.0.0.5</specific>
        <include-range>
            <begin>192.168.0.1</begin>
            <end>192.168.0.254</end>
        </include-range>
    <exclude-range>
            <begin>192.168.0.120</begin>
            <end>192.168.0.125</end>
        </exclude-range>
        <include-url>file:/opt/opennms/etc/include.txt</include-url>
    </definition>
</discovery-configuration>
```

In above configuration, specifics and ranges are moved into definition with SNMP and reverse-dnslookup detectors. When all of the detectors succeeeds at a given location, then only the specific IP Address considered to be discovered.

A definition without any detectors will fall back to ICMP ping for discovery.

11.14. Service Detectors

Service detectors allow to bind a service to an interface automatically if it is detected during provisioning of a requisition.

11.14.1. Meta-Data-DSL

Service detectors can leverage dynamic configuration by using the Meta-Data-DSL in each possible parameter.

During evaluation of an expression the following scopes are available:

- Node meta-data
- Interface meta-data

11.14.2. HTTP Detector

This detector is used to find and assigns services based on *HTTP*.

Detector facts

Implementation org.opennms.netmgt.provision.detector.simple.HttpDetector

Configuration and Usage

Table 100. Parameters for the HTTP detector

Paramet er	Description	Requi red	Default value
checkRetC ode	If set to true only HTTP status codes that are the same or lower than the value of <i>maxRetCode</i> pass.	option al	false
maxRetCod e	Highest HTTP response code that passes. <i>maxRetCode</i> is only evaluated if checkRetCode is set to true.	option al	399
port	Port to query .	option al	80
url	Url to query	option al	/
timeout	Timeout in milliseconds to wait for a response.	option al	2000

Please note: The Http Detector makes only one http request and doesn't follow redirects.

Example Configuration

```
<?rml version="1.0" encoding="UTF-8" standalone="yes"?>
<foreign-source date-stamp="2010-06-29T13:15:30.494+02:00" name="test" xmlns=
"http://xmlns.opennms.org/xsd/config/foreign-source">
<scan-interval>1d</scan-interval>
<detectors>
<detector class="org.opennms.netmgt.provision.detector.simple.HttpDetector" name=
"http8080">
<parameter key="port" value="8080"/>
<parameter key="url" value="index2.html" />
<parameter key="maxRetCode" value="200"/>
<parameter key="checkRetCode" value="true"/>
</detector>
</detector>
</detector>
</detector></plicies/>
</foreign-source>
```

11.14.3. HTTPS Detector

This detector is used to find and assigns services based on HTTPS.

Detector facts

Implementation org.opennms.netmgt.provision.detector.simple.HttpsDetector

Configuration and Usage

Parameters for the HTTPS detector

The parameters are the same as for the HTTP detector

11.14.4. SNMP Detector

This detector is used to find and assigns services based on *SNMP*. The detector binds a service with a given *Service Name* when a particular *SNMP OID* as scalar or table matches a given criteria.

Detector facts

Implementation org.opennms.netmgt.provision.detector.snmp.SnmpDetector

Configuration and Usage

Table 101	Parameters	for	the	CNIND	datactor
<i>Tuble</i> 101.	<i>Fuluitietels</i>	101	ine	SIVIVIE	uelector

Paramete	Description	Requi	Default
r		red	value
oid	SNMP OID for scalar or table to detect the service.	requir ed	.1.3.6.1.2.1 .1.2.0

Paramete r	Description	Requi red	Default value
retry	Number of retries to detect the service.	option al	agent config
timeout	Timeout in milliseconds to wait for a response from the <i>SNMP</i> agent.	option al	agent config
vbvalue	expected return value to detect the service; if not specified the service is detected if the <i>SNMP OID</i> returned any kind of valid value. The vbvalue is evaluated as Java Regular Expression.	option al	-
hex	Set true if the data is from type <i>HEX-String</i> .	option al	false
isTable	Set true if detector should evaluate <i>SNMP tables</i> .	option al	false
matchType	Set match type to evaluate the expected value in the SNMP table. <i>EXIST</i> : the expected vbalue is ignored, service detected if the given table under <i>OID</i> exist <i>ALL</i> : all values in the table must match against expected vbalue to detect service <i>ANY</i> : at least one value in the table must match against expected vbalue to detect service <i>NONE</i> : None of the values should match against expected value to detect service	option al	EXIST
useSnmpPro files	Set true if detector should use SNMP profiles to detect SNMP service.	option al	false
ttl	Time to live in milliseconds to wait for a response from the Minion.	option al	20000

Example for SNMP scalar value

We have *Dell* server farm and want to monitor the global server status provided by the *OpenManage Server Administrator*. Global status is provided by a scalar *OID* .1.3.6.1.4.1.674.10892.1.200.10.1.2.1. The service should be automatically detected if the server supports this *OID*.

For provisioning we have a requisition named *Server* which contains all server of our data center. A *Detector* with the name *Dell-OMSA-Global-State* for this requisition is created with the following parameter:

Table 102. Parameters for the SNMP detector

Paramete r	Value
Name	Dell-OMSA-Global-State

Paramete r	Value
oid	.1.3.6.1.4.1.674.10892.1.200.10.1.2.1

When the requisition *Server* is synchronized the service *Dell-OMSA-Global-State* will be detected in case they support the given *SNMP OID*.

Example using SNMP tables

We have a *HP* server farm and want to monitor the status of logical drives over *SNMP* provided from *HP Insight Manager*. The status for logical drives is provided in a *SNMP Table* under .1.3.6.1.4.1.232.3.2.3.1.1.4. The service should be automatically assigned to all servers exposing the given *SNMP OID*.

For provisioning we have a requisition named *Server* which contains all server of our data center. A *Detector* with the name *HP-Insight-Drive-Logical* for this requisition is created with the following parameter:

Table 103. Parameters for the SNMP detector

Paramete r	Value
Name	HP-Insight-Drive-Logical
oid	.1.3.6.1.4.1.232.3.2.3.1.1.4
isTable	true

When the requisition *Server* is synchronized the service *HP-Insight-Drive-Logical* will be detected in case they support the given *SNMP OID* table.

11.14.5. WS-Man Detector

The WS-Management detector attempts to connect to the agent defined in wsman-config.xml and issues an Identify command. If the Identify command is successful, the service is marked as detected and the product details returned by the command are optionally stored in the asset fields (see details bellow.)

Detector facts

Implementation org.opennms.netmgt.provision.detector.wsman.WsManDetector

Configuration and Usage

Table 104. Parameters for the <DETECTOR-NAME-HERE>

Paramet	Description	Requir	Default
er		ed	value
updateAss ets	Stores the product vendor and product version in the vendor and modelNumber asset fields	false	true

Examples

If a valid response to the Identify command is received, the product vendor and product version are stored in the vendor and modelNumber fields of the associated node`s assets table.

For example, a Windows Server 2008 machine returns:

Product Vendor	Microsoft Corporation
Product Version	OS: 6.1.7601 SP: 1.0 Stack: 2.0

If these assets field are being used for another purpose, this behavior can be disabled by settings the updateAssets parameters to false in the detector configuration of the appropriate foreign source.



Some agents may respond to the Identify command with generic identities such as Openwsman 2.0.0. These values can be overridden by specifying the product-vendor and product-version attributes in wsman-config.xml.

Example detector configuration:

The response is logged as *DEBUG* information in **provisiond.log** and looks like the following:

```
ID: 3
Response-Code: 200
309Encoding: UTF-8
Content-Type: application/soap+xml;charset=UTF-8
Headers: {Content-Length=[787], content-type=[application/soap+xml;charset=UTF-8],
Date=[Mon, 08 Feb 2016 14:21:20 GMT], Server=[Microsoft-HTTPAPI/2.0]}
Payload:
<s:Envelope xmlns:s="http://www.w3.org/2003/05/soap-envelope" xml:lang="en-US">
 <s:Header/>
 <s:Body>
    <wsmid:IdentifyResponse xmlns:wsmid=</pre>
"http://schemas.dmtf.org/wbem/wsman/identity/1/wsmanidentity.xsd">
    <wsmid:ProtocolVersion>
http://schemas.dmtf.org/wbem/wsman/1/wsman.xsd</wsmid:ProtocolVersion>
    <wsmid:ProductVendor>Microsoft Corporation</wsmid:ProductVendor>①
    <wsmid:ProductVersion>OS: 6.2.9200 SP: 0.0 Stack: 3.0</wsmid:ProductVersion>②
    <wsmid:SecurityProfiles>
<wsmid:SecurityProfileName>http://schemas.dmtf.org/wbem/wsman/1/wsman/secprofile/http/
basic</wsmid:SecurityProfileName>
<wsmid:SecurityProfileName>http://schemas.dmtf.org/wbem/wsman/1/wsman/secprofile/http/
spneqo-kerberos</wsmid:SecurityProfileName>
    </wsmid:SecurityProfiles>
    </wsmid:IdentifyResponse>
 </s:Body>
</s:Envelope>
```

① ProductVendor: Stored to the asset field vendor

② ProductVersion: Stored in the asset field modelNumber



The information of the asset fields are used in the *System Definition Rule* to decide which performance metrics will be gathered from *Collectd*.

11.14.6. WS-Man WQL Detector

The WS-Management WQL detector attempts to connect to the agent defined in wsman-config.xml and issues a WQL query. If the query successfully returns one or more items, the service is marked as detected. The WS-Man WQL detector can be used to define arbitrary services based on WQL filter results.

Detector facts

Implementation org.opennms.netmgt.provision.detector.wsman.WsManWQLDetector

Configuration and Usage

Table 105. Parameters for the <DETECTOR-NAME-HERE>

Parame ter	Description	Requi red	Default value
resource Uri	A resourceUri consists of a prefix and a path to a resource.	yes	<pre>http://schemas.microsoft.com/wbem/ wsman/1/wmi/root/cimv2/*</pre>
wql	A query using the WQL filter dialect	yes	none
serviceN ame	A custom service name to identify this service	no	WsManWQLService

Examples

Example detector configuration:

```
<detector name="WinRM" class=
"org.opennms.netmgt.provision.detector.wsman.WsManWQLDetector">
        <parameter key="resourceUri" value=
"http://schemas.microsoft.com/wbem/wsman/1/wmi/root/cimv2/*"/>
        <parameter key="serviceName" value="WinRM"/>
        <parameter key="wql" value="select Name,Status from Win32_Service where Name =
'WinRM' and StartMode='Auto' and Status = 'OK'"/>
    </detector>
```

The response is logged as *DEBUG* information in **provisiond**.log and looks like the following:

```
ID: 167
Response-Code: 200
Encoding: UTF-8
Content-Type: application/soap+xml;charset=UTF-8
Headers: {Content-Length=[975], content-type=[application/soap+xml;charset=UTF-8],
Date=[Thu, 02 Aug 2018 20:34:33 GMT], Server=[Microsoft-HTTPAPI/2.0]
Payload: <s:Envelope xmlns:s="http://www.w3.org/2003/05/soap-envelope" xmlns:a=</pre>
"http://schemas.xmlsoap.org/ws/2004/08/addressing" xmlns:n=
"http://schemas.xmlsoap.org/ws/2004/09/enumeration" xmlns:w=
"http://schemas.dmtf.org/wbem/wsman/1/wsman.xsd" xml:lang="en-US">
  <s:Header>
    <a:Action>
http://schemas.xmlsoap.org/ws/2004/09/enumeration/EnumerateResponse</a:Action>
    <a:MessageID>uuid:2298892C-575F-4722-82F6-C77F9E8B1A4F</a:MessageID>
    <a:To>http://schemas.xmlsoap.org/ws/2004/08/addressing/role/anonymous</a:To>
    <a:RelatesTo>urn:uuid:3c63e4d5-890c-4706-854b-876bf3b35b99</a:RelatesTo>
 </s:Header>
 <s:Body>
    <n:EnumerateResponse>
      <n:EnumerationContext/>
      <w:Items>
        <w:XmlFragment xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance" xmlns:w=</pre>
"http://schemas.dmtf.org/wbem/wsman/1/wsman.xsd" xmlns:m=
"http://schemas.microsoft.com/wbem/wsman/1/wsman.xsd">
          <Name>WinRM</Name>
          <Status>OK</Status>
        </w:XmlFragment>
      </w:Items>
      <w:EndOfSequence/>
    </n:EnumerateResponse>
 </s:Body>
</s:Envelope>
```

11.14.7. Reverse-DNS-Lookup Detector

This detector tries to detect if a given IP Address can be found in PTR records.

Detector facts

Implementation org.opennms.netmgt.provision.detector.rdns.ReverseDNSLookupDetector

Configuration and Usage

Parameters for the Reverse-DNS-Lookup Detector

Reverse DNS Lookup Detector doesn't take any parameters.


Examples

Reverse-DNS-Lookup Detector can be used in auto discovery with detectors to discover IP Addresses that only resolve FQDN.

Chapter 12. Business Service Monitoring

While *OpenNMS Meridian* detects issues in your network by device, interface or service, the *Business Service Monitoring (BSM)* takes it one step further. The *BSM* components allows you to monitor and model high level *Business Services (BS)* and helps quickly identify the most critical problems affecting these. With the *BSM* feature it is possible to model a high level *BS* context around the technical *Service Monitors* provided in *OpenNMS Meridian*. To indicate which *BS* is affected by events at the technical *Service Monitors* level, a BS *Operational Status* is calculated.

As an example, let's assume a company runs an online store. Customers enter through a login system, select items, place them in the shopping cart and checkout using a payment system. The whole service is provided by a few web servers and access data from databases. To monitor the status of the databases, a *SQL* service monitor on each database server is configured. For testing the web servers a *HTTP* service monitor is used for each of them. Covering the overall functionality a *Page Sequence Monitor (PSM)* is used to test the login, shop and payment workflow through the provided web portal. A possible representation of the whole system hierarchy is shown in figure Example scenario for a web shop.



To be able to model this scenarios the *BSM* functions can be used. The *Business Service Monitoring* (*BSM*) feature includes the following components:

- Business Service Monitoring Daemon (BSMD): Maintains and drives the state of all BS
- Business Service Editor: Web application which allows you to create, update or delete BS
- *Topology View for Business Services*: Visual representation of the *Business Service Hierarchy* as a component of the *Topology User Interface*.
- BSM ReST API: ReST based API to create, read, update or delete BS

12.1. Business Service Hierarchy

BS can depend on each other and build together a *Business Service Hierarchy*. It can be visualized using the *Topology User Interface* with the *Business Services View*. The *Operational Status* of a *BS* is ultimately calculated from *Alarms* and their *Severity*. To define the class of *Alarms* a *Reduction Key* is used and is represented as an *Edge* of a *BS*. Giving more granularity than just *Up* or *Down*, the *Operational Status* uses the *Severities*, i.e. *Normal, Warning, Minor, Major, Critical*.

Based on the hierarchy, the *Operational Status* is calculated with *Map* and *Reduce Functions*. A *Map Function* influences which *Severity* from the *Edge* is used as an input to the *BS*. A *Reduce Function* is used to consolidate the *Severities* from all *Edges* of a BS and uses them as inputs and reduces them into a single *Severity*, which is the *Operational Status*.

The Topology User Interface allows users to traverse Business Service Hierarchies using the Semantic Zoom Level (SZL). The Semantic Zoom Level (SZL, pronounced as 'sizzle') defines how many Neighbors are shown related to the elements which are in Focus. The number can be interpreted as how many Hops from the Focus should be shown on the Topology User Interface.




Figure 35. Business Service Hierarchy components

- (1) A top-level *Business Service* which depends on other *Business Services, Monitored Services* and *Alarms* (referenced by *Reduction Key*)
- ② Business Service as child an the Operational Status is used as input for the top-level Business Service
- ③ *IP Service Edge* used as an input with auto generated *Reduction Keys* for node down, interface down and node lost service
- ④ *Reduction Key Edge* used as an input to the top-level *BS*, which references just a node lost service of a *Page Sequence Monitor* for the user login

To add or remove an additional selected *BS* or *Edge* to *Focus* use in the context menu *Add To Focus* or *Remove From Focus. If you want to have a specific _BS* or *Edge* as a single focus use *Set as Focal*

Point. The *Eye* icon highlights all elements in the *Topology UI* which are set to *Focus*.

12.2. Operational status

Every *Business Service* maintains an *Operational Status* that represents the overall status calculated by the *Map and Reduce Functions* from the *Edges*. The *Operational Status* uses the *Severities* known from *Events* and *Alarms*.

Name	Numerica l code	Color / Code	Description
Critical	7	Purple / #c00	This event means that a severe service affecting event has occurred.
Major	6	Red / #f30	Indicates serious disruption or malfunction of a service or system.
Minor	5	Orange / #f90	Used for troubles that have not immediate effect on service or system performance.
Warning	4	Yellow/ #fc0	An event has occurred that may require action. This severity can also be used to indicate a condition that should be noted (logged) but does not require immediate action.
Normal	3	Dark green / #360	Informational message. No action required.
Cleared	2	Grey / <mark>#eee</mark>	This severity is reserved for use in alarms to indicate that an alarm describes a self-clearing error condition has been corrected and service is restored. This severity should never be used in event definitions. Please use "Normal" severity for events that clear an alarm.
Indetermi nate	1	Light green / #990	No Severity could be associated with this event.

Table 106. Operational Status representation

If a *Business Service* changes its *Operational Status* an *OpenNMS* event of the type uei.opennms.org/bsm/serviceOperationalStatusChanged is generated and sent to the *OpenNMS Event Bus.* In case the *Operational Status* changed from *Normal* to a higher *Severity* an *Event* of the type uei.opennms.org/bsm/serviceProblem is generated and has the *Severity* of the *BS.* When the *BS* goes back to normal a *Event* of the type uei.opennms.org/bsm/serviceProblemResolved is generated.



The *Service Problem* and *Service Problem Resolved* events can be used for notifications or ticketing integration.

The log message of the events have the following information:

- Business Service Name: businessServiceName
- Business Service Identifier: id

- Previous Severity Identifier: prevSeverityId
- Previous Severity Label: prevSeverityLabel
- New Severity Identifier: newSeverityId
- New Severity Label: newSeverityLabel


B

The BSM events are not associated to a Node, Interface or Service.

12.3. Root Cause and Impact Analysis

The *Root Cause* operation can be used to quickly identify the underlying *Reduction Keys* as *Edges* that contribute to the current *Operational Status* of an element. The *Impact Analysis* operation, converse to the *Root Cause* operation, can be used to identify all of the *BS* affected by a given element. Both of these options are available in the context menu of the *Topology User Interface* when visualizing *BS*.

The following example shows how to identify the *Root Cause* of the critical status of the *Shop* service. Use the *Context Menu* on the *BS* to investigate the *Root Cause* shown in figure View before performing Root Cause Analysis.



View before performing Root Cause Analysis


The *Topology UI* sets only elements to *Focus* which are the reason for the *Operational Status* of the selected *BS*. In figure View after performing Root Cause Analysis the *Page Sequence Monitor* which tests the user login is down and has set the *BS* to a critical status.

View after performing Root Cause Analysis

view Device Simulate (# Snare		1
Search	Lastupda	te time: Fri Apr 29 2016 01:24 AM
Bsm: nodeLostService:34 1 ×		(+)
Bsm: Shop 🖌 🗙		40
A Simulation Mode Enabled		
	.	٩
BSM Topology Provider		
This Topology Provider displays the hierarchy of the defined Business Services and their computed operational		
states.		
Selection Context		
Provider: bsm Vertices Edges	Shop	
Focus 2 0 Selection 0 0	Siop	
Context 2 1		Q
Total 28 27		+
		 ▲ ● ●
	PSM Shop	


Similar to identifying a root cause for a *BS* it is also possible to identfy which *Business Services* from a specific *Edge* are affected. Use the *Context Menu* on a specific *Edge* element and select *Impact Analysis* shown in figure View before performing Impact Analysis.

View before performing Impact Analysis



In figure View after performing Impact Analysis the *Business Services* for *Login, Shop* and *Payment* are affected if this *HTTP* service is unavailable.

View after performing Impact Analysis



12.4. Simulation Mode

To visualize if the configured behavior works as expected, the *Simulation Mode* can be used to manually set an *Alarm* status of an *Edge* element. The *Operational Status* is calculated with the given *Map and Reduce Functions*. This allows users to validate and tune their *Business Service Hierarchies* until the desired status propagation is achieved.

In order to enter *Simulation Mode*, open the *Business Service View* in the *Topology User Interface* and toggle the *Simulation Mode* option in the *Simulate* menu at the top of the screen. The *Info Panel* on the left hand side allows to set the *Severity* of the selected *Edge* element. In figure BSM Simulation Mode the *Menu* and *Severity* setting is shown.

BSM Simulation Mode

View	Device	Simulate	🔿 Share					
0	- 1-	Simulat	tion Mode			-		
	Login - HTTP -	Reset S			•			
Bsm: Bsm:	Payment nodeLos	ver 7 × t test 7 × ttService:HT Mode Enabl						
Simul Sever		inor	٥					
A		The <i>Info I</i>	<i>Panel</i> can be	e hidden with th	ne Arrow	button in	the top left	corner

In the *Simulate* menu there are *Inherite State* and *Reset State* as options available. With *Inherite State* the current *Severities* and *Operational Status* from monitoring is used for the *Simulation Mode*. By selecting *Reset State* all states will be set to *Normal* for simulation.

12.5. Share View

In some cases it is useful to share a specific view on a *Business Service Hierarchy*. For this reason the menu function *Share* can be used and generates a link for the current view and can be copied and sent to another user. In figure <u>Share Business Service View</u> the *Share* menu item was used and a link is generated. The link can be used with *Copy & Paste* and sent to another user to have access to exactly the same configured _Business Service View.

View Device Simulate 🏞 Share	
Search	· <u>4</u>
Bsm: Login ≁ × Bsm: HTTP ≁ ×	
Bsm: Web Server <table-cell-columns> 🛪</table-cell-columns>	
Bsm: Payment test 🛛 🛪	
Bsm: nodeLostService:HTTP / X	
	Login Payment
Simulation Mode Enabled	4
Simulate	
Severity* Minor	
Reduction Key Details	
Reduction Key uei.opennms.org/nodes/nodeLostService::28	WebServer
Friendly Name nodeLostService:HTTP	Share Link ×
Technical Details	Please use the following link to share the current view with others.
Name nodeLostService:HTTP	r lease use the following link to anale the content view with others.
ID bsm:ReductionKey:uei.opennms.org/nodes/nodeLe	http://localhost:8980/openms/topology?ui-fragment=(0),
Icon Key bsm.reduction-key	(-301,50,902,400),(150,0,250,0),(1CE0D6A4),(D0727DB2), (9EC3DB63),(E20C61A6)
	Close

Share Business Service View



12.6. Change Icons

Each element in the *Business Service View* has an icon which is assigned to a *BS* or an *Edge*. To be able to customize the *Business Service View* the icons for each element can be changed. Select the element in the *Business Service View* and choose *Change Icon* from the *Context Menu*. As shown in figure Change Icon for Business Service or Edges select the the new icon for the selected element and click *Ok* to permanently assign the new icon to the element.

View Device Structule r≠Share Search Bern: Login r≠ x Bern: Web Server r≠ x Bern: Yebs Server r≠ x Bern: rodeLostServiceHTTP r≠ x	4				Login	Payment tes	Last update time: Fri Apr 29 2016 02:51 AM
Simulate Severty* Minor Reduction Key Details		Change Icon	‡ ‡	Ē	• • •	<u>(6)</u>	Ť
Reduction Kay as common any horder-hordel.cot/Service -28 Friendy Name nodeLostService.HTTP Technical Details Name nodeLostService.HTTP ID bern:ReductorKay.uei.opennes.org/nodes/nodeLo toon Kay bern mutuction.kay				•			¢
				- © -			
Alarma Business Services Nodes						Ok Cancel	Select Al Deselect Al Acknowledge 🔒 Submit
ID * Severity	Node						Log Message 🕞

Change Icon for Business Service or Edges

It is also possible create custom *Icon Sets* which is described in the *Business Service Monitoring* section of the *Developer Guide*.

12.7. Business Service Definition

The status of *Service Monitors* and any kind of *Alarm* can be used to drive the *Operational Status* of a *BS*. A *BS* is defined with the following components:

- Business Service Name: A unique name used to identify the BS
- *Edges*: A set of elements on which this *BS* relies which can include other *BS*, or *Reduction Keys*.
- *Reduce Function*: Function used to aggregate the *Operational Status* from all the *Edges*. Specific functions may take additional parameters.
- *Attributes*: Optional key/value pairs that can be used to tag or enrich the *Busines Service* with additional information.

Each *Business Service* can contain a list of optional key/value attributes. These can be used to identify or tag the *BS*, and may be reference in other workflows. These attributes do not affect the

dependencies or the status calculation of the BS.

Attributes can be used to filter BS in Ops Board dashlets.

The Business Service Editor is used to manage and model the Business Services and their hierarchy. It is required to have administrative permissions and is available in "Login Name \rightarrow Configure OpenNMS \rightarrow Manage Business Services" in the Service Monitoring section.

Managing Business Services with the Business Service Editor

New Business Service	2 Refres	h Table 13 Reload Daemo
ME	LINKS	EDIT / DELETE
Login	View in Topology UI 7	🕼 Edit 🗎 🗎 Delete
web Server ⁶	View in Topology UI	Edit Delete
Database	View in Topology UI	🕼 Edit 🗎 💼 Delete
Payment	View in Topology UI	C Edit 🗎 Delete
▼Web Server	View in Topology UI	C Edit 🗎 Delete
Database	View in Topology UI	C Edit 🗊 Delete
Shop	View in Topology UI	🕼 Edit 🗎 💼 Delete

- ① Create a new *Business Service* definition
- 2 Collapse tree view for all *Business Services* in the view
- ③ Expand tree view for all Business Services in the view
- ④ Reload all Business Services in the view with current Business Services from the system
- (5) Reload the *Business Service Monitoring Daemon* to use the *Business Service* definition as configured
- 6 Business Service dependency hierarchy as tree view
- ⑦ Show the current Business Service with dependencies in the Topology UI
- 8 Edit and delete existing Business Service defintions

As shown in figure Managing Business Services with the Business Service Editor the Business Services can be created or changed. The hierarchy is created by assigning an existing Business Service as Child Service.

12.8. Edges

Edges map the Alarm status monitoring with OpenNMS

The following types can be used:

- Child Service: A reference to an existing Business Service on which to depend
- *IP Service*: A convenient way to refer to the alarms that can be generated by a monitored *IP Service*. This will automatically provided edges for the *nodeLostService*, *interfaceDown* and *nodeDown* reductions keys of the specified service.
- *Reduction Key*: A resolved *Reduction Key* used to refer to a specific *Alarm*, e.g. generated by a *SNMP Trap* or *Threshold* violation
- *Application*: A reference to an existing application. This will automatically provide edges for the *nodeLostService, interfaceDown* and *nodeDown* reductions keys of the defined services of this application.



If you need help determining the reduction key used by alarm, trigger the alarm in question and pull the reduction key from the *Alarm* details page.

All edge types have the following parameters:

- Map Function: The associated Map Function for this Edge
- Weight: The relative Weight of this edge. Used by certain Reduce Functions.

Both *IP Service* and *Reduction Key* type edges also support a *Friendly Name* parameter which gives the user control on how the edge is labeled in the *Topology User Interface*. The editor changing the *Edge* attributes is shown in figure Editor to add Business Service Edges.

Editor to add Business Service Edges

Business Servic	e Edge Edit		
Type *	✓ Child Service IP Service Reduction Key		S
Map Function*	Identity		0
Severity			
Weight*	1		
		Add Edge	Cancel
		Add Edge	Cancel

12.8.1. Child Services

To create a hierarchy of *Business Services* they need to be created first. The hierarchy is build by selecting the *Business Service* as_Child Service_ as dependency.

12.8.2. IP Services

The *IP Service* is a predefined set of *Reduction Keys* which allows easily to assign a specific *Monitored Service* to the given *BS*. As an example you have multiple Servers with a *Monitored Service SMTP* and you want to model a *BS* named *Mail Communication*. If just the *Reduction Key* for a *nodeLostService* is assgined, the *BS* would not be affected in case the *IP Interface* or the whole *Node* goes down. *OpenNMS* generates *Alarms* with different *UEI* which needs to be assigned to the *BS* as well. To make it easier to model this use case the *IP Service* generates the following *Reduction*

Keys automatically:

- uei.opennms.org/nodes/nodeLostService:%nodeId%:%ipAddress%:%serviceName%: Matches *Alarms* when the given *Monitored Service* goes down
- uei.opennms.org/nodes/interfaceDown:%nodeId%:%ipAddress%: Matches *Alarms* when the given *IP Interface* of the *Monitored Service* goes down
- uei.opennms.org/nodes/nodeDown:%nodeId%: Matches *Alarms* when the given *Node* of the *Monitored Service* goes down

12.8.3. Custom Reduction Key

The *Reduction Key* edge is used to refer to specific instance of alarms. When an alarm with the given *Reduction Key* is present, the alarms' severity will be used to calculate the *Operational Status* of the *BS*. To give a better explanation a *Friendly Name* can be set and is used in the *Business Service View*. The format of the *Reduction Key* is build by a set of attributes as a key separated by : and enclosed in %, i.e (%attribute%:%attribute%).

Example of a Reduction Key for a specific nodeLostService

%uei.opennms.org/nodes/nodeLostService%:%nodeId%:%ipAddress%:%serviceName%

12.8.4. Application

Already defined *Applications* can be used in *Business Service* topologies. An *Application* itself defines a set of *Monitored Services* - each of these generate *nodeLostService*, *interfaceDown* and *nodeDown* reduction keys automatically.

12.9. Map Functions

The *Map Functions* define how the *Severity* of the edge will be used in the *Reduce Function* of the parent when calculating the *Operational Status*.

The available *Map Functions* are:

Name	Description
Identity	Use the same Severity as Operational Status of the BS
Increase	Increase the Severity by one level and use it as Operational Status of the BS
Decrease	Decrease the Severity by one level and use it as Operational Status of the BS
SetTo	Set the Operational Status to a constant Severity value
Ignore	The input of the <i>Edge</i> is ignored for <i>Operational Status</i> calculation

Table 107. Calculation of the Operational Status with Map Functions

12.10. Reduce Functions

A *Reduce Function* is used to aggregate the *Operational Status* for the *BS*. The *Alarm Severity* from the *Edges* are used as input for the *Reduce Function*. For this operation the following *Reduce Functions* are available:

Table 108. Status	calculation	<i>Reduce Functions</i>
100001000000000000000000000000000000000	000000000000000000000000000000000000000	

Name	Description
Highest Severity	Uses the value of the highest severity, <i>Weight</i> is ignored.
Threshold	Uses the highest severity found more often than the given threshold, e.g. 0.26 can also be seen as 26%, which means at least 2 of 4 <i>Alarms</i> need to be raised to change the <i>BS</i> .
Highest Severity Above	Uses the highest severity greater than the given threshold severity.

Name	Description
Exponential Propagation	This reduce function computes the sum of the given child severities based on a base number. For this computation the severities are mapped to numbers:
	WARNING=0, MINOR=1, MAJOR=2, CRITICAL=3
	All other severities are ignored.
	For the aggregation the following formula will be used to compute the resulting Business Service severity from its <i>n</i> child entities based on the base number <i>b</i> :
	<pre>severity = log_{b}(sum_(i=1)^n b^(ch\ildSeverity_{i})) </pre>
	In summary the base value defines how many items of a severity <i>x</i> will result in a severity <i>x</i> +1. Results lower as 0 are treated as <i>NORMAL</i> and results higher than 3 are treated as <i>CRITICAL</i> . If all input values are of severity <i>INDETERMINATE</i> , the result is <i>INDETERMINATE</i> .
	For example if the Business Service depends on four child entities with the severities <i>WARNING</i> , <i>WARNING</i> , <i>NORMAL</i> and <i>NORMAL</i> and the base defined by the number 2 the following computation will be made:
	severity = log_{2}(2^{0} + 2^{0} + 0 + 0) = log_{2}(1 + 1 + 0 + 0) = log_{2}(2) = 1_ = 1
	which corresponds to the severity <i>MINOR</i> . The same computation with the base value of 3 results in:
	severity = log_{3}(3^{0} + 3^{0} + 0 + 0) = log_{3}(1 + 1 + 0 + 0) = log_{3}(2) = 0.63 = 0
	which means WARNING.

The following table shows the status calculation with *Edges* assigned to an *IP Service*. The *IP-Service* is driven by the monitoring of the *ICMP* service for three Web Server. In the table below you find a configuration where *Web Server 3* is weighted 3 times higher than the other and a threshold of 0.33 (33%) is configured.

Name	Weig	Weight	Input	Operational	Critic	Majo	Mino	Warni	Norm
	ht	Factor	Severity	Status	al	r	r	ng	al
Web- ICMP-1	1	0.2	Critical	Critical	0.2	0.2	0.2	0.2	0.2

Table 109. Example for status calculation using the Threshold function

Name	Weig ht	Weight Factor	Input Severity	Operational Status	Critic al	Majo r	Mino r	Warni ng	Norm al
Web- ICMP-2	1	0.2	Normal	Normal	0	0	0	0	0.2
Web- ICMP-3	3	0.6	Warning	Warning	0	0	0	0.6	0.6
Total		1.0			0.2	0.2	0.2	0.8	1
Percentag e		100%			20%	20%	20%	80%	100%

The *Operational Status Severity* is evaluated from left to right, the first value higher then the configured *Threshold* is used. In this case the *Operational Status* is set to *Warning* because the first threshold which exceeds 33% is *Warning* with 80%.

12.11. Business Service Daemon

The calculation of the *Operational Status* of the *BS* is driven by the *Business Service Monitoring Daemon* (bsmd). The daemon is responsible for tracking the operational status of all *BS* and for sending events in case of operational status changes.

In order to calculate the *Operational Status* the *reduction key* associated with a *Business Service* is used. The *reduction key* is obtained from an alarm generated by *OpenNMS Meridian*. This means that the alarm's *reduction key* of a defined *Business Service* must not change afterwards. Otherwise *bsmd* is not able to calculate the *Operational Status* correctly. This also applies for removing the *alarm data* from events associated to *Business Services* In addition the child type "IP Service" from the *Business Service Configuration Page* requires the following events with the default reduction keys being defined: * uei.opennms.org/nodes/nodeLostService * uei.opennms.org/nodes/nodeDown * uei.opennms.org/nodes/interfaceDown

Every time the configuration of a *Business Service* is changed a reload of the daemon's configuration is required. This includes changes like the name of the *Business Service* or its attributes as well as changes regarding the *Reduction Keys*, contained *Business Services* or *IP Services*. The *bsmd* configuration can be reloaded with the following mechanisms:

- Click the Reload Daemon button in the Business Service Editor
- Send the *reloadDaemonConfig* event using send-event.pl or use the WebUI in *Manually Send an Event* with parameter daemonName bsmd
- Use the ReST API to perform a POST request to /opennms/api/v2/business-services/daemon/reload

If the reload of the configuration is done an event of type uei.opennms.org/internal/reloadDaemonConfigSuccessful is fired.

\$OPENNMS_HOME/bin/send-event.pl -p 'daemonName bsmd'
uei.opennms.org/internal/reloadDaemonConfig

Example reloading bsmd configuration through ReST POST

```
curl -X POST -u admin:admin -v http://localhost:8980/opennms/api/v2/business-
services/daemon/reload
```

Chapter 13. Topology Map

This section describes how to configure the Topology Map.

13.1. Properties

The *Topology Map* supports the following properties, which can be influenced by changing the file etc/org.opennms.features.topology.app.cfg:

Property	Туре	Default	Description
showHeader	Boole an	true	Defines if the OpenNMS Meridian header is shown.
autoRefresh.e nabled	Boole an	false	If enabled, auto refresh is enabled by default.
autoRefresh.i nterval	Integ er	60	Defines the auto refresh interval in seconds.
hiddenCategor yPrefix	Strin g	empty String	A String which allows hiding categories. For example a value of server will hide all categories starting with server. Be aware, that this setting is case-sensistive, so Servers will be shown. The resolution is only enabled if no longitude/latitude information is available.

13.2. Edge Status

The choice of topology provider controls the status and color of an edge, or link between two vertices. Each topology provider has different notions of what an edge represents and may provide different controls for managing the behavior.

13.2.1. Linkd Topology Provider

The Linkd Topology Provider uses the state and existence of alarms to determine the color of the edge. An edge between two vertices on a topology map represents a link that has been discovered between two interfaces on distinct nodes. If an alarm is present with a UEI uei.opennms.org/internal/topology/linkDown, and the alarm is associated with either of the interfaces on either node, then the edge is red. If no such alarm is present, the edge is green.

These alarms are not generated by default. Enable them by changing the logmsg property on the uei.opennms.org/internal/topology/linkDown and uei.opennms.org/internal/topology/linkUp events from donotpersist to logndisplay. These events are automatically generated by the default set of event translator rules that process incoming SNMP Link Up & Down traps.

13.3. Icons

Each Vertex on the *Topology Map* is represented by an icon. The default icon is configured in the icon mapping file: \${OPENNMS_HOME}/etc/org.opennms.features.topology.app.icons.<topology-</pre>

namespace>.cfg. If an icon mapping file does not exist for a *Topology Provider*, the provider does not support customization.

List of available icon mapping files (may not be complete)

```
org.opennms.features.topology.app.icons.default.cfg ①
org.opennms.features.topology.app.icons.application.cfg ②
org.opennms.features.topology.app.icons.bsm.cfg ③
org.opennms.features.topology.app.icons.linkd.cfg ④
org.opennms.features.topology.app.icons.vmware.cfg ⑤
```

1 Default icon mapping

2 Icon mapping for the Application Topology Provider

③ Icon mapping for the Business Services Topology Provider

④ Icon mapping for the Linkd Topology Provider

⁽⁵⁾ Icon mapping for the Vmware Topology Provider

Each File contains a mapping in form of <icon key> = <icon id>.

Icon key

A Topology Provider dependent string which maps to an icon id. An icon key consists of one to multiple segments. Each segment must contain only numbers or characters. If multiple segments exist they must be separated by ., e.g. my.custom.key. Any existing default icon keys are not configurable and should not be changed.

Icon id

The icon id is a unique icon identifier to reference an icon within one of the available SVG icons located in {{OPENNMS_HOME}/jetty-webapps/opennms/svg. For more details see Add new icons.

Icon key and icon id specification using BNF

```
icon key ::= segment["."segment]*
segment ::= text+ [( "-" | "_" | ":" ) text]*
text ::== (char | number)+
char ::== A | B | ... | Z | a | b | ... | z
number ::= 0 | 1 | 2 | 3 | 4 | 5 | 6 | 7 | 8 | 9
icon id ::= segment
```

Example icon mapping file

```
# Business Service Topology
bsm.business-service = business_service ①
bsm.ip-service = IP_service ②
bsm.reduction-key = reduction_key ③
```

1 Icon definition for Business Services

② Icon definition for IP Services

③ Icon definition for Reduction Keys

13.3.1. Icon resolution

The icon of a vertex is resolved as follows:

- If a vertex id to icon id mapping is defined, the icon referenced by the icon id is used
- If a mapping for the icon key determined by the *Topology Provider* for the vertex is defined, the icon referenced by the icon id is used
 - If no mapping exists and the icon key has more than one segments, reduce the icon key by the last segment and try resolving that icon key
- If no mapping is defined, the fallback icon key default is used.

The following example icon mapping is defined for the *Linkd Topology Provider* to illustrate this behaviour.

linkd.system.snmp.1.3.6.1.4.1.9.1.485 = server1
linkd.system.snmp.1.3.6 = server2

If the Enterprise OID of a node is 1.3.6.1.4.1.9.1.485 the icon with id server1 is used. If the Enterprise OID of a node is 1.3.6 the icon with id server2 is used. However, if the Enterprise OID of a node is 1.3.6.1.4.1.9.1.13 the icon with id server2 is used.

Linkd Topology Provider

The *Linkd Topology Provider* uses the Enterprise OID from each node to determine the icon of a vertex.

13.3.2. Change existing icon mappings

The easiest way to change an icon representation of an existing Vertex is to use the *Icon Selection Dialog* from the Vertex' context menu in the *Topology Map*. This will create a custom icon key to icon id mapping in the *Topology Provider* specific icon mapping file. As icon key the Vertex id is used. This allows each Vertex to have it's own icon.

If a more generic approach is preferred the icon mapping file can be modified manually.



Do NOT remove the default mappings and do NOT change the icon keys in the default mappings.

13.3.3. Add new icons

All available icons are stored in SVG files located in *\${OPENNMS_HOME}/jetty-webapps/opennms/svg*. To add new icons, either add definitions to an existing SVG file or create a new SVG file in that directory.

Whatever way new icons are added to OpenNMS it is important that each new icon id describes a

set of icons, rather than a single icon. The following example illustrates this.

Example SVG file with a custom icon with id my-custom

```
<?xml version="1.0" encoding="utf-8"?>
<!DOCTYPE svg PUBLIC "-//W3C//DTD SVG 1.1//EN"
"http://www.w3.org/Graphics/SVG/1.1/DTD/svg11.dtd">
<svg id="icons" xmlns="http://www.w3.org/2000/svg">
 <g id="my-custom_icon"> ①
     <g id="my-custom_active"> ②
          <!-- rect, path, circle, etc elements, supported by SVG -->
     </q>
     <q id="my-custom rollover"> ③
         <!-- rect, path, circle, etc elements, supported by SVG -->
     </q>
     <g id="my-custom"> ④
         <!-- rect, path, circle, etc elements, supported by SVG -->
     </g>
 </q>
 <!-- Additional groups ... -->
</svg>
```

① Each icon must be in a SVG group with the id <icon id>_icon. Each SVG <icon id>_icon group must contain three sub groups with the ids: <icon id>_active, <icon id>_rollover and <icon id>.

② The icon to use when the Vertex is selected.

- ③ The icon to use when the Vertex is moused over.
- ④ The icon to use when the Vertex is not selected or not moused over (just visible).



It is important that each icon id is unique overall SVG files. This means there cannot be another my-custom icon id in any other SVG file.

If the new icons should be selectable from the *Topology Map's Icon Selection Dialog* an entry with the new icon id must be added to the file \${OPENNMS_HOME}/etc/org.opennms.features.topology.app.icons.properties.

Snippet of org.opennms.features.topology.app.icons.list

```
access_gateway ①
accesspoint
cloud
fileserver
linux_file_server
opennms_server
printer
router
workgroup_switch
my-custom ②
```

1 Already existing icon ids

2 New icon id



The order of the entries in org.opennms.features.topology.app.icons.list determine the order in the *Icon Selection Dialog* in the *Topology Map*.

Chapter 14. Asset Topology Provider

14.1. Overview

OpenNMS Meridian has introduced the ability for users to define arbitrarily complex layered topologies using GraphML (see http://graphml.graphdrawing.org/). The details of how *OpenNMS Meridian* interprets GraphML are given in the GraphML section of the *OpenNMS Meridian* developers guide. The ability to display complex layered topologies is a great feature but creating a usable GraphML topology for a large network can be a complex task for a user.


The *Asset Topology Provider* avoids the need for users to work directly with GraphML by directly generating a layered GraphML topology based upon node parameters and the contents of the Node Asset table. The *Asset Topology Provider* greatly simplifies the task for many use cases by allowing users to define fields in the Node Asset table which will enable nodes to be positioned correctly in a complex topology. This allows a physical and logical ordering of nodes which makes it easier for users to represent and navigate their infrastructure.

The structure of the generated topology is determined by the assetLayers configuration constant which can be set by a user. To illustrate how this works, we will consider the following configuration:

assetLayers=asset-region,asset-building

The *OpenNMS Meridian* Asset table is parsed to generate nested layers in the order of the comma separated keys in the assetLayers property. Each layer is a graph which is named after the key. Graph nodes in each layer reference related Graph nodes in the underlying layer. The lowest layer contains Graph nodes which are directly linked to monitored *OpenNMS Meridian* nodes which have entries in the Asset table.

The following diagram shows the structure of a topology generated by the above assetLayers property




In this example the **region** asset fields for node 1,2,3,4 are set to north. All of these nodes are in the same north region. The **building** asset fields for Node 1 and Node 2 are set to 21 (both nodes are in building 21) while the **building** asset fields for Node 3 and Node 4 are set to 22 (both nodes are in building 22).


The Asset Topology Provider generates four linked graphs for this configuration. The layer 0 graph is called asset-region, the layer 1 graph is called asset-building and the layer 2 graph is called nodes.

Conceptually we can see that the topology is rendered as concentric sets. The *Asset Topology Provider* first searches all of the nodes with regions defined and creates a new level 0 graph node representing each region found. The *Asset Topology Provider* then searches within each region to find the building entries and creates a corresponding level 1 graph node for each building name found. Finally the *Asset Topology Provider* creates layer 2 nodes corresponding to each *OpenNMS Meridian* monitored node and places each in the correct building.

If however *OpenNMS Meridian* monitored nodes are found which have either the region or building asset fields empty they cannot be placed correctly in this topology. These nodes as shown in the diagram as unallocated nodes. Finally, only building and region nodes are generated which can be linked to *OpenNMS Meridian* nodes in the topology. The *Asset Topology Provider* does not generate spurious graph nodes in upper layers which are not directly and completely referenced by *OpenNMS Meridian* nodes in the lowest layer.

Example screenshots of a topology containing regions, buildings, racks and nodes are shown below





14.2. Asset layers

The entries for assetLayers can be any node or asset entry from the following list (defined in class NodeParamLabels). Keys beginning with node- come from the node table. Keys beginning with parent- come from the node table entry of the designated parent node (If defined). Keys beginning with asset- come from the corresponding asset table entry for the given node (If defined).

node-nodelabel	node-nodeid	node-foreignsource	node-foreignid	node- nodesysname
node- nodesyslocation	node- operatingsystem	node-categories		

parent-nodelabel	parent-nodeid	parent- foreignsource	parent-foreignid	
asset-address1	asset-address2	asset-city	asset-zip	asset-state
asset-latitude	asset-longitude	asset-region	asset-division	asset- department
asset-building	asset-floor	asset-room	asset-rack	asset-slot
asset-port	asset-circuitid	asset-category	asset-displaycategory	asset- notifycategory
asset- pollercategory	asset- thresholdcategory	asset- managedobjecttype	asset- managedobjectinstanc e	asset- manufacturer
asset-vendor	asset- modelnumber	asset-description	asset-operatingsystem	asset-country

This allows arbitrary topologies to be generated including physical fields (room, rack etc.) and logical fields such as asset node categories. Please note you should not put any spaces in the comma separated assetLayers list. If the assetLayers property is defined as empty then a single graph layer will be generated containing all opennms nodes.

14.3. Node filtering

In many cases it is desirable to control which nodes are included or excluded from a topology. For instance it is useful to be able to generate customised topologies for specific customers which include only regions/buildings etc relevant to their filtered node set. To this end it is possible to define a node filter which chooses which nodes are included in a generated topology.

Filters are defined using the same asset table keys which are available for the assetLayers field.

Operatio n	Definition	Example
OR	key1=value1,value2 alternatively key1=value1;key1=value2	asset-region=north,south
AND	key1=val1;key2=val2	asset-region=north;asset- building=23
NOT	key1=!val1	asset-building=!23

Thus the following configuration means include only nodes with region north or south but exclude all nodes with building 23.

filter=asset-region=north,south;asset-building=!23

The filters are designed to treat all selected text key entries as comma separated values (csv). This allows OpenNMS node-categories which are many to many entries to be dealt with as a comma separated list of values; routers, servers, web etc. Thus we can select based on multiple separate node categories. The following configuration means show routers and servers on all buildings except building 23.

filter=node-categories=routers,servers;asset-building=!23

The filters treat all asset table entries as comma separated variables (csv). This also means that, for instance asset-displaycategory could also contain several values separated by commas. e.g. customer1,customer2,customer3 etc.



You should make sure asset addresses and other free format asset text fields do not contain commas if you want an exact match on the whole field

Regular expressions are also allowed. Regular expressions start with the ~ character. You can also negate a regular expression by preceding it with !~.

The following example will match against regions 'Stuttgart' and 'Isengard' and any building name which ends in 4

```
filter=asset-region=~.*gar(t|d);asset-building=~.*4
```

14.4. Configuration

The *Asset Topology Provider* persists both the asset topology graph definitions and the generated GraphML graphs. The persisted definitions mean that is is possible to regenerate graphs if the asset table is changed without reentering the configuration.

The *Asset Topology Provider* persists GraphML graphs along side any other GraphML graphs in the directory;

<opennms home>/etc/graphml

Please note that if you are using ReST or any other means to generate other GraphML graphs, you should ensure that the providerIds and labels are distinct from those used by the *Asset Topology Provider*

The asset graph definitions for the Asset Topology Provider are persisted to the following xml configuration file:

```
<opennms home>/etc/org.opennms.features.topology.plugins.topo.asset.xml
```

Normally you should not edit this file directly but use the karaf consol or events to define new

graphs.

The config file will contain each of the graph definitions as properties in the form

```
<?xml version="1.0" encoding="UTF-8" standalone="yes"?>
<configs>
    <config>
        <label>Asset Topology Provider</label>
        <breadcrumb-strategy>SHORTEST_PATH_TO_ROOT</breadcrumb-strategy>
        <provider-id>asset</provider-id>
        <preferred-layout>Grid Layout</preferred-layout>
        <filters>
            <filter>asset-region=South</filter>
        </filters>
        <layers>
            <layer>asset-region</layer>
            <layer>asset-building</layer>
            <layer>asset-rack</layer>
        </layers>
    </config>
</configs>
```

The individual definition parameters are described in the following table

Parameter	Description	
providerId	The unique name of the provider - used as handle to install and remove the topology	
label	The name which shows up on the topology menu (must be unique)	
assetLayers	List of asset layers (in order). See separate description.	
filters	List of filters to be applied. Filters determine which nodes are included in graph. See separate description.	
preferredLayout	Preferred layout of the nodes in generated graphs.	
breadcrumbStrat egy	Breadcrumb strategy used to display breadcrumbs above each graph	

14.5. Creating Asset Based Topologies From Karaf Consol

The *OpenNMS Meridian* Karaf Consol can be used to control topology generation. To login use admin password.

ssh admin@localhost -p 8101

Command	Description	Options
opennms:asset -topo-create	Creates Asset Topology.	(The default settings are used if a particular setting is not included in the command)
		-l,label : Asset Topology label (shows in topology menu) (Default: asset)
		-i,providerId : Unique providerId of asset topology (Default: 'Asset Topology Provider')
		-f,filter : Optional node filter (Default: empty filter i.e. allow all nodes)
		-a,assetLayers : Comma separated list of asset layers (Default: asset- region,asset-building,asset-rack)
		-p,preferredLayout : Preferred Layout (Default: 'Grid Layout')
		-b,breadcrumbStrategy : Bread Crumb Strategy (Default: SHORTEST_PATH_TO_ROOT)
		If you simply type asset-topology:create a default topology with providerId asset will be created.
opennms:asset -topo-remove	Removes Asset Topology.	-i,providerId : Unique providerId of asset topology (Default: asset)
opennms:asset -topo-list	Lists all Asset Topologies installed.	all : display detailed view including uriParams string
opennms:asset -topo -regenerate	Regenerates the graphs for the given Asset Topology definition.	-i,providerId : Unique providerId of asset topology to regenerate (Default: asset)
opennms:asset -topo -regenerateall	Best Effort regeneration of all asset topologies. (If one graph fails, the command will try to complete the rest of the definitions definition)	

14.6. Creating Asset Based Topologies Using *OpenNMS Meridian* **events**

The *Asset Topology Provider* listens for events which trigger the generation and installation or removal of topologies. The *Asset Topology Provider* events are defined in the file

```
<opennms home>/etc/events/GraphMLAssetPluginEvents.xml
```

These events will use the default parameters if parameters are not supplied

To create a new topology from the current OpenNMS inventory use

```
(for default topology)
sudo ./send-event.pl uei.opennms.plugins/assettopology/create localhost
(or with parameters)
sudo ./send-event.pl uei.opennms.plugins/assettopology/create localhost -p
'providerId test' -p 'label test' -p 'assetLayers asset-country,asset-city,asset-
building'-->
other example possible parameters are
-p 'filters asset-displaycategory=!testDisplayCategory'
-p 'preferredLayout Grid Layout'
-p 'breadcrumbStrategy SHORTEST_PATH_TO_ROOT'
```

To uninstall an asset topology use

```
(for default topology providerId)
sudo ./send-event.pl uei.opennms.plugins/assettopology/remove localhost
(or with specific providerId)
sudo ./send-event.pl uei.opennms.plugins/assettopology/remove localhost -p
'providerId test'
```

To regenerate an existing asset topology use

```
(for default topology providerId)
sudo ./send-event.pl uei.opennms.plugins/assettopology/regenerate localhost
(or with specific providerId)
sudo ./send-event.pl uei.opennms.plugins/assettopology/regenerate localhost-p
'providerId test'
```

To regenerate all existing asset topologies use

14.7. Viewing the topology

If all goes well, having installed the topology, upon refreshing your screen, you should see a new topology display option in the *OpenNMS Meridian* topology page. The displayed name of this topology is given by the label field

The label field need not be the same as the providerId which is used by the ReST api for the installation or removal of a topology. However the label field must be unique across all installed topologies.

It is possible to have several topologies installed which have been generated using different configurations. You simply need to ensure that the providerId and label field used for each installation command is different.

14.8. Additional notes

Please note you MUST first uninstall an *OpenNMS Meridian* graphml topology before installing a new one. You will also have to log out and log back into the UI in order to see the new topology file. If you uninstall a topology while viewing it, the UI will throw an error and you will also have to log out and back in to see the remaining topologies.

Chapter 15. Database Reports

Reporting on information from the *OpenNMS Meridian* monitoring system is important for strategical or operational decisions. Database reports give access to the embedded *JasperReports* engine and allow users to create and customize report templates. Run these reports on demand or on a predefined schedule within *OpenNMS Meridian*.



Originally database reports created reports working on data stored in the *OpenNMS Meridian* database only. This is no longer mandatory, performance data can also be used. Theoretically the reports do not need to be *OpenNMS Meridian* related.



The *OpenNMS Meridian Report Engine* allows the creation of various kinds of reports and also supports distributed report repositories. These features are not covered by this documentation. Only reports using *JasperReports* and Grafana dashboards are described here.

15.1. Overview

The *OpenNMS Meridian Report Engine* uses the *JasperReport* library to create reports in various output formats. Each report template must be a *.jrxml file. The *OpenNMS Meridian Report Engine* passes a *JDBC* Connection to the *OpenNMS Meridian Database* to each report on execution.

Supported Output Formats	PDF, CSV	
JasperReport Version	6.3.0	

For more details on how *JasperReports* works, please refer to the official documentation of *Jaspersoft Studio*.

15.2. Modify existing reports

All default *OpenNMS Meridian* reports are located in **\$OPENNMS_HOME/etc/report-templates**. Each .jrxml file located there can be modified; the changes are applied the next time *OpenNMS Meridian* creates a report.

When a subreport has been modified, *OpenNMS Meridian* will detect a change based on the report's lastModified time and will recompile the report. A compiled version of the report is represented by a .jasper file with the same name as the .jrxml file. Subreports are located in \$OPENNMS_HOME/etc/report-templates/subreports.



If unsure, simply delete all .jasper files and *OpenNMS Meridian* will automatically compile the subreports if needed.

15.3. Add a custom report

To add a new *JasperReport* report to the *Local OpenNMS Meridian Report Repository*, do the following:

Create a new entry in the \$OPENNMS_HOME/etc/database-reports.xml file.

```
<report

id="MyReport" ①

display-name="My Report" ②

online="true" ③

report-service="jasperReportService" ④

description="This is an example description. It shows up in the web ui when creating

an online report" ⑤

/>
```

- 1 A unique identifier.
- ② The name of the report. Appears in the web UI.
- ③ Defines if this report can be executed on demand, otherwise only scheduling is possible.
- ④ The report service implementation to use. In most cases this is jasperReportService.
- ⁽⁵⁾ A description of the report. Appears in the web UI.

In addition, create a new entry in the \$OPENNMS_HOME/etc/jasper-reports.xml file.

```
<report
id="MyReport" ①
template="My-Report.jrxml" ②
engine="jdbc" ③
/>
```

 The identifier defined in the previous step. This identifier must exist in \$OPENNMS_HOME/etc/database-reports.xml.

② The name of the template. The template must be located in **\$OPENNMS_HOME/etc/report-templates**.

③ The engine to use. It is either jdbc or null.

15.4. Usage of Jaspersoft Studio

When developing new reports, we recommended using the *Jaspersoft Studio* application. Download it here.




We recommend always using the same *Jaspersoft Studio* version that the OpenNMS Meridian *JasperReport* library uses. Currently OpenNMS Meridian uses version 6.3.0.

15.4.1. Connect to the OpenNMS Meridian Database

To actually create SQL statements against the *OpenNMS Meridian* database you must create a database Data Adapter. The official *Jaspersoft Studio* documentation and wiki cover how to do this.

15.4.2. Use Measurements Datasource and Helpers

To use the *Measurements API* you must add the *Measurements Datasource* library to the build path of *JasperStudio*. To do so, right click in the Project Explorer and select Configure Buildpath.



- 1. Switch to the Libraries tab.
- 2. Click Add External JARs and select the opennms-jasperstudio-extension-2020.1.22-jar-withdependencies.jar file located in \$OPENNMS_HOME/contrib/jasperstudio-extension.
- 3. Close the file selection dialog.

	Java Build Path	⇔•⇒• ◄
 Resource Builders Jaspersoft Studio Java Build Path Java Compiler Java Compiler Java Editor Javadoc Location Project References Refactoring History 	Jara Build Path	Add JARs Add External JARs Add Variable Add Library Add Class Folder Add External Class Folder
(?)		Edit Remove Migrate JAR File Cancel OK

- 4. The Measurements Datasource and Helpers should now be available.
- 5. Go to the Dataset and Query Dialog in Jaspersoft Studio and select a language called measurement.

	Dataset and Query Dialog				
QueryExecutorAdap •	QueryExecutorAdap •				
Query Java Bean					
Language measurement				Read Fields	
<source aggregation="AVERAGE" end="\$P{endDateTime}" label="I</th><th>tartDateTime}" maxrows<br=""/> fInOctets" attribute="ifHCInOctets" transien fOutOctets" attribute="ifHCOutOctets" transi	t="false" resourceId="node[\$P{nodeId}].inter	faceSnmp[\$P{interface}]"/> erfaceSnmp[\$P{interface}]"/>			
		× 7			
Field Name	Class Type	Description		Add	
IfOutOctets	java.lang.Double			Aud	
IfInOctets	java.lang.Double java.util.Date			Delete	
timestamp step	java.lang.Long			Builde	
	Jaranang.cong			Up	
				Down	
Fields Parameters Sorting Filter Expression Data prev	riew				
۲			Cancel	ОК	



If the Read Fields functionality is not available, use the Data preview. Access to the *Measurements API* is possible using the connection parameters MEASUREMENT_URL, MEASUREMENT_USERNAME and MEASUREMENT_PASSWORD. The Supported Fields section gives more details.

15.5. Accessing Performance Data



Before *OpenNMS Horizon 17* and *OpenNMS Meridian 2016*, it was possible to access the performance data stored in .rrd or .jrobin files directly by using the jrobin language extension provided by the RrdDataSource. This is no longer possible; you must use the *Measurements Datasource*.

To access performance data within reports, we created a custom Measurement Datasource that allows you to query the Measurements API and process the returned data in your reports. Please refer to the official Measurements API documentation on how to use the _Measurements API



When using the *Measurements Datasource* within a report a HTTP connection to the *Measurements API* is only established if the report is NOT running within OpenNMS Meridian, e.g. when used with *Jaspersoft Studio*.

To receive data from the *Measurements API* simply create a query as follows:

```
<query-request step="300000" start="$P{startDateTime}" end="$P{endDateTime}" maxrows=
"2000"> ①
<source aggregation="AVERAGE" label="IfInOctets" attribute="ifHCInOctets" transient
="false" resourceId="node[$P{nodeId}].interfaceSnmp[$P{interface}]"/>
<source aggregation="AVERAGE" label="IfOutOctets" attribute="ifHCOutOctets"
transient="false" resourceId="node[$P{nodeid}].interfaceSnmp[$P{interface}]"/>
</query-request>
```

① The query language. In our case, measurement, but JasperReports supports a lot out of the box, such as sql, xpath, etc.

15.5.1. Fields

Each datasource should return a number of fields, which can be used in the report. The *Measurement Datasource* supports the following fields:

Field name	Field type	Field description
<label></label>	java.lang.Double	Each Source defined as transient=false can be used as a field. The name of the field is the label, e.g. IfInOctets
timestamp	java.util.Date	The timestamp of the sample.
step	java.lang.Long	The Step size of the Response. Returns the same value for all rows.
start	java.lang.Long	The Start timestamp in milliseconds of the Resopnse. Returns the same value for all rows.
end	java.lang.Long	The End timestamp in milliseconds of the Response. Returns the same value for all rows.

For more details about the Response, please refer to the official Measurement API documentation.

15.5.2. Parameters

In addition to the queryString, the following *JasperReports* parameters are supported.

Parameter name	Required	Description
MEASUREMENT_URL	yes	The URL of the <i>Measurements</i> <i>API</i> , e.g. http://localhost:8980/ opennms/rest/measurements
MEASUREMENT_USERNAME	no	If authentication is required, specify the username, e.g. admin
MEASUREMENT_PASSWORD	no	If authentication is required, specify the password, e.g. admin

15.6. Disable Scheduler

In cases where the scheduler executing the reports must be disabled, set the system property opennms.report.scheduler.enabled to false. You can set this in \${OPENNMS_HOME}/etc/opennms.properties or \${OPENNMS_HOME}/etc/opennms.properties.d/<my-properties-file>.properties.

15.7. Helper methods

There are a few helper methods to help create reports in *OpenNMS Meridian*.

These helpers come with the *Measurement Datasource*.

Table 111. Supported helper methods

Helper class	Helper Method	Description
org.opennms.netmgt.jasper.help er.MeasurementsHelper	<pre>getNodeOrNodeSourceDescriptor(nodeId, foreignSource, foreignId)</pre>	Generates a node source descriptor according to the input paramters. Either node[nodeId] or nodeSource[foreignSource:forei gnId] is returned. nodeSource[foreignSource:forei gnId] is only returned if foreignSource and foreignId are not empty and not null. Otherwise node[nodeId] is always returned.
		nodeId : String, the ID of the node foreignSource: String, the foreign source of the node. May be null foreignId: String, the foreign ID of the node. May be null. For more details see Usage of the node source descriptor.

Helper class	Helper Method	Description
org.opennms.netmgt.jasper.help er.MeasurementsHelper	<pre>getInterfaceDescriptor(snmpifn ame, snmpifdescr, snmphysaddr)</pre>	Returns the interface descriptor of a given interface, e.g., en0-005e607e9e00. The input paramaters are prioritized. If a snmpifdescr is specified, it is used instead of the snmpifname. It a snmpifdescr is defined, it will be appended to snmpifname /snmpifdescr. snmpifname: String, the interface name of the interface, e.g., en0. May be null. snmpifdescr: String, the description of the interface, e.g., en0. May be null. snmphyaddr: String, the MAC address of the interface, e.g., 005e607e9e00. May be null. As each input parameter may be null, not all of them can be null at the same time. At least one input parameter has to be defined.
		For more details see Usage of the interface descriptor.

15.7.1. Usage of the node source descriptor

A node is addressed by a node source descriptor. The node source descriptor references the node either via the foreign source and foreign id or by the node id.

If store by foreign source is enabled addressing the node only via foreign source and foreign id is possible.

To make report creation easier, there is a helper method to create the node source descriptor.



For more information about store by foreign source, please see our Wiki.

The following example shows the usage of that helper.

jrxml report snippet to visualize the use of the node source descriptor.

```
<parameter name="nodeResourceDescriptor" class="java.lang.String" isForPrompting=</pre>
"false">
 <defaultValueExpression>
<![CDATA[org.opennms.netmgt.jasper.helper.MeasurementsHelper.getNodeOrNodeSourceDescri</pre>
ptor(String.valueOf($P{nodeid}), $P{foreignsource}, $P{foreignid})
]></defaultValueExpression>
</parameter>
<queryString language="Measurement">
 <![CDATA[<query-request step="300000" start="$P{startDateTime}"</pre>
end="$P{endDateTime}" maxrows="2000">
<source aggregation="AVERAGE" label="IfInOctets" attribute="ifHCInOctets"
transient="false" resourceId="$P{nodeResourceDescriptor}.interfaceSnmp[en0-
005e607e9e001"/>
<source aggregation="AVERAGE" label="IfOutOctets" attribute="ifHCOutOctets"
transient="false" resourceId="$P{nodeResourceDescriptor}.interfaceSnmp[en0-
005e607e9e00]"/>
</query-request>]]>
```

Depending on the input parameters, you either get a node resource descriptor or a foreign source/foreign id resource descriptor.

15.7.2. Usage of the interface descriptor

An interfaceSnmp is addressed with the exact interface descriptor. To allow easy access to the interface descriptor we provide a helper tool. The following example shows the usage of that helper.

jrxml report snippet to visualize the use of the interface descriptor

```
<parameter name="interface" class="java.lang.String" isForPrompting="false">
    <parameterDescription><![CDATA[]]></parameterDescription>
    <defaultValueExpression>
<![CDATA[org.opennms.netmgt.jasper.helper.MeasurementsHelper.getInterfaceDescriptor($P
{snmpifname}, $P{snmpifdescr}, $P{snmpphysaddr})]]></defaultValueExpression>
</parameter>
<queryString language="Measurement">
    <![CDATA[<query-request step="300000" start="$P{startDateTime}"
end="$P{endDateTime}" maxrows="2000">
<source aggregation="AVERAGE" label="IfInOctets" attribute="ifHCInOctets"
transient="false" resourceId="node[$P{nodeId}].interfaceSnmp[$P{interface}]"/>
</query-request>]]>
```

To get the appropriate interface descriptor depends on the input parameter.

15.7.3. Use HTTPS

To establish a secure connection to the *Measurements API*, you must import the public certificate of the running *OpenNMS Meridian* to the *Java Trust Store*. In addition, *OpenNMS Meridian* must be configured to use that *Java Trust Store*. Please follow the instructions in this chapter to setup the *Java Trust Store* correctly.

In addition please also set the property org.opennms.netmgt.jasper.measurement.ssl.enable in \$OPENNMS_HOME\etc\opennms.properties to true to ensure that only secure connections are established.



If org.opennms.netmgt.jasper.measurement.ssl.enable is set to false an accidentally insecure connection can be established to the *Measurements API* location. An SSL secured connection can be established even if org.opennms.netmgt.jasper.measurement.ssl.enable is set to false.

15.8. Limitations

• Only a *JDBC Datasource* to the *OpenNMS Meridian Database connection* can be passed to a report, or no datasource at all. One does not have to use the datasource, though.

15.9. Creating PDF Reports from Grafana Dashboards Using OpenNMS Meridian

OpenNMS Meridian provides three templates to create a PDF report from an existing Grafana dashboard. You can also schedule and email these PDF reports to anyone:

- Keep staff without access to OpenNMS Meridian informed about network performance for improved capacity planning
- Create a permanent record of strategic information and progress over a long period of time

The PDF report displays each of the panels from the specified dashboard, with one, two, or four panels per page, depending on the selected template.

Dashboard to PDF:





15.9.1. Before You Begin


This feature requires OpenNMS Meridian and an instance of Grafana with at least one dashboard and panel. OpenNMS allows you to create a report for any Grafana dashboard, not just those created using OpenNMS Helm.

You must set up Grafana as a datasource by configuring the Grafana endpoint in OpenNMS Meridian.

15.9.2. Configure the Grafana Endpoint

Configuring the Grafana endpoint sets up Grafana as the datasource for the dashboards from which you create PDFs.

- 1. Login to your Grafana instance.
- 2. Choose **Configuration** > **API Keys** and click **New API Key**.
- 3. Specify a key name and "Viewer" role and click Add.
 - a. Leave the time to live blank so that the key never expires.
- 4. Copy the key so that you can paste it into the OpenNMS Meridian UI.



a. If desired, test the key using the Curl command provided oi the API key dialog.

5. In OpenNMS, click Please add a Grafana endpoint:

Report Parameters

Grafana Endpoint 💉 😂

There is no Grafana Endpoint defined. Please add a Grafana Endpoint.

- 6. In the Endpoint Configuration screen click the plus sign on the right to add a new endpoint.
- 7. Fill in the information and click **Test Connection**.
- 8. Click Create.

You can now use OpenNMS Meridian to create PDF reports of Grafana dashboards.

15.9.3. Creating a PDF of a Grafana Dashboard

- 1. In the OpenNMS Meridian UI, choose Reports>Database Reports.
- 2. In the Report Templates area, click Grafana Dashboard Report <Xppp>, where <Xppp> represents the number of panels per page you want to display.
- 3. In the Report Parameters area, specify the appropriate information.
 - a. Note that Grafana Endpoint is the datasource. Select a Grafana dashboard from the dropdown list.
 - b. You can also specify CSV for report type.
- 4. Click Create Report.
 - a. You are prompted to save the report locally or open it. The file is saved to a folder on the OpenNMS Meridian Server. It also appears in the UI in the Persisted Reports tab.
- 5. To send the report to someone, click Deliver this report.
- 6. Fill out the Report Delivery Options.
 - a. If you select Email report, specify the recipient's email address in the Recipient field. Separate multiple recipient emails with a comma.
 - b. Webhook allows you to post the generated report to the specified URL.
- 7. Click Deliver Report.
- 8. To schedule the report for regular delivery, click Schedule this report.
- 9. Specify the report frequency (daily, days per week, etc.) and interval of the report.
- 10. Click Schedule Report.

Scheduled reports appear in the Report Schedules tab, where you can edit or delete them:

Report Template	es Report Schedules	Persisted Reports				
2 ±						
Action(s)	Template	Format	Delivery Options	Cron Expression	Trigger Name	Next fire time
💼 🔍	local_defaultCalendarReport	HTML	8	٥	local_defaultCalendarReport admin	

Chapter 16. Enhanced Linkd

Enhanced Linkd (Enlinkd) has been designed to discover connections between nodes using data generated by various link discovery protocols and accessible via SNMP. *Enlinkd* gathers this data on a regular interval and creates a snapshot of a device's neighbors from its perspective by SNMP Data Collectors. *Enlinkd* consolidate the collected Data by Bridge Domain Discovery and Topologies Updater.

Enlinkd-Bridge Domain Discovery use the data gathered by Bridge and IpNetToMedia collectors to provide Bridge Broadcast Domain layout. The Bridge Forwarding Table provided by the single nodes display information about mac address learned on which bridge port, this is what the Bridge consider a Connection: this is not very useful so Bridge Discovery will perform domain calculation to assign to every mac address the port where the device that holds it is effective connected (Or the known nearest bridge port).

Enlinkd-Updaters, for every supported discovery protocol, use the provided Topologies Update API to provide connections information to other OpenNMS service and daemon via OnmsTopologyDao. The provided topologies are used in topology-map and for sending TopologyMessage via Kafka Producer.

The connections discovered by *Enlinkd* collectors and by Bridge Domain Discovery are called *Links*. The term *Link*, within the context of *Enlinkd*, is not synonymous with the term "link" when used with respect to the network OSI *Layer 2* domain, whereby a link only indicates a *Layer 2* connection. A *Link* in context of *Enlinkd* is a more abstract concept and is used to describe any connection between two *OpenNMS Meridian Nodes*. These *Links* are discovered based on information provided by an agent's understanding of connections at the OSI *Layer 2*, *Layer 3*, or other OSI layers.

The Topologies discovered by *Enlinkd-Updaters* are made of *Vertices* and *Edges*.

The following sections describe the *Enlinkd* daemon and its configuration. Additionally, the supported *Link discovery* implementations will be described as well as a list of the SNMP MIBs that the SNMP agents must expose in order for *EnLinkd* to gather *Links* between *Nodes*. FYI: Detailed information about a node's connections (discovered *Links*) and supporting link data can be seen on the *Node detail page* within the *OpenNMS Meridian* Web-UI.

16.1. Enlinkd Daemon

Essentially each *Enlinkd-Collector* asks each device the following question: "What is the network topology from your point of view", this will provide local topology discovery features.

The *Enlinkd-Discovery* does attempt to discover bridge domain *Links* with the data coming from all collected *Bridge Forwarding Tables*.

The *Enlinkd-Updaters* does attempt to discover global *OnmsTopology* doing correlation with the data coming from all node discovered *Links*.

For large environments the behavior of *Enlinkd* can be configured. During the *EnLink* discovery process informational and error output is logged to a global log file.

Table 112. Global log and configuration files for Enlinkd

File	Location	Description
enlinkd-configuration.xml	<pre>\$OPENNMS_HOME/etc</pre>	Global configuration for the daemon process
enlinkd.log	<pre>\$OPENNMS_HOME/logs</pre>	Global <i>Enlinkd</i> log file
log4j2.xml	<pre>\$OPENNMS_HOME/etc</pre>	Configuration file to set the log level for <i>Enlinkd</i>

Configuration file for Enlinkd

xml version="1.0" encoding="ISO-8859-1"? <enlinkd-configuration <="" th="" threads="5"></enlinkd-configuration>
initial_sleep_time="60000"
rescan_interval="86400000"
use-cdp-discovery="true"
use-bridge-discovery="true"
use-lldp-discovery="true"
use-ospf-discovery="true"
use-isis-discovery="true"
topology_interval="30000"
<pre>bridge_topology_interval="300000"</pre>
max_bft="100"
discovery-bridge-threads="1"
/>

Table 113. Descriptione for global configuration parameter

Attribute	Туре	Defau lt	Description
threads	Intege r	5	Number of parallel threads used by <i>Collectors, Updaters</i> and <i>Discovery</i> .
initial_sleep_time	Intege r	60000	Time in milliseconds to wait for start <i>Collectors</i> after OpenNMS Meridian is started.
rescan_interval	Intege r	864000 00	Interval in milliseconds for <i>Collectors</i> .
topology_interval	Intege r	30000	Interval in milliseconds for <i>Updaters</i> .
bridge_topology_in terval	Intege r	300000	Interval in milliseconds for <i>Discovery</i> .
max_bft	Intege r	100	the max number of bft stored in memory for <i>Discovery</i> .
discovery-bridge- threads	Intege r	1	the number of threads used for <i>Discovery</i> .

Attribute	Туре	Defau lt	Description
use-cdp-discovery	Boole an	true	Enable or disable discovery based on <i>CDP</i> information.
use-bridge- discovery	Boole an	true	Enable or disable discovery based on the <i>Bridge</i> information.
use-lldp-discovery	Boole an	true	Enable or disable discovery based on <i>LLDP</i> information.
use-ospf-discovery	Boole an	true	Enable or disable discovery based on <i>OSPF</i> information.
use-isis-discovery	Boole an	true	Enable or disable discovery based on <i>IS-IS</i> information.

The *Discovery* for bridge first start is scheduled at *initial_sleep_time* + *bridge_topology_interval*. The *Updaters* first start are scheduled at *0L*. Configuration changes are applied by restarting OpenNMS and Enlinkd. It is also possible to send an Event to Enlinkd reloading the configuration. An Event can be sent on the CLI or the Web User Interface.

Send configuration reload event on CLI

```
cd $OPENNMS_HOME/bin
./send-event.pl uei.opennms.org/internal/reloadDaemonConfig --parm 'daemonName
Enlinkd'
```



If multiple protocols are enabled, the links will be discovered for each enabled discovery protocol. The topology WebUI will visualize *Links* for each discovery protocol. For example if you start *CDP* and *LLDP* discovery, the WebUI will visualize a *CDP Link* and an *LLDP Link*.

16.2. Layer 2 Link Discovery

Enlinkd is able to discover *Layer 2* network links based on the following protocols:

- Link Layer Discovery Protocol (LLDP)
- Cisco Discovery Protocol (CDP)
- Bridge Discovery (Bridge)

This information are provided by *SNMP Agents* with appropriate *MIB support*. For this reason it is required to have a working *SNMP* configuration running. The following section describes the required *SNMP MIB* provided by the *SNMP agent* to allow the *Link Discovery*.

16.2.1. LLDP Discovery

The *Link Layer Discovery Protocol (LLDP)* is a vendor-neutral link layer protocol. It is used by network devices for advertising their identity, capabilities, and neighbors. *LLDP* performs functions similar to several proprietary protocols, such as the *Cisco Discovery Protocol (CDP)*, *Extreme Discovery Protocol, Foundry Discovery Protocol (FDP), Nortel Discovery Protocol (also known as SONMP)*, and *Microsoft's Link Layer Topology Discovery (LLTD)*^[1].



Only nodes with a running *LLDP* process can be part of the link discovery. The data is similar to running a show lldp neighbor command on the device. Linux and Windows servers don't have an *LLDP* process running by default and will not be part of the link discovery.

The following OIDs are supported to discover and build the *LLDP* network topology and are collected by the *LLDP Discovery Collector*.

Name	OID	Description
<i>lldpLocChassisI</i> .1.0.8802.1.1.2. <i>dSubtype</i> 1.3.1.0		The type of encoding used to identify the chassis associated with the local system. Possible values can be: chassisComponent(1) interfaceAlias(2) portComponent(3) macAddress(4) networkAddress(5) interfaceName(6) local(7)
lldpLocChassisI d	.1.0.8802.1.1.2. 1.3.2.0	The string value used to identify the chassis component associated with the local system.
lldpLocSysName	.1.0.8802.1.1.2. 1.3.3.0	The string value used to identify the system name of the local system. If the local agent supports IETF RFC 3418, <i>lldpLocSysName</i> object should have the same value of <i>sysName</i> object.
lldpLocPortIdSu btype	.1.0.8802.1.1.2. 1.3.7.1.2	The type of port identifier encoding used in the associated <i>lldpLocPortId</i> object.
lldpLocPortId	.1.0.8802.1.1.2. 1.3.7.1.3	The string value used to identify the port component associated with a given port in the local system.
<i>lldpLocPortDesc</i>	.1.0.8802.1.1.2. 1.3.7.1.4	The string value used to identify the 802 LAN station's port description associated with the local system. If the local agent supports <i>IETF RFC 2863, lldpLocPortDesc</i> object should have the same value of <i>ifDescr</i> object.

Table 114. Supported OIDs from LLDP-MIB

Name	OID	Description
lldpRemChassisI dSubtype	.1.0.8802.1.1.2. 1.4.1.1.4	The type of encoding used to identify the chassis associated with the local system. Possible values can be: chassisComponent(1) interfaceAlias(2) portComponent(3) macAddress(4) networkAddress(5) interfaceName(6) local(7)
lldpRemChassisI d	.1.0.8802.1.1.2. 1.4.1.1.5	The string value used to identify the chassis component associated with the remote system.

Name	OID	Description
<i>lldpRemPortIdS</i> <i>ubtype</i>	.1.0.8802.1.1.2. 1.4.1.1.6	The type of port identifier encoding used in the associated <i>lldpRemPortId</i> object. <i>interfaceAlias(1)</i> the octet string identifies a particular instance of the <i>ifAlias</i> object (defined in IETF RFC 2863). If the particular <i>ifAlias</i> object does not contain any values, another port identifier type should be used. <i>portComponent(2)</i> the octet string identifies a particular instance of the <i>entPhysicalAlias</i> object (defined in IETF RFC 2737) for a port or backplane component. <i>macAddress(3)</i> this string identifies a particular unicast source address (encoded in network byte order and IEEE 802.3 canonical bit order) associated with the port (IEEE Std 802-2001). <i>networkAddress(4)</i> this string identifies a network address associated with the port. The first octet contains the <i>IANA</i> AddressFamilyNumbers enumeration value for the specific address value in network byte order. <i>interfaceName(5)</i> the octet string identifies a particular instance of the <i>ifName</i> object (defined in IETF RFC 2863). If the particular <i>ifName</i> object does not contain any values, another port identifier type should be used. <i>agentCircuitId(6)</i> this string identifies a agent-local identifier of the circuit (defined in RFC 3046) <i>local(7)</i> this string identifies a locally assigned port ID.
lldpRemPortId	.1.0.8802.1.1.2. 1.4.1.1.7	The string value used to identify the port component associated with the remote system.
lldpRemPortDes c	.1.0.8802.1.1.2. 1.4.1.1.8	The string value used to identify the description of the given port associated with the remote system.
lldpRemSysNam e	.1.0.8802.1.1.2. 1.4.1.1.9	The string value used to identify the system name of the remote system.

Generic information about the *LLDP* process can be found in the *LLDP Information* box on the *Node Detail Page* of the device. Information gathered from these OIDs will be stored in the following database table:




Figure 36. Database tables related to LLDP discovery

Lldp Topology Updater provide LLDP OnmsTopology consolidating lldp data collected by *LLDP Collector* only full bidirectional connections between two Lldp supported devices become *Edges*. *Node A* and *Node B* are connected by an *LLDP Edge* if and only if there is an LLDP MIB port connection in *Node A* to *Node B* and viceversa.

16.2.2. CDP Discovery

The *Cisco Discovery Protocol (CDP)* is a proprietary link layer protocol from *Cisco*. It is used by network devices to advertise identity, capabilities and neighbors. *CDP* performs functions similar to several proprietary protocols, such as the *Link Layer Discovery Protocol (LLDP)*, *Extreme Discovery Protocol, Foundry Discovery Protocol (FDP)*, *Nortel Discovery Protocol (also known as SONMP)*, and *Microsoft's Link Layer Topology Discovery (LLTD)*. The *CDP* discovery uses information provided by the CISCO-CDP-MIB and CISCO-VTP-MIB.



Only nodes with a running *CDP* process can be part of the link discovery. The data is similar to running a show cdp neighbor command on the IOS CLI of the device. Linux and Windows servers don't have a *CDP* process running by default and will not be part of the link discovery.

The following OIDs are supported to discover and build the *CDP* network topology and are collected by the *CDP Discovery Collector*.

Table 115. Supported OIDS from the IF-MIB

Nam e	OID	Description
ifDes cr	.1.3.6.1.2.1.2. 2.1.2	A textual string containing information about the interface. This string should include the name of the manufacturer, the product name and the version of the interface hardware/software.

Name	OID	Description
cdpInterfaceNa me	.1.3.6.1.4.1.9.9.2 3.1.1.1.1.6	The name of the local interface as advertised by <i>CDP</i> in the <i>Port-ID TLV</i> .
cdpCacheEntry	.1.3.6.1.4.1.9.9.2 3.1.2.1.1	An entry (conceptual row) in the <i>cdpCacheTable</i> , containing the information received via <i>CDP</i> on one interface from one device. Entries appear when a <i>CDP</i> advertisement is received from a neighbor device. Entries disappear when <i>CDP</i> is disabled on the interface, or globally.
cdpCacheAddres sType	.1.3.6.1.4.1.9.9.2 3.1.2.1.1.3	An indication of the type of address contained in the corresponding instance of <i>cdpCacheAddress</i> .
cdpCacheAddres s	.1.3.6.1.4.1.9.9.2 3.1.2.1.1.4	The (first) network-layer address of the device's SNMP-agent as reported in the Address <i>TLV</i> of the most recently received <i>CDP</i> message. For example, if the corresponding instance of <i>cacheAddressType</i> had the value ip(1), then this object would be an IP-address.
cdpCacheVersio n	.1.3.6.1.4.1.9.9.2 3.1.2.1.1.5	The Version string as reported in the most recent <i>CDP</i> message. The zero-length string indicates no Version field <i>(TLV)</i> was reported in the most recent <i>CDP</i> message.
cdpCacheDevice Id	.1.3.6.1.4.1.9.9.2 3.1.2.1.1.6	The <i>Device-ID</i> string as reported in the most recent <i>CDP</i> message. The zero-length string indicates no <i>Device-ID</i> field <i>(TLV)</i> was reported in the most recent <i>CDP</i> message.
cdpCacheDevice Port	.1.3.6.1.4.1.9.9.2 3.1.2.1.1.7	The <i>Port-ID</i> string as reported in the most recent <i>CDP</i> message. This will typically be the value of the <i>ifName</i> object (e.g., Ethernet0). The zero-length string indicates no <i>Port-ID</i> field <i>(TLV)</i> was reported in the most recent <i>CDP</i> message.
cdpCachePlatfor m	.1.3.6.1.4.1.9.9.2 3.1.2.1.1.8	The Device's Hardware Platform as reported in the most recent <i>CDP</i> message. The zero-length string indicates that no Platform field <i>(TLV)</i> was reported in the most recent <i>CDP</i> message.
cdpGlobalRun	.1.3.6.1.4.1.9.9.2 3.1.3.1.0	An indication of whether the Cisco Discovery Protocol is currently running. Entries in <i>cdpCacheTable</i> are deleted when CDP is disabled.

Name	OID	Description
cdpGlobalDevice Id	.1.3.6.1.4.1.9.9.2 3.1.3.4.0	The device ID advertised by this device. The format of this device id is characterized by the value of <i>cdpGlobalDeviceIdFormat</i> object.
cdpGlobalDevice IdFormat	.1.3.6.1.4.1.9.9.2 3.1.3.7.0	An indication of the format of Device-Id contained in the corresponding instance of <i>cdpGlobalDeviceId</i> . User can only specify the formats that the device is capable of as denoted in <i>cdpGlobalDeviceIdFormatCpb</i> object. <i>serialNumber(1):</i> indicates that the value of <i>cdpGlobalDeviceId</i> object is in the form of an <i>ASCII</i> string contain the device serial number. <i>macAddress(2):</i> indicates that the value of <i>cdpGlobalDeviceId</i> object is in the form of Layer 2 MAC address. <i>other(3):</i> indicates that the value of <i>cdpGlobalDeviceId</i> object is in the form of a platform specific <i>ASCII</i> string contain info that identifies the device. For example: <i>ASCII string</i> contains <i>serialNumber</i> appended/prepened with system name.

Table 117. Supported OIDS from the CISCO-VTP-MIB.

vtpVersion	.1.3.6.1.4.1.9.9.46 .1.1.1.0	The version of VTP in use on the local system. A device will report its version capability and not any particular version in use on the device. If the device does not support <i>VTP</i> , the version is <i>none(3)</i> .
ciscoVtpVla nState	.1.3.6.1.4.1.9.9.46 .1.3.1.1.2	The state of this VLAN. The state <i>mtuTooBigForDevice</i> indicates that this device cannot participate in this VLAN because the VLAN's MTU is larger than the device can support. The state <i>mtuTooBigForTrunk</i> indicates that while this VLAN's MTU is supported by this device, it is too large for one or more of the device's trunk ports. <i>operational(1), suspended(2), mtuTooBigForDevice(3),</i> <i>mtuTooBigForTrunk(4)</i>
ciscoVtpVla nType	.1.3.6.1.4.1.9.9.46 .1.3.1.1.3	The type of this VLAN. ethernet(1), fddi(2), tokenRing(3), fddiNet(4), trNet(5), deprecated(6)
ciscoVtpVla nName	.1.3.6.1.4.1.9.9.46 .1.3.1.1.4	The name of this <i>VLAN</i> . This name is used as the <i>ELAN-name</i> for an <i>ATM LAN-Emulation</i> segment of this <i>VLAN</i> .

Generic information about the *CDP* process can be found in the *CDP Information* box on the *Node Detail Page* of the device. Information gathered from these OIDs will be stored in the following database table:




Figure 37. Database tables related to CDP discovery

Cdp Topology Updater provide CDP OnmsTopology consolidating cdp data collected by *CDP Collector* only full bidirectional connections between two Cdp supported devices become *Edges*. *Node A* and *Node B* are connected by an *CDP Edge* if and only if there is a CDP MIB port connection in *Node A* to *Node B* and viceversa.

16.2.3. Transparent Bridge Discovery

Discovering *Layer 2* network links using the *Bridge Forwarding* table requires a special algorithm. To discover *Links* an algorithm based on a scientific paper with the title Topology Discovery for Large Ethernet Networks is implemented. The gathered information is used to classify *Links* in *macLink* and *bridgeLink*. A *macLink* represents a *Link* between a workstation or server identified by a mac address. A *bridgeLink* is a *connection* between backbone ports. A *Shared Segment* is a *connection among workstations or servers (several mac addresses) and backbone ports (for example devices connected via an hub). A _bridgeLink* is a *a shared segment* with only two bridge backbone ports. A *Broadcast Domain* is a collection of *Shared Segment* baed on common set of *mac* addresses.

Discovery Bridge Broadcast Domains is made in two step, the first step regards data collection. The Bridge Forwarding Table together with other Spanning Tree information is collected by the BridgeDiscovery Collector. The BTF is not persisted into database and is maintained in memory to be processed by the BridgeDomainDiscovery. *BridgeDomainDiscovery* runs the specified algorithm over collected BFT and will produce a Bridge Domain or several Bridge domains depending on the broadcasts set of mac addresses found. Bridge Domains are collection of Shared Segments as described above.

BridgeDomainDiscovery does not support multi vlan, the Bridge Network model identify a *Bridge* for every *VLAN*. Each VLAN has it's own Bridge Forwarding Table and it's own Spanning Tree. So in line to discovery a Bridge Topology the algorithm has to be run against every bridge and every vlan. Actually the discovery is run only against the main VLAN.

Bridge Domains provide no information about layer 3 but only a layer 2 two map of the Broadcast Domains. While Bridge/Switch are identified by the fact that are OpenNMS Nodes to map mac to

Nodes where possible the IpNetToMedia table is needed. In this manned we are able to associate to mac address the corresponding ip address and then the associated node. The *Bridge Topology Updater* put together the information stored into bridge domains with the *ipnettomedia* data. and provide Bridge OnmsTopology.

Bridge Topology Updater whenever possible tries to associate a mac address to an ip address and then to a node. It can happen that the mac address and the ip address specified are not associate to a single node (for example because there are duplicated node or also because the nodes supports protocol like LACP), in this case we do not resolve the node but leave the association found mac:ip into a specific Vertex.

Bridge Topology Updater do not support LACP protocols and other similar aggregation protocols.

Transparent bridging is not loop free so if you have loops you have to enable the spanning tree protocol that will detect loops and again will put some ports in a *blocking* state to avoid loops. To get links it is necessary to perform some calculations that let us define the *Links*. The following *MIBS* must be supported by the *SNMP agent* to allow *Transparent Bridge Discovery*.

Table 118. Supported MIBS from the Cisco-VTP MIB

ľ	Jame	OID	Description
		.1.3.6.1.4.1.9.9.46 .1.1.1.0	The version of VTP in use on the local system. A device will report its version capability and not any particular version in use on the device. If the device does not support <i>VTP</i> , the version is <i>none(3)</i> .

Name	OID	Description
ipNetToMediaIfIn dex	.1.3.6.1.2.1.4 .22.1.1	The interface on which this entry's equivalence is effective. The layer-2 interface identified by a particular value of this index is the same interface as identified by the same value of <i>ifIndex</i> .
ipNetToMediaPhy sAddress	.1.3.6.1.2.1.4 .22.1.2	The media-dependent <i>physical</i> address.
ipNetToMediaNet Address	.1.3.6.1.2.1.4 .22.1.3	The <i>IpAddress</i> corresponding to the media-dependent <i>physical</i> address.
ipNetToMediaTyp e	.1.3.6.1.2.1.4 .22.1.4	The type of mapping. Setting this object to the value <i>invalid(2)</i> has the effect of invalidating the corresponding entry in the <i>ipNetToMediaTable</i> . That is, it effectively dissasociates the interface identified with said entry from the mapping identified with said entry. It is an implementation-specific matter as to whether the agent removes an invalidated entry from the table. Accordingly, management stations must be prepared to receive tabular information from agents that corresponds to entries not currently in use. Proper interpretation of such entries requires examination of the relevant <i>ipNetToMediaType</i> object.

Table 119. Supported OIDs from the IP-MIB

Table 120. Supported OIDS from the BRIDGE-MIB

Name	OID	Description
dot1dBaseBridgeA ddress	.1.3.6.1.2.1.17 .1.1.0	The MAC address used by this bridge when it must be referred to in a unique fashion. It is recommended that this be the numerically smallest MAC address of all ports that belong to this bridge. However it is only required to be unique. When concatenated with <i>dot1dStpPriority</i> a unique <i>BridgeIdentifier</i> is formed which is used in the <i>Spanning Tree</i> <i>Protocol</i> .
dot1dBaseNumPort s	.1.3.6.1.2.1.17 .1.2.0	The number of ports controlled by this bridging entity.
dot1dBaseType	.1.3.6.1.2.1.17 .1.3.0	Indicates what type of bridging this bridge can perform. If a bridge is actually performing a certain type of bridging this will be indicated by entries in the port table for the given type.
dot1dBasePort	.1.3.6.1.2.1.17 .1.4.1.1	The port number of the port for which this entry contains bridge management information.
dot1dPortIfIndex	.1.3.6.1.2.1.17 .1.4.1.2	The value of the instance of the <i>ifIndex</i> object, defined in <i>MIB-II</i> , for the interface corresponding to this port.
dot1dStpProtocolS pecification	.1.3.6.1.2.1.17 .2.1.0	An indication of what version of the Spanning Tree Protocol is being run. The value <i>decLb100(2)</i> indicates the <i>DEC</i> <i>LANbridge 100 Spanning Tree protocol. IEEE 802.1d</i> implementations will return <i>ieee8021d(3)</i> . If future versions of the <i>IEEE Spanning Tree Protocol</i> are released that are incompatible with the current version a new value will be defined.
dot1dStpPriority	.1.3.6.1.2.1.17 .2.2	The value of the writeable portion of the <i>Bridge ID</i> , i.e., the first two octets of the (8 octet long) <i>Bridge ID</i> . The other (last) 6 octets of the <i>Bridge ID</i> are given by the value of <i>dot1dBaseBridgeAddress</i> .
dot1dStpDesignate dRoot	.1.3.6.1.2.1.17 .2.5	The bridge identifier of the root of the spanning tree as determined by the <i>Spanning Tree Protocol</i> as executed by this node. This value is used as the <i>Root Identifier</i> parameter in all configuration <i>Bridge PDUs</i> originated by this node.
dot1dStpRootCost	.1.3.6.1.2.1.17 .2.6	The cost of the path to the root as seen from this bridge.
dot1dStpRootPort	.1.3.6.1.2.1.17 .2.7	The port number of the port which offers the lowest cost path from this bridge to the root bridge.
dot1dStpPort	.1.3.6.1.2.1.17	The port number of the port for which this entry contains Spanning Tree Protocol management information.

	4 2 6 4 2 4 5	
dot1dStpPortPriori ty	.1.3.6.1.2.1.17 .2.15.1.2	The value of the priority field which is contained in the first (in network byte order) octet of the (2 octet long) Port ID. The other octet of the Port ID is given by the value of <i>dot1dStpPort</i> .
dot1dStpPortState	.1.3.6.1.2.1.17 .2.15.1.3	The port's current state as defined by application of the <i>Spanning Tree Protocol</i> . This state controls what action a port takes on reception of a frame. If the bridge has detected a port that is malfunctioning it will place that port into the <i>broken(6)</i> state. For ports which are disabled (see <i>dot1dStpPortEnable</i>), this object will have a value of <i>disabled(1)</i> .
dot1dStpPortEnabl e	.1.3.6.1.2.1.17 .2.15.1.4	The enabled/disabled status of the port.
dot1dStpPortPathC ost	.1.3.6.1.2.1.17 .2.15.1.5	The contribution of this port to the path cost of paths towards the spanning tree root which include this port. 802.1D-1990 recommends that the default value of this parameter be in inverse proportion to the speed of the attached LAN.
dot1dStpPortDesig natedRoot	.1.3.6.1.2.1.17 .2.15.1.6	The unique <i>Bridge Identifier</i> of the <i>Bridge</i> recorded as the <i>Root</i> in the <i>Configuration BPDUs</i> transmitted by the <i>Designated Bridge</i> for the segment to which the port is attached.
dot1dStpPortDesig natedCost	.1.3.6.1.2.1.17 .2.15.1.7	The path cost of the <i>Designated Port</i> of the segment connected to this port. This value is compared to the <i>Root</i> <i>Path Cost</i> field in received bridge <i>PDUs</i> .
dot1dStpPortDesig natedBridge	.1.3.6.1.2.1.17 .2.15.1.8	The <i>Bridge Identifier</i> of the bridge which this port considers to be the <i>Designated Bridge</i> for this port's segment.
dot1dStpPortDesig natedPort	.1.3.6.1.2.1.17 .2.15.1.9	The <i>Port Identifier</i> of the port on the <i>Designated Bridge</i> for this port's segment.
dot1dTpFdbAddres s	.1.3.6.1.2.1.17 .4.3.1.1	A unicast <i>MAC address</i> for which the bridge has forwarding and/or filtering information.
dot1dTpFdbPort	.1.3.6.1.2.1.17 .4.3.1.2	Either the value '0', or the port number of the port on which a frame having a source address equal to the value of the corresponding instance of <i>dot1dTpFdbAddress</i> has been seen. A value of '0' indicates that the port number has not been learned but that the bridge does have some forwarding/filtering information about this address (e.g. in the <i>dot1dStaticTable</i>). Implementors are encouraged to assign the port value to this object whenever it is learned even for addresses for which the corresponding value of <i>dot1dTpFdbStatus</i> is not <i>learned(3)</i> .

dot1dTpFdbStatus	.1.3.6.1.2.1.17 .4.3.1.3	The status of this entry. The meanings of the values are: other(1): none of the following. This would include the case where some other <i>MIB</i> object (not the corresponding instance of dot1dTpFdbPort, nor an entry in the dot1dStaticTable) is being used to determine if and how frames addressed to the value of the corresponding instance of dot1dTpFdbAddress are being forwarded. invalid(2): this entry is not longer valid (e.g., it was learned but has since aged-out), but has not yet been flushed from the table. learned(3): the value of the corresponding instance of dot1dTpFdbPort was learned, and is being used. self(4): the value of the corresponding instance of dot1dTpFdbAddress represents one of the bridge's addresses. The corresponding instance of dot1dTpFdbPort indicates which of the bridge's ports has this address. mgmt(5): the value of the corresponding instance of dot1dTpFdbAddress is also the value of an existing instance of dot1dStaticAddress.
------------------	-----------------------------	---

Table 121. Supported OIDS from the Q-BRIDGE-MIB

Name	OID	Description
dot1qTpFdb Port	.1.3.6.1.2.1.17.7. 1.2.2.1.2	Either the value 0, or the port number of the port on which a frame having a source address equal to the value of the corresponding instance of <i>dot1qTpFdbAddress</i> has been seen. A value of 0 indicates that the port number has not been learned but that the device does have some forwarding/filtering information about this address (e.g., in the <i>dot1qStaticUnicastTable</i>). Implementors are encouraged to assign the port value to this object whenever it is learned, even for addresses for which the corresponding value of <i>dot1qTpFdbStatus</i> is not <i>learned(3)</i> .

dot1qTpFdb Status	.1.3.6.1.2.1.17.7. 1.2.2.1.3	The status of this entry. The meanings of the values are: other(1): none of the following. This may include the case where some other MIB object (not the corresponding instance of dot1qTpFdbPort, nor an entry in the dot1qStaticUnicastTable) is being used to determine if and how frames addressed to the value of the corresponding instance of dot1qTpFdbAddress are being forwarded. invalid(2): this entry is no longer valid (e.g., it was learned but has since aged out), but has not yet been flushed from the table. learned(3): the value of the corresponding instance of dot1qTpFdbPort was learned and is being used. self(4): the value of the corresponding instance of dot1qTpFdbAddress represents one of the device's addresses. The corresponding instance of dot1qTpFdbPort indicates which of the device's ports has this address. mgmt(5): the value of the corresponding instance of dot1qTpFdbAddress is also the value of an existing instance of
		dot1qStaticAddress.

Generic information about the *bridge* link discovery process can be found in the *Bridge Information* box on the *Node Detail Page* of the device. Information gathered from this *OID* will be stored in the following database table:

	bridg	estplink						
ľ	🖉 id	INTEGER						
	nodeid	INTEGER			-			
	slpport	INTEGER	fk_bridgestplink_nodeid					
	stpportpriority	INTEGER						
	sipportatate	INTEGER						
	sipportenable sipportpathcost	INTEGER						
	stpportpathoost stpportifindex	INTEGER						
	stpportifname	TEXT						
	vlan	INTEGER						
	designatedroot	CHARACTER VARYING(16)						
	des ignated cost	INTEGER						
	designatedbridge	CHARACTER VARYING(16)						
	designatedport	CHARACTER VARYING(4)						
	bridge stplink create time	TIMESTAMP(6) WITH TIME ZO						
l	bridges plink is stpolitime	TIMESTAMP(6) WITH TIME ZO	NE					
	-	emaclink						
	₽ id	INTEGER						
	nodeid	INTEGER	At heidermanish and sid					
	bridgepart	INTEGER	fk_bridgemaclink_nodeid					
	bridge portifin dex	INTEGER						
	bridgeportifname vlan	TEXT INTEGER						
	macaddress	CHARACTER VAR VING(12)						
	bridgem ac link create time		ONE					
		TIMESTAMP(8) WITH TIME Z						
	brida	eelement						
		INTEGER						
	nodeid	INTEGER						
		CHARACTER VARYING(12)	fk_bridgeelement_nodeid					
		INTEGER						
		INTEGER						
		INTEGER						
		TEXT						
	stpp roto colsp ecification							
		INTEGER						
		CHARACTER VARYING(18) INTEGER						
		INTEGER						
		TIMESTAMP(8) WITH TIME ZO	NE					
		TIMESTAMP (6) WITH TIME ZO						
_								
	brid gel	bridgelink						
Γ,	Pid -	INTEGER						
[nodeid	INTEGER						
	bridgeport	INTEGER	fk_bridgebridgelink_nodeid					
	bridge portifin de x	INTEGER						
	bridge portifn ame	TEXT						
	vlan designatednodeid	INTEGER						node
	designatedhodeid designatedbildgeport	INTEGER	fk_bridgebridgelink_de sign ate dnod eid			8	nodeid	INTEGER
	d esign at ed bridg e portifin de x					9	nodecreatetime	TIMESTAMP(8) WITH TIME ZONE
	design at ed bridge portifname						nodeparentid	INTEGER
	design ated vlan	INTEGER					nodetype	CHARACTER(1)
	bridge bridge link create time						nodesysoid	CHARACTER VARYING(256)
	bridgebridgelinklastpolitim	TIMESTAMP(6) WITH TIME 2	ZONE				nodesysname	CHARACTER VARYING(258)
							nodesystescription nodesystocation	CHARACTER VARYING(256) CHARACTER VARYING(256)
		tomedia					nodesyscontact	CHARACTER VARYING(256)
		EGER					nodelabel	CHARACTER VARYING(256)
	netaddress TEX						nodelabelsource	CHARACTER(1)
		RACTER VARYING(32)						CHARACTER VARYING(18)
	sourcenodeid NTE sourceifindex NTE		fk_ipnettomedia_sourcenodeid					CHARACTER VARYING(16)
		ESTAMP(8) WITH TIME ZONE					operatingsystem lastcapsdpoll	CHARACTER VARYING(64) TIMESTAMP(6) WITH TIME ZONE
	the second se	ESTAMP(8) WITH TIME ZONE					foreign source	CHARACTER VARY ING(64)
	Powered by yrin	53					fomignid	CHARACTER VARY ING(84)

Figure 38. Database tables related to transparent bridge discovery

16.3. Layer 3 Link Discovery

With *Enlinkd* it is possible to get *Links* based on network routing applications. The following routing daemons can be used to provide a discovery of links based *Layer 3* information:

- Open Shortest Path First (OSPF)
- Intermediate System to Intermediate System (IS-IS)

This information is provided by *SNMP Agents* with appropriate *MIB support*. For this reason it is required to have a working *SNMP* configuration running. The link data discovered from *Enlinkd* is provided in the *Topology User Interface* and on the detail page of a node.

16.3.1. OSPF Discovery

The following MIBSs are supported to discover and build the *OSPF* network topology and are collected by the *OSPF Discovery Collector*.

The relevant MIBs for OSPF topology are *OSPF-MIB* and *OSPF-TRAP-MIB*. In these MIBs are defined the relevant objects used to find OSPF links, specifically:

- The Router ID which, in OSPF, has the same format as an IP address
- But identifies the router independent of its IP address.

Also all the interfaces are identified by their IP addresses. The OSPF links come from the SNMP *ospfNbrTable* defined in OSPF-MIB and this table is in practice persisted in the *ospfLink* table:

Name	OID	Description
ospfRouterId	.1.3.6.1.2.1.1 4.1.1.0	A 32-bit integer uniquely identifying the router in the Autonomous System. By convention, to ensure uniqueness, this should default to the value of one of the router's IP interface addresses. This object is persistent and when written the entity should save the change to non-volatile storage.
ospfAdminStat	.1.3.6.1.2.1.1 4.1.2.0	The administrative status of <i>OSPF</i> in the router. The value <i>enabled</i> denotes that the <i>OSPF Process</i> is active on at least one interface; <i>disabled</i> disables it on all interfaces. This object is persistent and when written the entity should save the change to non-volatile storage.
ospfVersionNum ber	.1.3.6.1.2.1.1 4.1.3.0	The current version number of the OSPF protocol is 2.
ospfAreaBdrRtrS tatus	.1.3.6.1.2.1.1 4.1.4.0	A flag to note whether this router is an Area Border Router.
ospfAreaASBdrR trStatus	.1.3.6.1.2.1.1 4.1.5.0	A flag to note whether this router is configured as an <i>Autonomous System Border Router</i> . This object is persistent and when written the entity should save the change to non-volatile storage.
ospfIfIpAddress	.1.3.6.1.2.1.1 4.7.1.1	The IP address of this OSPF interface.
ospfAddressLessI f	.1.3.6.1.2.1.1 4.7.1.2	For the purpose of easing the instancing of addressed and addressless interfaces; this variable takes the value <i>0</i> on interfaces with IP addresses and the corresponding value of <i>ifIndex</i> for interfaces having no <i>IP address</i> .
ospfNbrIpAddr	.1.3.6.1.2.1.1 4.10.1.1	The IP address this neighbor is using in its IP source address. Note that, on addressless links, this will not be 0.0.0.0 but the address of another of the neighbor's interfaces.

Table 122. Supported OIDs from OSPF-MIB

Name	OID	Description
ospfNbrAddressL essIndex	.1.3.6.1.2.1.1 4.10.1.2	On an interface having an <i>IP address</i> , zero. On addressless interfaces, the corresponding value of <i>ifIndex</i> in the <i>Internet Standard MIB</i> . On row creation, this can be derived from the instance.
ospfNbrRtrId	.1.3.6.1.2.1.1 4.10.1.3	A 32-bit integer (represented as a type <i>IpAddress</i>) uniquely identifying the neighboring router in the <i>Autonomous System</i> .

Table 123. Supported OIDs from IP-MIB

Name	OID	Description
ipAdEntIfIn dex	.1.3.6.1.2.1.4. 20.1.2	The index value which uniquely identifies the interface to which this entry is applicable. The interface identified by a particular value of this index is the same interface as identified by the same value of the <i>IF-MIB's ifIndex</i> .
ipAdEntNet Mask	.1.3.6.1.2.1.4. 20.1.3	The subnet mask associated with the <i>IPv4</i> address of this entry. The value of the mask is an <i>IPv4</i> address with all the network bits set to 1 and all the hosts bits set to 0.

Generic information about the *OSPF* link discovery process can be found in the *OSPF Information* box on the *Node Detail Page* of the device. Information gathered from these OIDs will be stored in the following database table:




Figure 39. Database tables related to OSPF discovery

OSPF Topology Updater provide OSPF OnmsTopology consolidating OSPF data collected by *OSPF Collector* only full bidirectional connections between two OSPF supported devices become *Edges*. *Node A* and *Node B* are connected by an *OSPF Edge* if and only if there is a *OSPF link* in *Node A* to *Node B* and viceversa.

16.3.2. IS-IS Discovery

IS-IS Links are found in the *isisISAdjTable* that is defined in *ISIS-MIB* (mib-rfc4444.txt). In this table is found the information needed to find the Adjacency Intermediate System. The information about IS-IS is stored into two tables: *isisElement* and *isisLink. isisElement* contains the *ISISSysID*, a unique identifier of the "Intermediate System" (the name for the Router in ISO protocols). Each entry in this SNMP MIB table represents a unidirectional link from the *Intermediate System* that is queried to the *Adjacent Intermediate Systems* running IS-IS and "peering" with the source router. If two routers *IS-A* and *IS-B* support *ISIS-MIB*, then *EnLinkd* will create two link entries in OpenNMS Meridian: one from *IS-A* to *IS-B* (from the *adjtable* of *IS-A*) the complementary link back from *IS-B* to *IS-A* (from the *adjTable of _IS-B*). IS-IS links are represented in the *ISIS-MIB* as follows:

The following OIDs are supported to discover and build the *ISIS* network topology and are collected by the *ISIS Discovery Collector*.

Name	OID	Description
isisSysID	.1.3.6.1.2.1.138 .1.1.1.3.0	The ID for this Intermediate System. This value is appended to each of the area addresses to form the Network Entity Titles. The derivation of a value for this object is implementation specific. Some implementations may automatically assign values and not permit an SNMP write, while others may require the value to be set manually. Configured values must survive an agent reboot.
isisSysAdminStat e	.1.3.6.1.2.1.138 .1.1.1.8.0	The administrative state of this Intermediate System. Setting this object to the value on when its current value is off enables the Intermediate System. Configured values must survive an agent reboot.
isisSysObject	.1.3.6.1.2.1.138 .1.1.1	isisSysObject
isisCircIfIndex	.1.3.6.1.2.1.138 .1.3.2.1.2	The value of ifIndex for the interface to which this circuit corresponds. This object cannot be modified after creation.
isisCircAdminStat e	.1.3.6.1.2.1.138 .1.3.2.1.3	The administrative state of the circuit.
isisISAdjState	.1.3.6.1.2.1.138 .1.6.1.1.2	The state of the adjacency.
isisISAdjNeighSN PAAddress	.1.3.6.1.2.1.138 .1.6.1.1.4	The SNPA address of the neighboring system.
isisISAdjNeighSys Type	.1.3.6.1.2.1.138 .1.6.1.1.5	The type of the neighboring system.
isisISAdjNeighSys ID	.1.3.6.1.2.1.138 .1.6.1.1.6	The system ID of the neighboring Intermediate System.

Table 124. Supported OIDs from ISIS-MIB

Name	OID	Description
isisISAdjNbrExte ndedCircID	.1.3.6.1.2.1.138 .1.6.1.1.7	The 4-byte <i>Extended Circuit ID</i> learned from the Neighbor during 3-way handshake, or 0.

Generic information about the *IS-IS* link discovery process can be found in the *IS-IS Information* box on the *Node Detail Page* of the device. Information gathered from this OIDs will be stored in the following database table:




Figure 40. Database tables related to IS-IS discovery

ISIS Topology Updater provide ISIS OnmsTopology consolidating Is-IS data collected by *ISIS Collector* only full bidirectional connections between two ISIS supported devices become *Edges*. *Node A* and *Node B* are connected by an *ISIS Edge* if and only if there is a *ISIS link* in *Node A* to *Node B* and viceversa.

[1] Wikipedia LLDP: https://en.wikipedia.org/wiki/Link_Layer_Discovery_Protocol

Chapter 17. OpenTracing

17.1. Introduction

OpenTracing enables distributed tracing which makes it possible to monitor RPCs or transactions across process boundaries. This functionality can be leveraged to help track and diagnose communication problems that may arise in distributed deployments of *OpenNMS Meridian* that leverage *Minion* and/or *Sentinel. OpenNMS Meridian* currently supports Jaeger which implements the OpenTracing API.

OpenTracing is now supported on RPC calls between *Minion* and *OpenNMS Meridian* and Sink API calls (including flows) between *Minion* and *Sentinel* or *OpenNMS Meridian*.

17.1.1. Enabling Tracing on OpenNMS Meridian

By default the tracing instrumentation *OpenNMS Meridian* is disabled (a no-op tracer is used.)

Enable tracing with Jeager as follows:

```
echo 'org.opennms.core.tracer=jaeger' >>
"$OPENNMS_HOME/etc/opennms.properties.d/jaeger.properties"
echo 'opennms-core-tracing-jaeger' >> "$OPENNMS_HOME/etc/featuresBoot.d/jaeger.boot"
```

Restart OpenNMS Meridian to apply the changes.

Additional Jaeger tracing options can be added to the jaeger.properties file specified above. Available configuration options are listed here.

17.1.2. Enabling Tracing on Minion

Enable tracing with Jaeger on *Minion* by installing the opennms-core-tracing-jaeger feature.

```
echo 'opennms-core-tracing-jaeger' >> "$MINION_HOME/etc/featuresBoot.d/jaeger.boot"
```



Uninstalling the opennms-core-tracing-jaeger feature at runtime is not yet supported. To disable tracing with Jaeger, remove the reference from the features boot file and restart *Minion*.

Additional Jaeger tracing options can be added to \$MINION_HOME/etc/system.properties on *Minion*. Available configuration options are listed here.

17.1.3. Enabling Tracing on Sentinel

Enable tracing with Jaeger on *Sentinel* by installing the opennms-core-tracing-jaeger feature.



Either sentinel-flows or sentinel-telemetry need to be installed before installing opennms-core-tracing-jaeger feature. Uninstalling the opennms-core-tracing-jaeger feature at runtime is not yet supported. To disable tracing with Jaeger, remove the reference from the features boot file and restart *Sentinel*.

Additional Jaeger tracing options can be added to **\$SENTINEL_HOME/etc/system.properties** on *Sentinel*. Available configuration options are listed here.

Chapter 18. Operation

18.1. HTTPS / SSL

This chapter covers the possibilities to configure *OpenNMS Meridian* to protect web sessions with HTTPS and also explains how to configure *OpenNMS Meridian* to establish secure connections.



In order to use HTTPS the Java command line tool keytool is used. It is automatically shipped with each JRE installation. More details about the keytool can be found at the official documentation.

18.1.1. Standalone HTTPS with Jetty

To configure *OpenNMS Meridian* to protect web sessions with HTTPS, see How to setup SSL with Jetty.

18.1.2. OpenNMS Meridian as HTTPS client

To establish secure HTTPS connections within Java one has to setup a so called *Java Trust Store*.

The *Java Trust Store* contains all certificates a Java application should trust when making connections as a client to a server.

Setup Java Trust Store

To setup the Java Trust Store the following command can be issued.



If you do not have a *Java Trust Store* setup yet, it is created automatically.

Import a certificate to the Java Trust Store

```
keytool \
  -import \ ①
  -v \ ②
  -trustcacerts \ ③
  -alias localhost \ ④
  -file localhost.cert \ ⑤
  -keystore /$OPENNMS_HOME/etc/trust-store.jks ⑥
```

- ① Define to import a certificate or a certificate chain
- 2 Use verbose output
- ③ Define to trust certificates from cacerts
- ④ The alias for the certificate to import, e.g. the common name
- ⑤ The certificate to import
- 6 The location of the Java Trust Store

If you create a new *Java Trust Store* you are asked for a password to protect the *Java Trust Store*. If you update an already existing *Java Trust Store* please enter the password you chose when creating the *Java Trust Store* initially.

Download existing public certificate

To Download an existing public certificate the following command can be issued.

Download an existing public certificate

```
openssl \
s_client \ ①
-showcerts \ ②
-connect localhost:443 \ ③
-servername localhost \ ④
< /dev/null \ ⑤
> localhost.cert ⑥
```

① Use SSL/TLS client functionality of openssl.

- ② Show all certificates in the chain
- ③ PORT:HOST to connect to, e.g. localhost:443
- ④ This is optional, but if you are serving multiple certificates under one single ip address you may define a server name, otherwise the ip of localhost:PORT certificate is returned which may not match the requested server name (mail.domain.com, opennms.domain.com, dns.domain.com)
- 5 No input
- ⁶ Where to store the certificate.

Configure OpenNMS Meridian to use the defined Java Trust Store

To setup *OpenNMS Meridian* to use the defined *Java Trust Store* the according javax.net.ssl.trustStore* properties have to be set. Open \$OPENNMS_HOME/etc/opennms.properties and add the properties javax.net.ssl.trustStore and javax.net.ssl.trustStorePassword as shown below.

\$OPENNMS_HOME/etc/opennms.properties snippet to define a Java Trust Store

javax.net.ssl.trustStore=/\$OPENNMS_HOME/etc/trust-store.jks ①
javax.net.ssl.trustStorePassword=change-me ②

1 The location of the Java Trust Store

2 The password of the Java Trust Store

For more details on the Java build-in SSL System properties have a look at chapter Debugging / Properties.



Each time you modify the *Java Trust Store* you have to restart *OpenNMS Meridian* to have the changes take effect.

18.1.3. Differences between Java Trust Store and Java Key Store

The *Java Trust Store* is used to determine whether a remote connection should be trusted or not, e.g. whether a remote party is who it claims to be (client use case).

The *Java Key Store* is used to decide which authentication credentials should be sent to the remote host for authentication during SSL handshake (server use case).

For more details, please check the JSSE Reference Guide.

18.1.4. Debugging / Properties

If you encounter issues while using HTTPS it might be useful to enable debugging or use one of the build-in Java System Properties to configure the proper use of SSL.

System Property Name	Description
javax.net.ssl.keyStore	Location of the Java keystore file containing an application process's own certificate and private key. On Windows, the specified pathname must use forward slashes, /, in place of backslashes, \.
javax.net.ssl.keyStorePassword	Password to access the private key from the keystore file specified by javax.net.ssl.keyStore. This password is used twice: to unlock the keystore file (store password) and to decrypt the private key stored in the keystore (key password). In other words, the JSSE framework requires these passwords to be identical.
javax.net.ssl.keyStoreType	(Optional) For Java keystore file format, this property has the value jks (or JKS). You do not normally specify this property, because its default value is already jks.
javax.net.ssl.trustStore	Location of the Java keystore file containing the collection of CA certificates trusted by this application process (trust store). On Windows, the specified pathname must use forward slashes, /, in place of backslashes, \. If a trust store location is not specified using this property, the Sun JSSE implementation searches for and uses a keystore file in the following locations (in order): \$JAVA_HOME/lib/security/jssecacerts and \$JAVA_HOME/lib/security/cacerts

Table 125. Java build-in System Properties (Source)

System Property Name	Description
javax.net.ssl.trustStorePassword	Password to unlock the keystore file (store password) specified by javax.net.ssl.trustStore.
javax.net.ssl.trustStoreType	(Optional) For Java keystore file format, this property has the value jks (or JKS). You do not normally specify this property, because its default value is already jks.
javax.net.debug	To switch on logging for the SSL/TLS layer, set this property to ssl. More details about possible values can be found here.

18.2. Request Logging

HTTP requests logs for *Jetty* can be enabled by uncommenting the following snippet in etc/jetty.xml:



If you do not have a jetty.xml in the etc directory, you can start by copying the example from etc/examples/jetty.xml.

If you would like the include the usernames associated with the requests in the log file, you must also uncomment the following snippet in jetty-webapps/opennms/WEB-INF/web.xml:

After restarting *OpenNMS Meridian*, requests logs of the following form should be available in logs/jetty-requests-*.log:

```
127.0.0.1 - - [02/Jun/2017:09:16:38 -0500] "GET / HTTP/1.1" 302 0 "-" "Mozilla/5.0
(X11; Fedora; Linux x86_64) AppleWebKit/537.36 (KHTML, like Gecko) Chrome/5
8.0.3029.110 Safari/537.36"
127.0.0.1 - anonymousUser [02/Jun/2017:09:16:39 -0500] "GET /opennms/ HTTP/1.1" 302 0
"-" "Mozilla/5.0 (X11; Fedora; Linux x86_64) AppleWebKit/537.36 (KHTML, like Gecko)
Chrome/58.0.3029.110 Safari/537.36"
127.0.0.1 - admin [02/Jun/2017:09:16:46 -0500] "POST
/opennms/rest/datachoices?action=enable HTTP/1.1" 200 0
"http://127.0.0.1:8980/opennms/index.jsp" "Mozilla/5.0 (X11; Fedora; Linux x86_64)
AppleWebKit/537.36 (KHTML, like Gecko) Chrome/58.0.3029.110 Safari/537.36"
127.0.0.1 - rtc [02/Jun/2017:09:16:45 -0500] "POST
/opennms/rtc/post/DNS+and+DHCP+Servers HTTP/1.1" 200 35 "-" "Java/1.8.0_121"
```

18.3. Geocoder Service

The *Geocoder Service* is used to resolve geolocation information within *OpenNMS Meridian*. *OpenNMS Meridian* supports several *Geocoder Services*. By default geolocation resolution is disabled.



To enable or configure the *Geocoder Service* please use the web based configuration tool. This can be found in the administration section: $Admin \rightarrow Configure Geocoder Service$

The currently used *Geocoder Service* is configured via the property activeGeocoderId in etc/org.opennms.features.geocoder.cfg.

18.3.1. Google

The Google Geocoder API requires at least an apiKey or a clientId and signature. For more details please refer to the official documentation.

The following properties in etc/org.opennms.features.geocoder.google.cfg are supported:

Property	Туре	Requi red	Default	Description
аріКеу	Strin g	yes	empty string	Is only required if useEnterpriseCredentials is false. The apiKey provided by the Google Cloud Platform.
useEnterpriseC redentials	Boole an	NO	false	If authentication with clientId and signature is required, set this to true.
clientId	Strin g	yes	empty string	Is only required if useEnterpriseCredentials is true The Google Geocoder API Client ID.
signature	Strin g	yes	empty string	The Google Geocoder API Signature.
useSystemProxy	Boole an	NO	false	Should the system wide proxy settings be used? The system proxy settings can be configured in opennms.conf
timeout	Integ er	NO	500	The connection timeout in milliseconds the Geocoder tries to resolve a single geolocation.

18.3.2. Mapquest

For more details please refer to the official documentation.

The following properties in etc/org.opennms.features.geocoder.mapquest.cfg are supported:

Prope rty	Тур е	Req uire d	Default	Description
аріКеу	Stri ng	yes	empty string	The apiKey.
url	Stri ng	yes	http://www.mapquestapi.com/geocoding/ v1/address?format=json&key={apiKey}& maxResults=1&location={query}	The url template for the Mapquest Geocoder API. The {apiKey} and {query} strings are substituted before making the request.
useSys temPro xy	Bool ean	ΠΟ	false	Should the system wide proxy settings be used? The system proxy settings can be configured in opennms.conf

18.3.3. Nominatim

For more details please refer to the official documentation and ensure to check out the Nominatim Usage Policy before using the Geocoder Service.

The following properties in etc/org.opennms.features.geocoder.nominatim.cfg are supported:

Prope rty	Тур e	Required	Default	Description
accept UsageT erms	Boo lea n	yes	false	In order to use the Nominatim Geocoder Service the Nominatim Usage Policy must be accepted. Set this to true to agree to their terms.
url	Str ing	yes	<pre>https://nominatim.openstreetmap .org/search?format=json& email={email}&limit=1&q={query}</pre>	The url template for the Nominatim Geocoder API. The {email} and {query} strings are substituted before making the request.
email	Str ing	yes	empty string	According to the official documentation, this should be provided in case you are making a large number of requests. Alternatively provide this information in the userAgent property.
refere r	Str ing	either referer or userAgent is required.	empty string	According to the Nominatim Usage Policy please provide either a referer or userAgent
userAg ent	Str ing	either referer or userAgent is required.	OpenNMS- NominatimGeocoderService/2.0	According to the Nominatim Usage Policy please provide either a referer or userAgent
useSys temPro xy	Boo lea n	NO	false	Should the system wide proxy settings be used? The system proxy settings can be configured in system properties

18.4. newts-repository-converter: Rrd/Jrb to Newts migration utility

This utility can be used to migrate existing *RRDTool-* or *JRobin-*based data to a *Newts* cluster. This will be achieved by traversing the share/rrd directory and its subdirectories, reading the data and properties files and persisting this data to *Newts*.

18.4.1. Migration

The following suggestions try to minimize the data collection gap that occur when reconfiguring *OpenNMS Meridian* for a different storage strategy. First, we determine the parameters needed for migration of the existing data. After that, we reconfigure *OpenNMS Meridian* to persists all new collected data to *Newts* storage. Finally, the *Rrd-* or *JRobin*-based data will be converted and persisted to *Newts* using the *newts-repository-converter* utility.

Prerequisites

- Working OpenNMS Meridian installation with *RRDTool-* or *JRobin-*based storage strategy configured.
- Installed and working *Newts* cluster reachable by the *OpenNMS Meridian* instance.

Migration plan

- 1. Check and write down the values for the following options in your opennms.properties file. You will need these information later to invoke the *newts-repository-converter* utility.
 - a. File etc/opennms.properties:
 - Check for the entry org.opennms.rrd.storeByGroup whether storeByGroup is enabled.
 - Check for the entry rrd.base.dir for the location where *Rrd* or *Jrb* files are stored.
 - Check for the entry rrd.binary for the location of the *RRDTool* binary.
 - b. File etc/rrd-configuration.properties:
 - Check for the entry org.opennms.rrd.strategyClass whether JRobinRrdStrategy (*JRobin*) or JniRrdStrategy / MultithreadedJniRrdStrategy (*RRDTool*) is used.
- 2. Stop your OpenNMS Meridian instance.
- 3. Reconfigure *OpenNMS Meridian* to persist data to *Newts* so, when correctly configured all new samples will be persisted into *Newts* after *OpenNMS Meridian* is started. Note, that the converter assumes storeByForeignSource to be enabled.
- 4. Start your OpenNMS Meridian instance.
- 5. Use the *newts-repository-converter* utility to convert the existing data to *Newts* by specifying the options that correspond to the information gathered during step #1.

This procedure will minimize the data collection gap to the time needed to reconfigure *OpenNMS Meridian* for *Newts* storage.



The *newts_converter* utility needs the path to the base directory of your *OpenNMS Meridian* instance for reading the configuration files. For instance the utility needs the datasource configuration during the migration process to query the database to lookup node data.

18.4.2. Usage

The utility is installed by default and its wrapper script is located in the *\${OPENNMS_HOME}/bin* directory.

- \$ cd /path/to/opennms/bin
- \$./newts-repository-converter



When invoked without parameters the usage and help information is printed.

The *newts-repository-converter* tool provide the following options and parameters:

Short- option	Long- option	Description	Default
h	help	Prints help and usage information	false
0	onms-home	OpenNMS Meridian Home Directory	/opt/opennms
Γ	rrd-dir	The path to the RRD data	ONMS- HOME/share/rrd
t	rrd-tool	Whether to use rrdtool or JRobin	
Т	rrd-binary	The binary path to the rrdtool command (only used if rrd-tool is set)	/usr/bin/rrdtool
S	store-by- group	Whether store by group was enabled or not	
Π	threads	Number of conversion threads	defaults to number of CPUs

18.4.3. Example 1: convert Rrd-based data with storeByGroup enabled

The following example shows how to convert *RRDTool*-based data that was stored with storeByGroup enabled. The OpenNMS Meridian home is /opt/opennms, the data directory is /opt/opennms/share/rrd and the *RRDTool* binary located at /usr/local/bin/rrdtool. This program call will use 16 concurrent threads to convert the *Rrd* files.

\$./newts-repository-converter -t true -s true -T /usr/local/bin/rrdtool -n 16
<output omitted>

18.4.4. Example 2: convert JRobin-based data with storeByGroup disabled

The following example shows how to convert *JRobin*-based data located in the directory /mnt/opennms/rrd that was collected with storeByGroup disabled. This program call will use 8 concurrent threads to convert the *Jrb* files.

```
$ ./newts-repository-converter -t false -s false -r /mnt/opennms/rrd -n 8
<output omitted>
```

18.5. Configuration Tester

To identify configuration problems there is a config-tester located in **\$OPENNMS_HOME/bin/**. Use **config-tester** to check configuration files. Type **-1**, **--list** to view the list of files checked. It prints issues into **output.log**. The tool can be used while OpenNMS is running to check configuration beforehand.

Possible Parameters:

```
$OPENNMS HOME/bin/config-tester -h
usage: config-tester -a
                    OR: config-tester [config files]
                    OR: config-tester -l
                    OR: config-tester -h
                      check all supported configuration files
-a,--all
                      print this help and exit
-h,--help
-i,--ignore-unknown
                     ignore unknown configuration files and continue
                      processing
-1,--list
                      list supported configuration files and exit
                      list each configuration file as it is tested
-v,--verbose
```

18.6. Newts

This section describes how to configure *OpenNMS Meridian* to use *Newts* and how to use *OpenNMS Meridian* to monitor your Cassandra cluster.

18.6.1. Configuration

Enabling Newts

OpenNMS Meridian can be configured to use Newts by setting the following property in in \${OPENNMS_HOME}/etc/opennms.properties:

```
org.opennms.timeseries.strategy=newts
```

It is also highly recommended that resources stored in *Newts* are referenced by their foreign source and foreign ID, as opposed to their database ID. To this end, the following property should also be set in the same file:

org.opennms.rrd.storeByForeignSource=true

With these set, *OpenNMS Meridian* will begin persisting metrics using the *Newts* engine when restarted.

Additional configuration options are presented in the next section.

Configuration Reference

The following properties, found in *\${OPENNMS_HOME}/etc/opennms.properties*, can be used to configure and tune *Newts*.

General

Name	Default	Description	
org.opennms.newts.config.keys pace	newts	Name of the keyspace to use.	
org.opennms.newts.config.host name	localhost	IP address or hostnames of the Cassandra nodes. Multiple hosts can be separated by a comma.	
org.opennms.newts.config.port	9042	CQL port used to connect to the Cassandra nodes.	
org.opennms.newts.config.user name	cassandra	Username to use when connecting to Cassandra via CQL.	
org.opennms.newts.config.pass word	cassandra	Password to use when connecting to Cassandra via CQL.	
org.opennms.newts.config.ssl	false	Enable/disable SSL when connecting to Cassandra.	
org.opennms.newts.config.core -connections-per-host	Driver default	Core number of connections per host.	
org.opennms.newts.config.max- connections-per-host	Driver default	Maximum number of connections per host.	
org.opennms.newts.config.max- requests-per-connection	Driver default	Maximum amount of requests that can be in-flight or single connection at the same time.	
org.opennms.newts.config.read _consistency	ONE	Consistency level used for <i>read</i> operations. See Configuring data consistency for a list of available options.	
org.opennms.newts.config.writ e_consistency	ANY	Consistency level used for <i>write</i> operations. See Configuring data consistency for a list of available options.	
org.opennms.newts.config.max_ batch_size	16	Maximum number of records to insert in a single transaction. Limited by the size of the Cassandra cluster's batch_size_fail_threshold_in_kb property.	
org.opennms.newts.config.ring _buffer_size	8192	Maximum number of records that can be held in the ring buffer. Must be a power of two.	
org.opennms.newts.config.writ er_threads	16	Number of threads used to pull samples from the ring buffer and insert them into Newts.	
org.opennms.newts.config.ttl	31540000	Number of seconds after which samples will automatically be deleted. Defaults to one year.	
org.opennms.newts.config.reso urce_shard	604800	Duration in seconds for which samples will be stored at the same key. Defaults to 7 days in seconds.	
org.opennms.newts.query.minim um_step	300000	Minimum step size in milliseconds. Used to prevent large queries.	

Name	Default	Description		
org.opennms.newts.query.inter val_divider	2	If no interval is specified in the query, the step will be divided into this many intervals when aggregating values.		
org.opennms.newts.query.heart beat	450000	Duration in milliseconds. Used when no heartbeat is specified. Should generally be 1.5x your largest collection interval.		
org.opennms.newts.query.paral lelism	Number of cores	Maximum number of threads that can be used to compute aggregates. Defaults to the number of available cores.		
org.opennms.newts.config.cach e.strategy	See bellow	Canonical name of the class used for resource level caching. See the table bellow for all of the available options.		
org.opennms.newts.config.cach e.max_entries	8192	Maximum number of records to keep in the cache when using an in-memory caching strategy.		
org.opennms.newts.nan_on_coun ter_wrap	false	Disables the processing of counter wraps, replacing these with NaNs instead.		
org.opennms.newts.config.cach e.priming.disable	false	Disables the cache primer, which pre-emptively loads the cache with indexed resources on start-up.		
org.opennms.newts.config.cach e.priming.block_ms	120000	Block startup for this many milliseconds while waiting for the cache to be primed. Set this value to -1 to disable blocking. Set this value to 0 to block indefinitely waiting for all of the records to be read.		

Available caching strategies include:

Name	Class	Defaul t
In-Memory Cache	org.opennms.netmgt.newts.support.GuavaSearchableResourceMetadataCac he	Y
Redis-based Cache	org.opennms.netmgt.newts.support.RedisResourceMetadataCache	Ν

Redis Cache

When enabled, the following options can be used to configure the Redis-based cache.

Name	Default	Description
org.opennms.newts.config.cache.redis_hostna me	localhos t	IP address of hostname of the <i>Redis</i> server.

Name	Default	Description
org.opennms.newts.config.cache.redis_port	6379	TCP port used to connect to the <i>Redis</i> server.

Recommendations

You will likely want to change the values of cache.max_entries and the ring_buffer_size to suit your installation.

Meta-data related to resources are cached in order to avoid writing redundant records in *Cassandra*. If you are collecting data from a large number of resources, you should increase the cache.max_entries to reflect the number of resources you are collecting from, with a suitable buffer.

The samples gathered by the collectors are temporarily stored in a ring buffer before they are persisted to *Cassandra* using *Newts*. The value of the ring_buffer_size should be increased if you expect large peaks of collectors returning at once or latency in persisting these to *Cassandra*. However, note that the memory used by the ring buffer is reserved, and larger values may require an increased heap size.

Cache priming is used to help reduce the number of records that need to be indexed after restarting *OpenNMS Meridian*. This works by rebuilding the cache using the index data that has already been persisted in Cassandra. If you continue to see large spikes of index related inserts after rebooting you may want to consider increasing the amount of time spent priming the cache.

18.6.2. Cassandra Monitoring

This section describes some of the metrics *OpenNMS Meridian* collects from a *Cassandra* cluster.

\bigcirc

JMX must be enabled on the *Cassandra* nodes and made accessible from _*OpenNMS Meridian* in order to collect these metrics. See Enabling JMX authentication for details.

\mathbf{O}

The data collection is bound to the agent IP interface with the service name *JMX*-*Cassandra*. The *JMXCollector* is used to retrieve the *MBean* entities from the *Cassandra* node.

Client Connections

The number of active client connections from org.apache.cassandra.metrics.Client are collected:

Name	Description
connectedNativeClients	Metrics for connected native clients
connectedThriftClients	Metrics for connected thrift clients

Compaction Bytes

The following compaction manager metrics from org.apache.cassandra.metrics.Compaction are collected:

Name	Description
BytesCompacted	Number of bytes compacted since node started

Compaction Tasks

The following compaction manager metrics from org.apache.cassandra.metrics.Compaction are collected:

Name	Description
CompletedTasks	Estimated number of completed compaction tasks
PendingTasks	Estimated number of pending compaction tasks

Storage Load

The following storage load metrics from org.apache.cassandra.metrics.Storage are collected:

Nam e	Description
Load	Total disk space (in bytes) used by this node

Storage Exceptions

The following storage exception metrics from org.apache.cassandra.metrics.Storage are collected:

Name	Description
Exceptions	Number of unhandled exceptions since start of this Cassandra instance

Dropped Messages

Measurement of messages that were *DROPPABLE*. These ran after a given timeout set per message type so was thrown away. In *JMX* these are accessible via org.apache.cassandra.metrics.DroppedMessage. The number of dropped messages in the different message queues are good indicators whether a cluster can handle its load.

Name	Stage	Description
Mutation	MutationStage	If a write message is processed after its timeout (write_request_timeout_in_ms) it either sent a failure to the client or it met its requested consistency level and will relay on hinted handoff and read repairs to do the mutation if it succeeded.

Name	Stage	Description
Counter_Mut ation	MutationStage	If a write message is processed after its timeout (write_request_timeout_in_ms) it either sent a failure to the client or it met its requested consistency level and will relay on hinted handoff and read repairs to do the mutation if it succeeded.
Read_Repair	MutationStage	Times out after write_request_timeout_in_ms.
Read	ReadStage	Times out after read_request_timeout_in_ms. No point in servicing reads after that point since it would of returned error to client.
Range_Slice	ReadStage	Times out after range_request_timeout_in_ms.
Request_Res ponse	RequestRespons eStage	Times out after request_timeout_in_ms. Response was completed and sent back but not before the timeout

Thread pools

Apache Cassandra is based on a so called *Staged Event Driven Architecture* (SEDA). This seperates different operations in stages and these stages are loosely coupled using a messaging service. Each of these components use queues and thread pools to group and execute their tasks. The documentation for *Cassandra* Thread pool monitoring is originated from Pythian Guide to Cassandra Thread Pools.

Table 126. Collected metrics for Thread Pools

Name	Description
ActiveTasks	Tasks that are currently running
CompletedTasks	Tasks that have been completed
CurrentlyBlockedTasks	Tasks that have been blocked due to a full queue
PendingTasks	Tasks queued for execution

Memtable FlushWriter

Sort and write *memtables* to disk from org.apache.cassandra.metrics.ThreadPools. A vast majority of time this backing up is from over running disk capability. The sorting can cause issues as well however. In the case of sorting being a problem, it is usually accompanied with high load but a small amount of actual flushes (seen in cfstats). Can be from huge rows with large column names, i.e. something inserting many large values into a *CQL* collection. If overrunning disk capabilities, it is recommended to add nodes or tune the configuration.



Alerts: pending > 15 || blocked > 0

Memtable Post Flusher

Operations after flushing the *memtable*. Discard commit log files that have had all data in them in *sstables*. Flushing non-cf backed secondary indexes.



Anti Entropy Stage

Repairing consistency. Handle repair messages like merkle tree transfer (from Validation compaction) and streaming.



Alerts: pending > 15 || blocked > 0

Gossip Stage

Post 2.0.3 there should no longer be issue with pending tasks. Instead monitor logs for a message:

Gossip stage has {} pending tasks; skipping status check ...

Before that change, in particular older versions of 1.2, with a lot of nodes (100+) while using vnodes can cause a lot of CPU intensive work that caused the stage to get behind. Been known to of been caused with out of sync schemas. Check *NTP* working correctly and attempt nodetool resetlocalschema or the more drastic deleting of system column family folder.



Migration Stage

Making schema changes



Alerts: pending > 15 || blocked > 0

MiscStage

Snapshotting, replicating data after node remove completed.



Alerts: pending > 15 || blocked > 0

Mutation Stage

Performing a local including:

- insert/updates
- Schema merges
- commit log replays
- hints in progress

Similar to ReadStage, an increase in pending tasks here can be caused by disk issues, over loading a system, or poor tuning. If messages are backed up in this stage, you can add nodes, tune hardware and configuration, or update the data model and use case.



Read Stage

Performing a local read. Also includes deserializing data from row cache. If there are pending values this can cause increased read latency. This can spike due to disk problems, poor tuning, or over loading your cluster. In many cases (not disk failure) this is resolved by adding nodes or tuning the system.



Alerts: pending > 15 || blocked > 0

Request Response Stage

When a response to a request is received this is the stage used to execute any callbacks that were created with the original request.



Alerts: pending > 15 || blocked > 0

Read Repair Stage

Performing read repairs. Chance of them occurring is configurable per column family with read_repair_chance. More likely to back up if using CL.ONE (and to lesser possibly other non-CL.ALL queries) for reads and using multiple data centers. It will then be kicked off asynchronously outside of the queries feedback loop. Note that this is not very likely to be a problem since does not happen on all queries and is fast providing good connectivity between replicas. The repair being droppable also means that after write_request_timeout_in_ms it will be thrown away which further mitigates this. If pending grows attempt to lower the rate for high read CFs.



Alerts: pending > 15 || blocked > 0

JVM Metrics

Some key metrics from the running Java virtual machine are also collected:

java.lang:type=Memory

The memory system of the Java virtual machine. This includes heap and non-heap memory

java.lang:type=GarbageCollector,name=ConcurrentMarkSweep

Metrics for the garbage collection process of the Java virtual machine



If you use *Apache Cassandra* for running *Newts* you can also enable additional metrics for the *Newts* keyspace.

18.6.3. Newts Monitoring

This section describes the metrics *OpenNMS Meridian* collects for monitoring the *Newts* keyspace from org.apache.cassandra.metrics.Keyspace on an *Cassandra* node.

JMX must be enabled on the *Cassandra* nodes and made accessible from _*OpenNMS Meridian* in order to collect these metrics. See Enabling JMX authentication for details.

The data collection is bound to the agent IP interface with the service name *JMX-Cassandra-Newts*. The *JMXCollector* is used to retrieve the *MBean* entities from the *Cassandra* node.

All Memory Table Data Size

Name	Description
AllMemtablesLiveData Size	Total amount of live data stored in the memtables (2i and pending flush memtables included) that resides off-heap, excluding any data structure overhead
AllMemtablesOffHeapD ataSize	Total amount of data stored in the memtables (2i and pending flush memtables included) that resides off-heap.
AllMemtablesOnHeapDa taSize	Total amount of data stored in the memtables (2i and pending flush memtables included) that resides on-heap.

Memtable Switch Count

Name	Description
MemtableSwitchCount	Number of times flush has resulted in the memtable being switched out.

Memtable Columns Count

Name	Description
MemtableColumnsCount	Total number of columns present in the memtable.

Memory Table Data Size

Name	Description	
MemtableLiveDataSi ze	Total amount of live data stored in the memtable, excluding any data structure overhead	
MemtableOffHeapDat aSize	eOffHeapDat Total amount of data stored in the memtable that resides off-heap, including column related overhead and partitions overwritten.	
MemtableOnHeapData Size	Total amount of data stored in the memtable that resides on-heap, including column related overhead and partitions overwritten.	

Read and Write Latency

Name	Description
ReadTotalLatency	Local read metrics.
WriteTotalLatency	Local write metrics.

Range Latency

Name	Description
RangeLatency 99th Percentile	Local range slice metrics 99th percentile.

Latency

Name	Descriptio n
CasCommitTotalLatency	
CasPrepareTotalLatency	
CasProposeTotalLatency	

Bloom Filter Disk Space

Name	Description
BloomFilterDiskSpaceUsed	Disk space used by bloom filter

Bloom Filter Off Heap Memory

Name	Description	
BloomFilterOffHeapMemoryUsed	Off heap memory used by bloom filter	

Newts Memory Used

Name	Description
CompressionMetadataOffHeapMemoryUsed	Off heap memory used by compression meta data
IndexSummaryOffHeapMemoryUsed	Off heap memory used by index summary

Pending

Name	Description	
PendingCompactions	Estimate of number of pending compactions for this column family	
PendingFlushes	Estimated number of tasks pending for this column family	

Disk Space

Name	Description
TotalDiskSpaceU sed	Total disk space used by <i>SSTables</i> belonging to this column family including obsolete ones waiting to be garbage collected.
LiveDiskSpaceUs ed	Disk space used by SSTables belonging to this column family

18.7. Timeseries Integration Layer

This section describes how to configure *OpenNMS Meridian* to use the *Time Series Integration Layer*.

Traditionally *OpenNMS Meridian* supports storing time series data in *RRD* files on disk or via *Newts* in *Cassandra*. These implementations require a deep knowledge of OpenNMS. It is hard to add another time series database.

With the rise of many new time series databases, we want to provide an easy way to support other time series databases with minimal effort. This lead to the development of the *Time Series Integration Layer*.

The *Time Series Integration Layer* allows users to integrate a new time series database via OSGi plugin.

Examples of time series plugins:

- In Memory
- InfluxDB
- TimescaleDB

18.7.1. Configuration

Enabling Time Series Integration Layer

OpenNMS Meridian can be configured to use the Time Series Integration Layer by setting the following property in *\${OPENNMS_HOME}/etc/opennms.properties*:

```
org.opennms.timeseries.strategy=integration
```

After activating the *Time Series Integration Layer*, you need to start an actual implementation. Do this via Karaf. Here is an example of how to activate the *in memory time series* plugin:

```
clone & build:
git clone git@github.com:opennms-forge/timeseries-integration-inmemory.git
mvn install
in Karaf shell:
bundle:install -s mvn:org.opennms.plugins.timeseries.inmemory/timeseries-inmemory-
plugin/1.0.0-SNAPSHOT
```

For specific instructions, check your plugin description.

We also highly recommend that you reference resources stored in the *Time Series Integration Layer* by their foreign source and foreign ID, as opposed to their database ID. To this end, set the following property in the same file:

```
org.opennms.rrd.storeByForeignSource=true
```

With these set, *OpenNMS Meridian* will begin persisting metrics using the *Time Series Integration Layer* when restarted.

Additional configuration options are presented in the next section.

Configuration Reference

The following properties, found in *\${OPENNMS_HOME}/etc/opennms.properties*, can be used to configure and tune the *Time Series Integration Layer*.

General

Name	Default	Description
org.opennms.timeseries.config .ring_buffer_size	8192	Maximum number of records that can be held in the ring buffer. Must be a power of two.
org.opennms.timeseries.config .writer_threads	16	Number of threads used to pull samples from the ring buffer and insert them into the Time Series Database.
org.opennms.timeseries.query. minimum_step	300000	Minimum step size in milliseconds. Used to prevent large queries.
org.opennms.timeseries.query. interval_divider	2	If no interval is specified in the query, the step will be divided into this many intervals when aggregating values.
org.opennms.timeseries.query. heartbeat	450000	Duration in milliseconds. Used when no heartbeat is specified. Should generally be 1.5x your largest collection interval.

Name	Default	Description
org.opennms.timeseries.query. parallelism	Number of cores	Maximum number of threads that can be used to compute aggregates. Defaults to the number of available cores.
cache.timeseriesPersisterMeta TagCache.expireAfterRead	300	Expiry time in seconds for MetaTagCache.
cache.timeseriesPersisterMeta TagCache.maximumSize	8192	Maximum size for MetaTagCache.
cache.timeseriesPersisterMeta TagCache.recordStats	true	Should cache statistics be exposed via JMX for MetaTagCache?
<pre>cache.timeseriesSearcherCache .expireAfterRead</pre>	300	Expiry time in seconds for TimeseriesSearcherCache.
<pre>cache.timeseriesSearcherCache .maximumSize</pre>	8192	Maximum size for TimeseriesSearcherCache.
<pre>cache.timeseriesSearcherCache .recordStats</pre>	true	Should cache statistics be exposed via JMX for TimeseriesSearcherCache?
cache.timeseriesMetaDataCache .expireAfterRead	300	Expiry time in seconds for TimeseriesMetaDataCache.
cache.timeseriesMetaDataCache .maximumSize	8192	Maximum size for TimeseriesMetaDataCache.
<pre>cache.timeseriesMetaDataCache .recordStats</pre>	true	Should cache statistics be exposed via JMX for TimeseriesMetaDataCache?

Recommendations

Caches have been introduced to improve performance. You might need to tune the cache settings to suit your needs. See parameters above.

Name	Description	
TimeseriesMetaDataCache	Caches metadata that uses OpenNMS Meridian internally.	
TimeseriesSearcherCache	Caches metrics by tag to improve the resource lookup.	
TimeseriesPersisterMetaTagC ache	Caches all additionally configured and resolved meta-tag values by resource.	

The samples gathered by the collectors are temporarily stored in a ring buffer before they are persisted to the *Time Series Integration Layer*. The value of the ring_buffer_size should be increased if you expect large peaks of collectors returning at once or latency in persisting these. However, note that the memory used by the ring buffer is reserved, and larger values may require an increased heap size.

Expose additional meta tags

Metrics that are stored via the time series plugin contain the minimal set of tags for *OpenNMS Meridian* to work. This might not be sufficient if the data is used outside of *OpenNMS Meridian* as well. Configure additional meta tags via \${OPENNMS_HOME}/etc/opennms.properties.

The configuration of the tags has the following form: prefix.tagKey=\${query expression}

- The prefix is: org.opennms.timeseries.tin.metatags.tag
- The tagKey can by an arbitrary string as long as it doesn't break the java property file syntax.
- The query expression allows to query the value. Hereby we can make use of the Meta-Data-DSL

```
Examples: org.opennms.timeseries.tin.metatags.tag.nodelabel=${node:label} org.opennms.timeseries.tin.metatags.tag.sysObjectID=${node:sys-object-id}
```

Expose categories by setting org.opennms.timeseries.tin.metatags.exposeCategories to true.

```
Example: org.opennms.timeseries.tin.metatags.exposeCategories=true will lead to:
Tag("cat_myFirstCategory", "myFirstCategory") Tag("cat_mySecondCategory", "mySecondCategory")
```

18.8. Daemon Configuration Files

Configuration changes require a restart of OpenNMS and some daemons are able to reload configuration changes triggered by a daemon reload event. This section gives an overview about all daemons and the related configuration files and which can be reloaded without restarting OpenNMS.

18.8.1. Eventd

Internal Daemon Name	Reload Event	
Eventd	<pre>uei.opennms.org/internal/reloadDaemonConfig -p 'daemonName Eventd'</pre>	

Table 127. Eventd configuration file overview

File	Restart Required	Reload Event	Description
eventd- configuration.x ml	yes	no	Configure generic behavior of <i>Eventd</i> , i.e. <i>TCP</i> and <i>UDP</i> port numbers with <i>IP addresses</i> to listen for <i>Events</i> and socket timeouts.
eventconf.xml	no	yes	Main configuration file for <i>Eventd</i> .
events/*	no	yes	Out-of-the-box, all files in this folder are included via include directives in eventconf.xml.

18.8.2. Notifd

Internal Daemon Name	Reload Event
Notifd	uei.opennms.org/internal/reloadDaemonConfig -p 'daemonName Notifd'

Table 128. Notifd configuration file overview

File	Restart Required	Reload Event	Description
notifd- configuration.xml	no	yes	Describes auto-acknowledge prefix, e.g. prefix "RESOLVED: " for nodeUp/nodeDown events.
<pre>notificationCommands .xml</pre>	no	no	Configuration for notification media, e.g. scripts, XMPP or HTTP Post, immediately applied.
notifications.xml	no	no	Event notification definitions and changes are immediately applied.
destinationPaths.xml	no	no	Contains paths for notification targets, e.g. JavaMail, XMPP or external scripts.
users.xml	no	no	Contain pager and address information for notification destination paths.
groups.xml	no	no	Groups can be used as target for notifications.
javamail- configuration.proper ties	no	no	Configuration to send notification mails via specific mail servers.

18.8.3. Pollerd

Internal Daemon Name	Reload Event
Pollerd	<pre>uei.opennms.org/internal/reloadDaemonConfig -p 'daemonName Pollerd'</pre>

<i>Table 129.</i>	Pollerd	configuration	file	overview
-------------------	---------	---------------	------	----------

File	Restart Required	Reload Event	Description
poller- configuration.x ml	yes	yes	Restart is required in case new monitors are created or removed. Reload Event loads changed configuration parameters of existing monitors.
response- graph.propertie s	no	no	Graph definition for response time graphs from monitors

File	Restart Required		Description
poll- outages.xml	no	yes	Can be reloaded with uei.opennms.org/internal/schedOutagesChanged

18.8.4. Syslogd

Internal Daemon Name	Reload Event
Syslogd	<pre>uei.opennms.org/internal/reloadDaemonConfig -p 'daemonName Syslogd'</pre>

Syslogd reload event stops and starts daemon and loads all the syslogd configuration changes.

Syslog daemon can be reloaded with following shell command on karaf.

\$ ssh -p 8101 admin@localhost
...
admin@opennms> opennms:reload-daemon syslogd

18.8.5. Trapd

Internal Daemon Name	Reload Event
Trapd	<pre>uei.opennms.org/internal/reloadDaemonConfig -p 'daemonName Trapd'</pre>

Trapd reload event stops and starts daemon and loads all the trapd configuration changes.

Trapd daemon can also be reloaded with following shell command on karaf.

\$ ssh -p 8101 admin@localhost
...
admin@opennms> opennms:reload-daemon trapd

Chapter 19. System Properties

The global behavior of *OpenNMS Meridian* is configured with properties files. Configuration can also affect the *Java Virtual Machine* under which *OpenNMS Meridian* runs. Changes in these properties files require a restart of *OpenNMS Meridian*. The configuration files can be found in $\{OPENNMS_HOME\}/etc$.

The priority for *Java system properties* is as follows:

- 1. Those set via the Java command line i.e. in opennms.conf via ADDITIONAL_MANAGER_OPTIONS
- 2. opennms.properties.d/*.properties
- 3. opennms.properties
- 4. libraries.properties
- 5. rrd-configuration.properties
- 6. bootstrap.properties

Property files in opennms.properties.d/ are sorted alphabetically.

To avoid conflicts with customized configurations, all custom properties can be added to one or more files in $OPENNMS_HOME/etc/opennms.properties.d/$. It is recommended to avoid modification of OpenNMS properties from the default installation. Create dedicated files with your customized properties in opennms.properties.d/.

19.1. Configuring system proxies

System proxy settings may be used with certain *OpenNMS Meridian* components via the use-systemproxy or useSystemProxy parameters. To configure system proxy servers, set some or all of the following properties:

Property	Defau lt	Description
http.proxyHost	None	Hostname or IP address of proxy server to use for plain HTTP requests
http.proxyPort	3128	TCP port of proxy server to use for plain HTTP requests
https.proxyHost	None	Hostname or IP address of proxy server to use for HTTPS requests
https.proxyPort	3128	TCP port of proxy server to use for HTTPS requests
http.nonProxyHost s	None	Pipe-separated list of hostnames or IP addresses which bypass HTTP proxying
https.nonProxyHos ts	None	Pipe-separated list of hostnames or IP addresses which bypass HTTPS proxying



Depending on the JVM in use, the properties http.proxyUser, http.proxyPassword, and their https.* equivalents *may* enable the use of proxy servers that require authentication.



Setting these properties may have unintended effects. Use with care.

Chapter 20. Ticketing

The ticketing integration allows *OpenNMS Meridian* to create trouble tickets in external systems. Tickets can be created and updated in response to new and/or resolved alarms.

To activate the ticketing integration, the following properties in \${OPENNMS_HOME}/etc/opennms.properties must be set accordingly:

Property	Default	Description
opennms.ticketer.plugin	NullTickete rPlugin	The plugin implementation to use. Each ticketer integration should define which value to set. The NullTicketerPlugin does nothing when attempting to create/update/delete tickets.
opennms.alarmTroubleTick etEnabled	false	Defines if the integration is enabled. If enabled various links to control the issue state is shown on the alarm details page.
opennms.alarmTroubleTi cketLinkTemplate	\${id}	A template to generate a link to the issue, e.g. http://issues.opennms.org/browse/\${id}

20.1. JIRA Ticketing Plugin

The JIRA Ticketing Plugin is used to create JIRA Issues in response to OpenNMS Meridian alarms.

20.1.1. Setup

First, you'll need to install the opennms-plugin-ticketer-jira package for your system. The JIRA ticketing plugin and its dependencies are not part of the core packages.

Now, in order to enable the plugin start by setting following property in \${OPENNMS_HOME}/etc/opennms.properties:

opennms.ticketer.plugin=org.opennms.netmgt.ticketd.OSGiBasedTicketerPlugin

Configure the plugin options by setting the following properties in \${OPENNMS_HOME}/etc/jira.properties:

Name	Description
jira.host	JIRA Server Url
jira.username	Username
jira.password	Password
jira.project	The key of the project to use. Use jira:list-projects command to determine the project key.

Name	Description
jira.type	The Issue Type Id to use when opening new issues. Use jira:list-issue-types command to determine the issue type id.
jira.resolve	Name of the transition to use when resolving issues
jira.reopen	Name of the transition to use when re-opening issues
jira.status.open	Comma-separated list of JIRA status names for which the ticket should be considered 'Open'
jira.status.close d	Comma-separated list of JIRA status names for which the ticket should be considered 'Closed'
jira.status.cance lled	Comma-separated list of JIRA status names for which the ticket should be considered 'Cancelled'
jira.cache.reload Time	The time in milliseconds it takes to reload the <i>fields cache</i> . This is required to prevent the plugin to read the issue type's meta data every time an issue is created. A value of 0 disables the cache. Default value is 300000 (5 minutes).



The transition names for resolve and reopen are typically found on buttons when looking at the ticket in JIRA



Either use opennms:jist-list-issue-types OSGI Command or https://confluence.atlassian.com/display/JIRA050/Finding+the+Id+for+Issue+Types for determining the appropriate issue type id.

Next, add jira-troubleticketer to the featuresBoot property in the \${OPENNMS_HOME}/etc/org.apache.karaf.features.cfg

Restart OpenNMS Meridian.

When OpenNMS Meridian has started again, login to the Karaf Shell and install the feature:

```
feature:install jira-troubleticketer
```

The plugin should be ready to use.

20.1.2. Jira Commands

The *JIRA Ticketing Plugin* provides various *OSGI Commands* which can be used on the *Karaf Shell* to help set up the plugin.

There are OSGI Commands to list all available projects, versions, components, groups, issue types and even more.

To list all available commands simply type help | grep jira in the Karaf Shell.

Afterwards you can type for example opennms:jira-list-projects --help to determine the usage of a command.

20.1.3. Custom fields

The *OpenNMS Meridian* Ticketer model is limited to the most common fields provided by all ticketing systems.

Besides the common fields creator, create date, description or subject, ticket system proprietary fields usually need to be set.

In some cases, even additional - so called - custom fields are defined.

In order to set these fields, the *JIRA Ticketing Plugin* provides the possibility to define those in the OpenNMS Ticket attributes which can be overwritten with the Usage of Drools.

To enable the Drools Ticketing integration, the following property in \${OPENNMS_HOME}/etc/opennms.properties must be set:

opennms.ticketer.servicelayer=org.opennms.netmgt.ticketd.DroolsTicketerServiceLayer

In addition the property in \${OPENNMS_HOME/etc/drools-ticketer.properties must point to a droolsticketer-rules.drl file:

drools-ticketer.rules-file=\${OPENNMS_HOME/etc/drools-ticketer-rules.drl

Finally a Drools Rule file named drools-ticketer-rules.drl must be placed in \${OPENNMS_HOME}/etc.

The following drools example snippet defines attributes to set custom fields:

```
// Set ticket defaults
rule "TicketDefaults"
salience 100
when
   $alarm : OnmsAlarm()
then
   ticket.setSummary($alarm.logMsg);
   ticket.setDetails($alarm.description);
   ticket.addAttribute("customfield_10111", "custom-value");
   ticket.addAttribute("customfield_10112", "my-location");
   ticket.addAttribute("customfield_10113", "some classification");
end
```

Fields must be referenced by their id. To identify the id of a field, the opennms:jira-list-fields command can be used. By default only custom fields are shown. The -s options allows to show all fields. This may be necessary if JIRA default values need to be set as well, e.g. the Component, the Reporter, the Asignee, etc. Even the project key or issue type can be defined differently than

originally in the jira.properties.

The *OpenNMS Ticketer Attribute* model only allows to set a String value. However the JIRA model is slightly different. Therefore each String value must be converted to a JIRA field type. The following table describes valid values for an OpenNMS attribute.

Туре	Description		
any	Any string.		
date	Any date in the format of YYYY-MM-DD.		
datetime	Any datetime in ISO 8601 format: YYYY-MM-DDThh:mm:ss.sTZD.		
group	The name of the group.		
user	The name of the user.		
project	The key of the project (e.g. NMS)		
version	The name of the version. To list all available versions, use jira:list-versions.		
string	Any string.		
option	The name of the option.		
issuetype	The name of the issuetpye, e.g. Bug. To list all issue types, use jira:list-issue- types.		
priority	The name of the priority, e.g. Major. To list all priorites, use jira:list-priorities.		
option-with- child	Either the name of the option, or a comma separated list (e.g. parent, child).		
number	Any valid number (e.g. 1000)		
аггау	If the type is array the value must be of the containing type. E.g. to set a custom field which defines multiple groups, the value jira-users, jira-administrators is mapped properly. The same is valid for versions: 18.0.3, 19.0.0.		

As described above the values are usually identified by their name instead of their id (projects are identified by their key). This is easier to read, but may break the mapping code, if for example the name of a component changes in the future. To change the mapping from name (or key) to id an entry in jira.properties must be made:

jira.attributes.customfield_10113.resolution=id

To learn more about the Jira REST API please consult the following pages:

- https://developer.atlassian.com/jiradev/jira-apis/jira-rest-apis/jira-rest-api-tutorials/jira-rest-api-example-create-issue#JIRARESTAPIExample-CreateIssue-MultiSelect
- https://docs.atlassian.com/jira/REST/cloud/

The following jira (custom) fields have been tested with jira version 6.3.15:

- Checkboxes
- Date Picker
- Date Time Picker
- Group Picker (multiple groups)
- Group Picker (single group)
- Labels
- Number Field
- Project Picker (single project)
- Radio Buttons
- Select List (cascading)
- Select List (multiple choices)
- Select List (single choice)
- Text Field (multi-line)
- Text Field (read only)
- Text Field (single line)
- URL Field
- User Picker (multiple user)
- User Picker (single user)
- Version Picker (multiple versions)
- Version Picker (single version)



All other field types are mapped as is and therefore may not work.

Examples

The following output is the result of the command opennms:jira-list-fields -h http://localhost:8080 -u admin -p testtest -k DUM -i Bug -s and lists all available fields for project with key DUM and issue type Bug:

Name	Id .	Custom	Туре
Affects Version/s	versions	false	аггау
Assignee	assignee	false	USEF
Attachment	attachment	false	аггау
Component/s	components	false	array (1)
Description	description	false	string
Environment	environment	false	string
Epic Link	customfield_10002	true	any
Fix Version/s	fixVersions	false	array 2
Issue Type	issuetype	false	issuetype ③
Labels	labels	false	аггау
Linked Issues	issuelinks	false	аггау
Priority	priority	false	priority 🕘
Project	project	false	project (5)
Reporter	reporter	false	user
Sprint	customfield_10001	true	аггау
Summary	summary	false	string
custom checkbox	customfield_10100	true	array 🌀
custom datepicker	customfield_10101	true	date

① Defined Components are core, service, web

- 2 Defined versions are 1.0.0 and 1.0.1
- ③ Defined issue types are Bug and Task
- ④ Defined priorities are Major and Minor
- ⑤ Defined projects are NMS and HZN
- 6 Defined options are yes, no and sometimes

The following snipped shows how to set the various custom fields:

```
ticket.addAttribute("components", "core,web"); ①
ticket.addAttribute("assignee", "ulf"); ②
ticket.addAttribute("fixVersions", "1.0.1"); ③
ticket.addAttribute("issueType", "Task"); ④
ticket.addAttribute("priority", "Minor"); ⑤
ticket.addAttribute("project", "HZN"); ⑥
ticket.addAttribute("customfield_10100", "yes,no"); ⑧
ticket.addAttribute("customfield_10101", "2016-12-06"); ⑨
```

- ① Sets the components of the created issue to core and web.
- ② Sets the Asignee of the issue to the user with login ulf.
- 3 Sets the fix version of the issue to 1.0.1
- ④ Sets the issue type to Task, overwriting the value of jira.type.
- **(5)** Sets the priority of the created issue to Minor.
- 6 Sets the project to HZN, overwriting the value of jira.project.

⑦ Sets the summary to Custom Summary, overwriting any previous summary.

8 Checks the checkboxes yes and no.

9 Sets the value to 2016-12-06.

20.1.4. Troubleshooting

When troubleshooting, consult the following log files:

- \${OPENNMS_HOME}/data/log/karaf.log
- \${OPENNMS_HOME}/logs/trouble-ticketer.log

You can also try the opennms:jira-verify OSGI Command to help identifying problems in your configuration.

20.2. Remedy Ticketing Plugin

The *Remedy Ticketing Plugin* is used to create requests in the BMC Remedy ARS Help Desk Module in response to *OpenNMS Meridian* alarms.

20.2.1. Remedy Product Overview

It's important to be specific when discussing Remedy, because BMC Remedy is a suite of products. The *OpenNMS Meridian* Remedy Ticketing Plugin requires the core Remedy ARS and the Help Desk Module. The Help Desk Module contains a Help Desk Interface Web Service, which serves as the endpoint for creating, updating, and fetching tickets.

The Help Desk Interface (HDI) Web Service requires extensive configuration for its basic operation, and may need additional customization to interoperate with the *OpenNMS Meridian* Remedy Ticketing Plugin. Contact your Remedy administrator for help with required configuration tasks.

20.2.2. Supported Remedy Product Versions

Currently supported Remedy product versions are listed below:

Product	Version		
Remedy ARS	7.6.04 Service Pack 2		
Help Desk Module	7.6.04 Service Pack 1		
HDI Web Service	Same as Help Desk Module		

20.2.3. Setup

The Remedy Ticketing Plugin and its dependencies are part of the *OpenNMS Meridian* core packages.

Start by enabling the plugin and the ticket controls in the *OpenNMS Meridian* web interface, by setting the following properties in {OPENNMS_HOME}/etc/opennms.properties:

opennms.ticketer.plugin=org.opennms.netmgt.ticketer.remedy.RemedyTicketerPlugin
opennms.alarmTroubleTicketEnabled = true

In the same file, set the property opennes.alarmTroubleTicketLinkTemplate to a value appropriate for constructing a link to tickets in the Remedy web interface. A sample value is provided but must be customized for your site; the token \${id} will be replaced with the Remedy ticket ID when the link is rendered.

Now configure the plugin itself by setting the following properties in \${OPENNMS_HOME}/etc/remedy.properties:

Name	Requi red	Description
remedy.username	requir ed	Username for authenticating to Remedy
remedy.password	requir ed	Password for authenticating to Remedy
remedy.authentication	option al	Authentication style to use
remedy.locale	option al	Locale for text when creating and updating tickets
remedy.timezone	option al	Timezone for interaction with Remedy
remedy.endpoint	requir ed	The endpoint URL of the HPD web service
remedy.portname	requir ed	The Port name of the HPD web service
remedy.createendpoint	requir ed	The endpoint location of the Create-HPD web service
remedy.createportname	requir ed	The Port name of the Create-HPD web service
remedy.targetgroups	option al	Colon-separated list of Remedy groups to which created tickets may be assigned ({group} below refers to values from this list)
remedy.assignedgroup.{grou p}	option al	Assigned group for the target group {group}
remedy.assignedsupportcomp any.{group}	option al	Assigned support company for the target group {group}

Name	Requi red	Description
<pre>remedy.assignedsupportorga nization.{group}</pre>	option al	Assigned support organization for the target group {group}
remedy.assignedgroup	requir ed	Default group to assign the ticket in case the ticket itself lacks information about a target assigned group
remedy.firstname	requir ed	First name for ticket creation and updating. Must exist in Remedy.
remedy.lastname	requir ed	Last name for ticket creation and updating. Must exist in Remedy.
remedy.serviceCI	requir ed	A valid Remedy Service CI for ticket creation
remedy.serviceCIReconID	requir ed	A valid Remedy Service CI Reconciliation ID for ticket creation
remedy.assignedsupportcomp any	requir ed	A valid default assigned support company for ticket creation
remedy.assignedsupportorga nization	requir ed	A valid default assigned support organization for ticket creation
remedy.categorizationtier1	requir ed	A valid categorization tier (primary) for ticket creation
remedy.categorizationtier2	requir ed	A valid categorization tier (secondary) for ticket creation
remedy.categorizationtier3	requir ed	A valid categorization tier (tertiary) for ticket creation
remedy.serviceType	requir ed	A valid service type for ticket creation
remedy.reportedSource	requir ed	A valid Reported Source for ticket creation
remedy.impact	requir ed	A valid value for Impact, used in ticket creation
remedy.urgency	requir ed	A valid value for Urgency, used in ticket creation
remedy.reason.reopen	requir ed	The reason code set in Remedy when the ticket is reopened in <i>OpenNMS Meridian</i>
remedy.resolution	requir ed	The reason code set in Remedy when the ticket is closed in <i>OpenNMS Meridian</i>

Name	Requi red	Description
remedy.reason.cancelled	-	The reason code set in Remedy when the ticket is cancelled in <i>OpenNMS Meridian</i>



The values for many of the required properties are site-specific; contact your Remedy administrator for assistance.

Restart OpenNMS Meridian.

The plugin should be ready to use. When troubleshooting, consult the following log files:

• \${OPENNMS_HOME}/logs/trouble-ticketer.log

20.3. TSRM Ticketing Plugin

The *TSRM Ticketing Plugin* is used to create TSRM incidents in response to *OpenNMS Meridian* alarms.

20.3.1. Setup

In order to enable the plugin start by setting following property in
\${OPENNMS_HOME}/etc/opennms.properties:

opennms.ticketer.plugin=org.opennms.netmgt.ticketd.OSGiBasedTicketerPlugin

Configure	the	plugin	options	by	setting	the	following	properties	in
\${OPENNMS_HC)ME}/etc	/tsrm.prop	erties:						

Name	Description
tsrm.url	TSRM Endpoint URL
tsrm.ssl.strict	Strict SSL Check (true/false)
tsrm.status.open	TSRM status for open ticket
tsrm.status.close	TSRM status for close ticket

Next, add tsrm-troubleticketer to the featuresBoot property in the \${OPENNMS_HOME}/etc/org.apache.karaf.features.cfg

Restart OpenNMS.

When *OpenNMS* has started again, login to the *Karaf Shell* and install the feature:

```
feature:install tsrm-troubleticketer
```

The plugin should be ready to use. When troubleshooting, consult the following log files:

- \${OPENNMS_HOME}/data/log/karaf.log
- \${OPENNMS_HOME}/logs/trouble-ticketer.log

20.3.2. Mapping OpenNMS Ticket with TSRM Incident

Following tables shows mapping between OpenNMS ticket and TSRM Incident

Ticket Field	TSRM Incident Field
id	TICKETID
state	STATUS
summary	DESCRIPTION
details	DESCRIPTIONLONGDESCRIPTION
user	REPORTEDBY

Below fields are not part of Ticket, they have to be added as attributes.

Ticket Field	TSRM Incident Field
affectedPerson	AFFECTEDPERSON
assetNum	ASSETNUM
classId	CLASS
classStructureId	CLASSSTRUCTUREID
commodity	COMMODITY
location	LOCATION
ownerGroup	OWNERGROUP
shsCallerType	SHSCALLERTYPE
shsReasonForOutage	SHSREASONFOROUTAGE
shsResolution	SHSRESOLUTION
shsRoomNumber	SHSROOMNUMBER
siteId	SITEID
source	source
statusIface	STATUSIFACE

Chapter 21. Enabling RMI

By default, the RMI port in the OpenNMS Meridian server is disabled, for security reasons. If you wish to enable it so you can access OpenNMS Meridian through jconsole, remote-manage OpenNMS Meridian, or use the remote poller over RMI, you will have to add some settings to the default OpenNMS Meridian install.

21.1. Enabling RMI

To enable the RMI port in OpenNMS Meridian, you will have to add the following to the \${OPENNMS_HOME}/etc/opennms.conf file. If you do not have an opennms.conf file, you can create it.

Configure remote JMX ADDITIONAL_MANAGER_OPTIONS="\$ADDITIONAL_MANAGER_OPTIONS -Dcom.sun.management.jmxremote.port=18980" ADDITIONAL_MANAGER_OPTIONS="\$ADDITIONAL_MANAGER_OPTIONS -Dcom.sun.management.jmxremote.local.only=false" ADDITIONAL_MANAGER_OPTIONS="\$ADDITIONAL_MANAGER_OPTIONS -Dcom.sun.management.jmxremote.authenticate=true" ADDITIONAL_MANAGER_OPTIONS="\$ADDITIONAL_MANAGER_OPTIONS -Dcom.sun.management.jmxremote.ssl=false" # Listen on all interfaces ADDITIONAL_MANAGER_OPTIONS="\$ADDITIONAL_MANAGER_OPTIONS -Dopennms.poller.server.serverHost=0.0.0.0" # Accept remote RMI connections on this interface ADDITIONAL_MANAGER_OPTIONS="\$ADDITIONAL_MANAGER_OPTIONS

-Djava.rmi.server.hostname=<your-server-ip-address>"

This tells OpenNMS Meridian to listen for RMI on port 18980, and to listen on all interfaces. (Originally, RMI was only used for the Remote Poller, so despite the porperty name mentioning the "opennms poller server" it applies to RMI as a whole.) Note that you *must* include the -Djava.rmi.server.hostname= option or OpenNMS Meridian will accept connections on the RMI port, but not be able to complete a valid connection.

Authentication will only be allowed for users that are in the admin role (i.e. ROLE_ADMIN), or the jmx role (i.e. ROLE_JMX). To make a user an admin, be sure to add only the ROLE_ADMIN role to the user in users.xml. To add the jmx role to the user, add the ROLE_JMX role to the user in users.xml, and also the ROLE_USER role if is required to provide access to the WebUI.

Make sure \$OPENNMS_HOME/etc/jmxremote.access has the appropriate settings:

admin readwrite jmx readonly

The possible types of access are:

readwrite

Allows retrieving JMX metrics as well as executing MBeans.

readonly

Allows retrieving JMX metrics but does **not** allow executing MBeans, even if they just return simple values.

21.2. Enabling SSL

To enable SSL on the RMI port, you will need to have an existing keystore for the OpenNMS Meridian server. For information on configuring a keystore, please refer to the official *OpenNMS Meridian* Wiki article Standalone HTTPS with Jetty.

You will need to change the com.sun.management.jmxremote.ssl option to true, and tell OpenNMS Meridian where your keystore is.

```
# Configure remote JMX
ADDITIONAL_MANAGER_OPTIONS="$ADDITIONAL_MANAGER_OPTIONS
-Dcom.sun.management.jmxremote.port=18980"
ADDITIONAL_MANAGER_OPTIONS="$ADDITIONAL_MANAGER_OPTIONS
-Dcom.sun.management.jmxremote.local.only=false"
ADDITIONAL MANAGER OPTIONS="$ADDITIONAL MANAGER OPTIONS
-Dcom.sun.management.jmxremote.authenticate=true"
ADDITIONAL_MANAGER_OPTIONS="$ADDITIONAL_MANAGER_OPTIONS
-Dcom.sun.management.jmxremote.ssl=true"
# Configure SSL Keystore
ADDITIONAL_MANAGER_OPTIONS="$ADDITIONAL_MANAGER_OPTIONS
-Djavax.net.ssl.keyStore=/opt/opennms/etc/opennms.keystore"
ADDITIONAL MANAGER OPTIONS="$ADDITIONAL MANAGER OPTIONS
-Djavax.net.ssl.keyStorePassword=changeit"
# Listen on all interfaces
ADDITIONAL_MANAGER_OPTIONS="$ADDITIONAL_MANAGER_OPTIONS
-Dopennms.poller.server.serverHost=0.0.0.0"
# Accept remote RMI connections on this interface
ADDITIONAL_MANAGER_OPTIONS="$ADDITIONAL_MANAGER_OPTIONS
-Djava.rmi.server.hostname=<your-server-ip-address>"
```

21.3. Connecting to RMI over SSL

Note that if you are using a self-signed or otherwise untrusted certificate, you will need to configure a *truststore* on the client side when you attempt to connect over SSL-enabled RMI. To create a truststore, follow the example in the HTTPS client instructions in the operator section of the manual. You may then use the truststore to connect to your OpenNMS Meridian RMI server.

For example, when using jconsole to connect to the OpenNMS Meridian RMI interface to get JVM statistics, you would run:

jconsole -J-Djavax.net.ssl.trustStore=/path/to/opennms.truststore -J
-Djavax.net.ssl.trustStorePassword=changeit

Chapter 22. Minion

22.1. Using JMS

By default, *OpenNMS Meridian* uses the *JMS* protocol with an *ActiveMQ* broker to communicate with *Minions*. This is used for both issuing remote procedure calls (RPCs, ie. ping this host) and for transporting unsolicited messages such as SNMP traps and syslog messages. *OpenNMS Meridian* provides an embedded *ActiveMQ* broker to help simplify installation.



It is also possible (and recommended for large installations) to use an external broker.

22.1.1. Tuning the ActiveMQ broker

The settings for the embedded *ActiveMQ* broker are found in **\$OPENNMS_HOME/etc/opennms**activemq.xml. Memory and storage limits are conservative by default and should be tuned to accommodate your workload. Consider increasing the memoryUsage (defaults to 20MB) to 512MB or greater, assuming you have enough heap available.



If the memory limit is reached, flow control will prevent messages from being published to the broker.

22.1.2. Monitoring the ActiveMQ broker using the Karaf shell

The opennms:activemq-stats command available via the *Karaf shell* can be used to show statistics about the embedded broker:

opennms:activemq-stats



If the command is not available, try installing the feature using feature:install opennms-activemq-shell

This command reports some high level broker statistics as well as message, enqueue and dequeue counts for the available queues. Pay close attention to the memory usage that is reported. If the usage is high, use the queue statistics to help isolate which queue is consuming most of the memory.

The opennms:activemq-purge-queue command can be used to delete all of the available messages in a particular queue:

opennms:activemq-purge-queue OpenNMS.Sink.Trap

22.1.3. Authentication and authorization with ActiveMQ

The embedded ActiveMQ broker is pre-configured to authenticate clients using the same authentication mechanisms (JAAS) as the *OpenNMS Meridian* web application.

Users associated with the ADMIN role can read, write or create any queue or topic.

Users associated with the MINION role are restricted in such a way that prevents them from making RPC requests to other locations, but can otherwise read or write to the queues they need.

See the authorizationPlugin section in \$OPENNMS_HOME/etc/opennms-activemq.xml for details.

22.1.4. Multi-tenancy with OpenNMS Meridian and ActiveMQ

The queue names used by *OpenNMS Meridian* are prefixed with a constant value. If many *OpenNMS Meridian* are configured to use the same broker, then these queues would end up being shared amongst the instances, which is not desired. In order to isolate multiple instances on the same broker, you can customize the prefix by setting the value of the org.opennms.instance.id system property to something that is unique per instance.

```
echo 'org.opennms.instance.id=MyNMS' >
"$OPENNMS_HOME/etc/opennms.properties.d/instance-id.properties"
```



If you change the instance id setting when using the embedded broker, you will need to update the authorization section in the broker's configuration to reflect the updated prefix.

22.1.5. Tuning the RPC client in OpenNMS

The following system properties can be used to tune the thread pool used to issue RPCs:

General

Name	Defa ult	Description
org.opennms.ipc.rpc.t hreads	10	Number of threads which are always active.
org.opennms.ipc.rpc.t hreads.max	20	Maximum number of threads which can be active. These will exit after remaining unused for some period of time.
org.opennms.ipc.rpc.q ueue.max	1000	Maximum number of requests to queue. Set to -1 to be unlimited.



Use the opennms:stress-rpc *Karaf shell* command to help evaluate and tune performance.

22.1.6. Diagnosing RPC failures

Symptoms of RPC failures may include missed polls, missed data collection attempts and the inability to provision or re-scan existing nodes. For these reasons, it is important to ensure that RPC related communication with Minion at the various monitoring locations remains healthy.

If you want to verify that a specific location is operating correctly make sure that:

- 1. Nodes exist and were automatically provisioned for all of the Minions at the location
- 2. The Minion-Heartbeat, Minion-RPC and JMX-Minion services are online for one or more Minions at the location
- 3. Response time graphs for the Minion-RPC service are populated and contain reasonable values
 - These response time graphs can be found under the 127.0.0.1 response time resource on the Minion node
 - Values should typically be under 100ms but may vary based on network latency
- 4. Resource graphs for the JMX-Minion service are populated and reasonable values

To interactively test RPC communication with a remote location use the **opennms:poll** command from the *Karaf shell*:

opennms:poll -1 LOCATION -c org.opennms.netmgt.poller.monitors.IcmpMonitor 127.0.0.1



Replace LOCATION in the command above with the name of the location you want to test.

22.2. Using AWS SQS

By default, *OpenNMS Meridian* uses an *ActiveMQ* broker to communicate with *Minions*. This broker is used for both issuing remote procedure calls (RPCs, ie. ping this host) and for transporting unsolicited messages such as SNMP traps and syslog messages.

AWS SQS can be used as an alternative to *ActiveMQ* for both remote procedure calls and transporting the unsolicited messages.

AWS SQS must be enabled on both OpenNMS Meridian and Minion to function.

22.2.1. OpenNMS Meridian Configuration

Enable and configure the *AWS SQS* on *OpenNMS Meridian* by using the following commands. The initialSleepTime property will ensure that messages are not consumed from *AWS SQS* until the *OpenNMS Meridian* system has fully initialized.

```
echo 'org.opennms.core.ipc.rpc.strategy=sqs
org.opennms.core.ipc.sink.strategy=sqs
org.opennms.core.ipc.sink.initialSleepTime=60000
org.opennms.core.ipc.aws.sqs.aws_region=us-east-1' >
"$OPENNMS_HOME/etc/opennms.properties.d/aws-sqs.properties"
```

AWS Credentials are required in order to access SQS. The default credential provider chain looks for credentials in this order:

- Environment Variables (i.e. AWS_ACCESS_KEY_ID and AWS_SECRET_ACCESS_KEY)
- Java system properties (i.e. aws.accessKeyId and aws.secretKey. These keys can be added to \$OPENNMS_HOME/etc/opennms.conf)
- Default credential profiles file (i.e. </ .aws/credentials)
- Amazon ECS container credentials (i.e. AWS_CONTAINER_CREDENTIALS_RELATIVE_URI)
- Instance profile credentials (i.e. through the metadata service when running on EC2)

Alternatively, the credentials can be specified inside the aws-sqs.properties file:

When running OpenNMS inside AWS, it is possible to use the default provider chain with an IAM Role to avoid hard coding the AWS Credentials on a configuration file. The following shows an example of the role that should be associated with the EC2 instance on which OpenNMS is going to run:

aws Services - Resource Groups	× . ♠	Global 👻 Support 👻
Create role	1 2	3
	Trust Permissions	Review
Review		
Provide the required information below	and review this role before you create it.	
Role name*	SQS-Access	
	Maximum 64 characters. Use alphanumeric and '+=,,@' characters.	
Role description	Provide Full SQS Access from EC2 instances.	
	Maximum 1000 characters. Use alphanumeric and '+=,.@' characters.	6
Trusted entities	AWS service: ec2.amazonaws.com	
Policies	MmazonSQSFullAccess 🗷	

If you require consistent ordering of the messages, you should use FIFO queues instead of Standard queues. You can enable FIFO queues by adding the following parameter to the aws-sqs.properties file referenced above:

org.opennms.core.ipc.aws.sqs.sink.FifoQueue=true

Restart OpenNMS Meridian to apply the changes.

22.2.2. Minion Configuration

Enable the AWS SQS on Minion using:

```
echo '!minion-jms
!opennms-core-ipc-rpc-jms
!opennms-core-ipc-sink-camel
opennms-core-ipc-rpc-aws-sqs
opennms-core-ipc-sink-aws-sqs' > "$MINION_HOME/etc/featuresBoot.d/aws-sqs.boot"
```



The snippet above prevents the default JMS related features from starting and loads the SQS related features instead.

Next, configure AWS SQS on Minion using:

echo 'aws_region=us-east-1 aws_access_key_id=XXXXXXXXXXX aws_secret_access_key=XXXXXXXXXXX' > "\$MINION_HOME/etc/org.opennms.core.ipc.aws.sqs.cfg"

The AWS credentials are required. If they are not specified on the configuration file, the default credentials provider chain (explained above) will be used instead.

If you require consistent ordering to the messages, you should use FIFO queues instead of Standard queues. You can enable FIFO queues by adding the following parameter to the org.opennms.core.ipc.aws.sqs.cfg file referenced above:

```
sink.FifoQueue=true
```

Restart *Minion* to apply the changes.



AWS credentials are required when the Minion is not running inside a VPC.



The Minion SQS settings must match what OpenNMS currently has. This is particularly critical for the *FifoQueue* setting.

22.2.3. SQS Configuration Settings

From the Amazon SQS Documentation, the following tables list parameters which can be added to either Minion (via MINION_HOME/etc/org.opennms.core.ipc.aws.sqs.cfg) or *OpenNMS Meridian* (via OPENNMS_HOME/etc/opennms.properties.d/aws-sqs.properties), along with the correct syntax for each environment.

Sink Settings

Queues used for reception of unsolicited messages (e.g. SNMP traps, syslog messages) are configured by setting properties with sink prepended to the SQS parameter name:

Parameter	Notes	OpenNMS Meridian	Minion
DelaySeconds	Default: 0 seconds	org.opennms.core.ipc.a ws.sqs.sink.DelaySecon ds	sink.DelaySeconds
MaximumMessageSize	Default: 262144 bytes	org.opennms.core.ipc.a ws.sqs.sink.MaximumMes sageSize	sink.MaximumMessageSiz e
MessageRetentionPeriod	Default: 1209600 seconds	org.opennms.core.ipc.a ws.sqs.sink.MessageRet entionPeriod	sink.MessageRetentionP eriod
ReceiveMessageWaitTime Seconds	Default: 10 seconds (for OpenNMS)	org.opennms.core.ipc.a ws.sqs.sink.ReceiveMes sageWaitTimeSeconds	sink.ReceiveMessageWai tTimeSeconds
VisibilityTimeout	Default: 30 seconds	org.opennms.core.ipc.a ws.sqs.sink.Visibility Timeout	sink.VisibilityTimeout
Policy	-	org.opennms.core.ipc.a ws.sqs.sink.Policy	sink.Policy
RedrivePolicy	-	org.opennms.core.ipc.a ws.sqs.sink.RedrivePol icy	sink.RedrivePolicy
KmsMasterKeyId	-	org.opennms.core.ipc.a ws.sqs.sink.KmsMasterK eyId	sink.KmsMasterKeyId
KmsDataKeyReusePeriodS econds	-	org.opennms.core.ipc.a ws.sqs.sink.KmsDataKey ReusePeriodSeconds	sink.KmsDataKeyReusePe riodSeconds
FifoQueue	Default: false	org.opennms.core.ipc.a ws.sqs.sink.FifoQueue	sink.FifoQueue
ContentBasedDeduplicat ion	Valid only when sink.FifoQueue is true	org.opennms.core.ipc.a ws.sqs.sink.ContentBas edDeduplication	sink.ContentBasedDedup lication

RPC Settings

Queues used for provisioning, service polling, data collection, and other concerns apart from unsolicited message reception are configured by setting properties with rpc prepended to the SQS parameter name:

Parameter	Notes	OpenNMS Meridian	Minion
DelaySeconds	Default: 0 seconds	org.opennms.core.ipc.a ws.sqs.rpc.DelaySecond s	rpc.DelaySeconds
MaximumMessageSize	Default: 262144 bytes	org.opennms.core.ipc.a ws.sqs.rpc.MaximumMess ageSize	rpc.MaximumMessageSize
MessageRetentionPeriod	Default: 1209600 seconds	org.opennms.core.ipc.a ws.sqs.rpc.MessageRete ntionPeriod	rpc.MessageRetentionPe riod
ReceiveMessageWaitTime Seconds	Default: 10 seconds (for OpenNMS)	org.opennms.core.ipc.a ws.sqs.rpc.ReceiveMess ageWaitTimeSeconds	rpc.ReceiveMessageWait TimeSeconds
VisibilityTimeout	Default: 30 seconds	org.opennms.core.ipc.a ws.sqs.rpc.VisibilityT imeout	rpc.VisibilityTimeout
Policy	-	org.opennms.core.ipc.a ws.sqs.rpc.Policy	rpc.Policy
RedrivePolicy	-	org.opennms.core.ipc.a ws.sqs.rpc.RedrivePoli cy	rpc.RedrivePolicy
KmsMasterKeyId	-	org.opennms.core.ipc.a ws.sqs.rpc.KmsMasterKe yId	rpc.KmsMasterKeyId
KmsDataKeyReusePeriodS econds	-	org.opennms.core.ipc.a ws.sqs.rpc.KmsDataKeyR eusePeriodSeconds	rpc.KmsDataKeyReusePer iodSeconds
FifoQueue	Default: false	org.opennms.core.ipc.a ws.sqs.rpc.FifoQueue	rpc.FifoQueue
ContentBasedDeduplicat ion	Valid only when rpc.FifoQueue is true	org.opennms.core.ipc.a ws.sqs.rpc.ContentBase dDeduplication	<pre>rpc.ContentBasedDedupl ication</pre>



When FIFO queues are not required, there is no need to add FifoQueue=false to the configuration files, as this is the default behavior.

22.2.4. Managing Multiple Environments

In order to support multiple *OpenNMS Meridian* environments in a single AWS region, the aws_queue_name_prefix property can be used to prefix the queue names.

For example, if we set this property to be "PROD", the queue names will resemble PROD-OpenNMS-Sink-Heartbeat, instead of OpenNMS-Sink-Heartbeat.



This property must be properly configured at *OpenNMS Meridian* and Minion side.

22.2.5. AWS Credentials

The credentials (a.k.a. the Access Key ID and the Secret Access Key) are required in both sides, OpenNMS and Minion.

In order to create credentials just for accessing SQS resources, follow this procedure:

- From the AWS Console, choose the appropriate region.
- Open the IAM Dashboard and click on "Add user".
- Choose a name for the user, for example opennms-minion.
- Check only Programmatic access for the Access type.
- On the permissions, click on Attach existing policies directly.
- On the search bar, write SQS, and then check on AmazonSQSFullAccess.
- Click on Create User

aws s	ervices 🗸	Resource Groups 🐱	*			Global 👻 Support
Add user			Details	Permissions	3 Review	
			Details	Permissions	Neview	Complete
Review						
Review your choices.	After you creat	e the user, you can view ar	nd download the a	autogenerated password a	and access key.	
User details						
	User name	e opennms-minion				
AW	/S access type	Programmatic access	- with an access	key		
Permissions sum	imary					
The following policies	will be attache	d to the user shown above				
Туре	Name					
Managed policy	AmazonSC	SFullAccess				
					Cancel Previo	ous Create user
					Previo	Greate user

Finally, either click on Download .csv or click on "Show" to grab a copy of the Access key ID, and the Secret access key.

22.2.6. Limitations

There are a number of limitations when using AWS SQS, in particular:

- A message can include only XML, JSON, and unformatted text. The following Unicode characters are allowed: #x9 | #xA | #xD | #x20 to #xD7FF | #xE000 to #xFFFD | #x10000 to #x10FFFF. Any characters not included in this list are rejected.
- The minimum message size is 1 byte (1 character). The maximum is 262,144 bytes (256 KB).

• Without batching, FIFO queues can support up to 300 messages per second (300 send, receive, or delete operations per second).

See Amazon SQS Limits for further details.

Location names

Queue names in *AWS SQS* are limited to 80 characters. When issuing remote procedure calls, the target location is used a part of the queue name. For this reason, it is important that:

- The length of the location name and queue name prefix (if used) must not exceed 32 characters in aggregate.
- Both the location name and queue name prefix (if used) may only contain alphanumeric characters, hyphens (-), and underscores (_). :imagesdir: ../../images

22.3. Using Off-heap Storage for Sink Messages

If a *Minion* loses connectivity with the broker (i.e. *Kafka* or *ActiveMQ*), then any received messages (i.e. syslog, flows, SNMP traps) are queued until connectivity is restored. This queue is limited by a fixed (and configurable) number of messages queued in the JVM heap and can optionally queue additional messages by persisting directly to the filesystem avoiding heap memory usage. Once the queue is full, additional messages will be dropped.

The off-heap storage feature allows us to extend the storage capacity by queuing messages outside of the JVM heap.

22.3.1. Configuring Off-heap Storage

Configure storage limits:

```
echo 'offHeapSize = 1GB
entriesAllowedOnHeap = 100000
offHeapFilePath =' > "$MINION_HOME/etc/org.opennms.core.ipc.sink.offheap.cfg"
```

A file will be created for each module and the configuration will be applied to each module individually. Therefore setting a size of 1GB for example means that the maximum size for each module's file is 1GB not that the total for all modules is 1GB.

The number of entries allowed to be queued on the heap can be controlled by setting the entriesAllowedOnHeap value.

Specify offHeapSize in KB, MB or GB. For ex: 1, 128MB, 65536KB. The size specified must be a power of 2. For example 128MB is a valid value but 140MB is not.

The offHeapSize can also be left empty or set to 0 to disable queueing off heap. In this case only heap memory will be used for queueing.

The offHeapFilePath should be set to the path where the queue files should be stored and defaults

22.4. Installing JDBC drivers in Minion

For any JDBC service to be detected/polled/collected, corresponding JDBC driver needs to be installed in *Minion*. Following are steps to install JDBC driver.

- JDBC driver jar needs to be copied into minion/repositories/default by following maven repositories pattern. For ex: Mysql driver jar should be placed in repositories/core/mysql/mysql-connector-java/8.0.15/mysql-connector-java-8.0.15.jar
- Install the JDBC driver jar as a feature. Modify contents of following features-jdbc.xml relevant to JDBC driver that is getting installed. Copy features-jdbc.xml file into \${MINION_HOME}/deploy/. Multiple JDBC drivers can be added to this file each one as a new feature.

features-jdbc.xml

• Restart *Minion* with : systemctl restart minion and that should load the JDBC driver. :imagesdir: ../../images

22.5. Time to Live (TTL) for RPCs

Remote procedure calls (RPCs) between *OpenNMS Meridian* and *Minion* include a time limit which, if exceeded, aborts the requests and discards any subsequent responses. We call this limit the time-to-live or TTL. We make an effort to use logical values where possible and provide means to configure the TTLs for circumstances where the default values are not suitable (i.e. for interacting with devices or locations with high latency).

Our modules and services have different rules for determining the TTL.



To troubleshoot TTLs, consider enabling the OpenTracing integration on both *OpenNMS Meridian* and *Minion*.

22.5.1. TTLs in Pollerd & Collectd

The TTL used when invoking monitors and collectors remotely is:

- 1. The value from the ttl parameter associated with the service
- 2. Fall-back to using the service interval as the TTL (this is the rate at which the service is scheduled)

These rules apply to all monitors and collectors, excluding the SnmpCollector.

22.5.2. TTLs for the SNMP Collector

The TTL used when invoking the SnmpCollector remotely is:

- 1. The value of the ttl associate with the SNMP agent's configuration
- 2. Fall-back to using the service interval as the TTL (this is the rate at which the service is scheduled)

22.5.3. TTLs for the other SNMP communication

The TTL used when invoking other types of SNMP requests remotely is:

- 1. The value of the ttl associate with the SNMP agent's configuration
- 2. Fall-back to using the service interval as the TTL (this is the rate at which the service is scheduled)



These rules apply to SNMP queries like agent scans in provisiond, table scans in enlinkd, etc...

22.5.4. TTLs for Provisiond Detectors

The TTL used when invoking detectors remotely is:

- 1. The value from the ttl parameter associated with the detector
- 2. Fall-back to using the global default TTL

22.5.5. Global TTL

For cases where we cannot derive a suitable TTL, a global value is used wich defaults to 20000 (20 seconds). This value can be configured. When using the JMS-based RPC implementation, set value of the org.opennms.jms.timeout system property to the desired number of milliseconds. When using the Kafka-based RPC implementation, set the value of the org.opennms.core.ipc.rpc.kafka.ttl system property to the desired number of milliseconds.

22.5.6. Using meta-data for TTLs

For RPCs that derive TTLs from service parameters, the meta-data feature can be used to customize these values on a node/interface/service basis.

For example, the ICMP detector could be configured to use the value of the ttl associated with the node meta-data, or default to 30 seconds if none is setup as follows:

```
<detector name="ICMP" class="org.opennms.netmgt.provision.detector.icmp.IcmpDetector">
    cparameter key="ttl" value="${requisition:ttl|300000}"/>
</detector>
```

Chapter 23. Sentinel

The goal of *Sentinel* is to scale out and distribute individual components from *OpenNMS Meridian*.



The sentinel feature is still in development and this is only a very rough documentation, not covering all aspects. Please refer to the Limitations section for more details

23.1. Limitations

Currently *Sentinel* is in a very early state of development and therefore the usage is limited:

- Only allows distribution of *Telemetryd* functionality (such as processing flows, or use the existing telemetry adapters to store measurements data to *Newts*)
- Requires a Minion to work as a (message) producer
- In most cases, it is advised to disable those adapters and listeners in *OpenNMS Meridian* if they are also running by a *Sentinel* instance.

23.2. Installation

If *Minion* is working, the ground work for *Sentinel* is already done. For more details on how to install *Sentinel* refer to the Installation Guide.

23.3. Clean Start

On each start the cache of the *Sentinel* is cleared, that means the container returns in it's original state. To disable this functionality set karaf.clean.cache = false in \${SENTINEL_HOME}/etc/system.properties.

23.4. Configuration

It is assumed, that the *Sentinel* container is running on a different system than the *OpenNMS Meridian* and *Minion*. Therefore at least the following configurations are necessary:

- Configure the datasource to connect to the Postgres database
- Configure the controller (identity and connection to communicate with OpenNMS same as for *Minion*)
- Configure the communication layer (for now either JMS or Kafka)
- Install features

23.4.1. Configure the datasource

This is required in order to have Sentinel connect to the PostgreSQL database OpenNMS Meridian.

```
config:edit org.opennms.netmgt.distributed.datasource
config:property-set datasource.url jdbc:postgresql://<db-host>:<db-port>/<db-name>
config:property-set datasource.username <db-user>
config:property-set datasource.password <db-password>
config:property-set datasource.databaseName <db-name>
config:update
```

23.4.2. Configure the controller

```
config:edit org.opennms.sentinel.controller
config:property-set location SENTINEL ①
config:property-set id 0000000-0000-0000-0000000ddba11 ②
config:property-set http-url http://127.0.0.1:8980/opennms ③
config:property-set broker-url failover:tcp://127.0.0.1:61616 ④
config:update
```

- 1 used only for tracing, must be provided
- 2 used only for tracing, must be provided
- ③ url which points to OpenNMS Meridian (required)
- ④ url which points to the OpenNMS Meridian Active MQ Broker (only required if using feature sentinel-jms, otherwise may be omitted)



Basically the same properties as for the *Minion Controller* are supported, but must be placed in config file org.opennms.sentinel.controller.cfg instead of org.opennms.minion.controller.cfg.

23.4.3. Configure Connectivity

By default the *Sentinel* consumes messages from the *OpenNMS Meridian ActiveMQ Broker*. See Configure the Controller for more details.

As with Minion the Sentinel can also be configured to consume messages from Kafka

Using Kafka

When Using Sentinel with Kafka the same rules for using Kafka with Minions apply.

Kafka Configuration

Each *Minion* works as a Producer and must be configured beforehead. Please refer to section Minion Kafka Producer Configuration on how to configure *Minion* as a *Kafka Producer*.

Each Sentinel works configured as а Consumer and can be in the file \${SENTINEL_HOME}/etc/org.opennms.core.ipc.sink.kafka.consumer.cfg. Either manually or via the config:edit org.opennms.core.ipc.sink.kafka.consumer statement. For supported properties, see here

By default each *Kafka Consumer* starts consuming messages immediately after the feature has been started. It is possible to set a property org.opennms.core.ipc.sink.initialSleepTime to define an initial sleep time in ms before any messages are consumed. In order to set this up, please add an entry to the end of the file \${SENTINEL_HOME}/etc/system.properties:

Initial delay of 5 seconds before consuming of messages is started in milliseconds
org.opennms.core.ipc.sink.initialSleepTime=5000

23.4.4. Available features

The following list contains some features which may be installed manually:

Feature	Required	Description
sentinel-core	true	Base feature, installing all required bundles such as opennms:health-check and service requirements for other bundles, e.g. sentinel- persistence.
sentinel-jms	false	Provides connectivity to the OpenNMS Meridian <i>ActiveMQ</i> Broker.
sentinel-kafka	false	Provides connectivity to Kafka.
sentinel-flows	false	Feature which starts all dependencies to start processing flows.
sentinel-newts	false	Provides functionality to persist measurement data to <i>Newts</i> .
sentinel-telemetry-nxos	false	Allows using the NxosGpbAdapter
sentinel-telemetry-jti	false	Allows using the JtiGpbAdapter
sentinel-telemetry-bmp	false	Allows using the BmpTelemetryAdapter

23.4.5. Auto install

In some cases it is desired to automatically configure the *Sentinel* instance and also start required features/bundles. As *Sentinel* is based on *Apache Karaf* - which supports auto deployment by simply copying any kind of data to the deploy folder, *Sentinel* can make use of that mechanism to enable auto or hot deployment.

In order to do so, in most cases it is sufficient to copy a features.xml file to \${SENTINEL_HOME}/deploy.
This can be done even if the container is running.

The chapter *Configure Flow Processing* contains an example on how to automatically start them with *Sentinel*

23.4.6. Auto Start

In some cases it might not be sufficient to auto-deploy/configure the container with a features.xml file. If more flexibility is required it is suggested to modify/copy .cfg and .properties files directly to the \${SENTINEL_HOME}/etc directory. To automatically start features with the container, the file \${SENTINEL_HOME}/etc/org.apache.karaf.features.cfg must be updated:

```
# ...
featuresBoot = \
      (aries-blueprint, ∖
      deployer), ∖
      instance/4.2.2, ∖
      package/4.2.2, \setminus
      log/4.2.2, \
      scv/2020.1.22, \
      ssh/4.2.2, \
      framework/4.2.2, ∖
      system/4.2.2, \
      eventadmin/4.2.2, ∖
      feature/4.2.2, ∖
      shell/4.2.2, \
      management/4.2.2, \setminus
      service/4.2.2, ∖
      system/4.2.2, \
      eventadmin/4.2.2, ∖
      feature/4.2.2, \
      shell/4.2.2, \
      management/4.2.2, \setminus
      service/4.2.2, ∖
      jaas/4.2.2, \
      shell-compat/4.2.2, \
      diagnostic/4.2.2, ∖
      wrap, \
      bundle/4.2.2, \
      config/4.2.2, \
      kar/4.2.2, ∖
      sentinel-jms, \ ①
      sentinel-flows (2)
```

....

1 Install and Start JMS communication feature

2 Install and Start Sentinel Flows feature

23.4.7. Health Check / Troubleshooting

The opennms:health-check command allows to verify the health of the *Sentinel* container. It performs various health checks depending on the installed features to calculate the overall container health. For more information please try opennms:health-check --help.



In order to run the opennms:health-check command, the feature sentinel-core must be installed.



This is also available in *Minion* Containers and will replace the now deprecated command minion:ping.

23.5. Flow Processing

In order to process flows via *Sentinel* ensure that *OpenNMS Meridian, Minion* and *Sentinel* are all installed according to the official Installation Guide.

Afterwards the following configuration examples help setting everything up.

23.5.1. Configure Sentinel

In order to process flows, *Sentinel* must start appropriate flow adapters. In *Sentinel* flow adapters are configured by either be placing a .cfg file in \${SENTINEL_HOME}/etc or via config:edit statement.

The following example will configure the consumption of Netflow5 flows and saves the configuration in \${SENTINEL_HOME/etc/org.oennms.features.telemetry.adaters-netflow5.cfg.

First login to the Karaf Shell

\$ ssh -p 8301 admin@localhost

```
admin@sentinel> config:edit --alias netflow5 --factory
org.opennms.features.telemetry.adapters
admin@sentinel> config:property-set name Netflow-5
admin@sentinel> config:property-set adapters.0.name Netflow-5-Adapter
admin@sentinel> config:property-set adapters.0.class-name
org.opennms.netmgt.telemetry.protocols.netflow.adapter.netflow5.Netflow5Adapter
admin@sentinel> config:update
```

Afterwards the feature **sentinel-flows** can be installed:

admin@sentinel> feature:install sentinel-jms ①
admin@sentinel> feature:install sentinel-flows

① or sentinel-kafka



To check everything is working as expected, run the opennms:health-check command, e.g.:

```
admin@sentinel> opennms:health-check
Verifying the health of the container
Verifying installed bundles [Success]
Connecting to JMS Broker [Success]
Connecting to OpenNMS ReST API [Success]
Retrieving NodeDao [Success]
Connecting to ElasticSearch ReST API (Flows) [Success]
=> Everything is awesome
```

23.5.2. Configure Minion

The Minion must be configured to listen to incoming flow packages, e.g.:

\$ ssh -p 8201 admin@localhost

```
admin@minion()> config:edit --alias udp-8877 --factory
org.opennms.features.telemetry.listeners
admin@minion()> config:property-set name Netflow-5
admin@minion()> config:property-set class-name
org.opennms.netmgt.telemetry.listeners.UdpListener
admin@minion()> config:property-set parameters.port 8877
admin@minion()> config:property-set parsers.0.name Netflow-5-Parser
admin@minion()> config:property-set parsers.0.class-name
org.opennms.netmgt.telemetry.protocols.netflow.parser.Netflow5UdpParser
admin@minion()> config:update
```



The name of the listener, in this case Netflow-5 must match with the name of the adapter configuration in the *Sentinel* container.

23.5.3. Configure OpenNMS

OpenNMS Meridian must expose its *ActiveMQ Broker* to have a *Minion* and *Sentinel* connect to it. This can be done in *\$OPENNMS_HOME/etc/opennms-activemq.xml*. For more details please refer to the Minion Installation Guide.

23.5.4. Auto configure flow processing for Sentinel

The following examples illustrate a features.xml which configures the *Sentinel* instance and automatically starts all required features to either consume messages via JMS (*ActiveMQ*) or *Kafka*.

Simply copy it to \${SENTINEL_HOME}/deploy/.

JMS

```
<?xml version="1.0" encoding="UTF-8"?>
<features
        name="opennms-${project.version}"
        xmlns="http://karaf.apache.org/xmlns/features/v1.4.0"
        xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance"
        xsi:schemaLocation="http://karaf.apache.org/xmlns/features/v1.4.0
http://karaf.apache.org/xmlns/features/v1.4.0"
>
    <!-- Bootstrap feature to start all flow related features automatically -->
    <feature name="autostart-sentinel-flows" version="${project.version}" start-level
="100" install="auto">
        <!-- Configure the controller itself -->
        <config name="org.opennms.sentinel.controller">
            location = SENTINEL
            id = 0000000-0000-0000-0000-00000ddba11
            http-url = http://127.0.0.1:8980/opennms
            broker-url = failover:tcp://127.0.0.1:61616
        </config>
        <!-- Configure datasource connection -->
        <config name="org.opennms.netmgt.distributed.datasource">
            datasource.url = jdbc:postgresql://localhost:5432/opennms
            datasource.username = postgres
            datasource.password = postgres
            datasource.databaseName = opennms
        </config>
        <!--
            Starts the Netflow5Adapter to process Netflow5 Messages.
            Be aware, that this requires a Listener with name "Netflow-5" on the
Minion-side to have messages
            processed properly.
        -->
        <config name="org.opennms.features.telemetry.adapters-netflow5">
            name = Netflow-5
            class-name =
org.opennms.netmgt.telemetry.adapters.netflow.v5.Netflow5Adapter
        </config>
        <!-- Point sentinel to the correct elastic endpoint -->
        <config name="org.opennms.features.flows.persistence.elastic">
            elasticUrl = http://elasticsearch:9200
        </config>
        <!-- Install JMS related features -->
        <feature>sentinel-jms</feature>
        <!-- Install Flow related features -->
        <feature>sentinel-flows</feature>
    </feature>
</features>
```

```
<?xml version="1.0" encoding="UTF-8"?>
<features
        name="opennms-${project.version}"
        xmlns="http://karaf.apache.org/xmlns/features/v1.4.0"
        xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance"
        xsi:schemaLocation="http://karaf.apache.org/xmlns/features/v1.4.0
http://karaf.apache.org/xmlns/features/v1.4.0"
>
    <!-- Bootstrap bootstrap feature to start all flow related features automatically
-->
    <feature name="autostart-sentinel-telemetry-flows" version="${project.version}"
start-level="200" install="auto">
        <!-- Configure the controller itself -->
        <config name="org.opennms.sentinel.controller">
            location = SENTINEL
            id = 0000000-0000-0000-0000-00000ddba11
            http-url = http://127.0.0.1:8980/opennms
            broker-url = failover:tcp://127.0.0.1:61616
        </config>
        <!-- Configure datasource connection -->
        <config name="org.opennms.netmgt.distributed.datasource">
            datasource.url = jdbc:postgresql://localhost:5432/opennms
            datasource.username = postgres
            datasource.password = postgres
            datasource.databaseName = opennms
        </config>
        <!--
            Starts the Netflow5Adapter to process Netflow5 Messages.
            Be aware, that this requires a Listener with name "Netflow-5" on the
Minion-side to have messages
            processed properly.
        -->
        <config name="org.opennms.features.telemetry.adapters-netflow5">
            name = Netflow-5
            class-name =
org.opennms.netmgt.telemetry.adapters.netflow.v5.Netflow5Adapter
        </config>
        <!-- Point sentinel to the correct elastic endpoint -->
        <config name="org.opennms.features.flows.persistence.elastic">
            elasticUrl = http://elasticsearch:9200
        </config>
        <!--
            Configure as Kafka Consumer.
            All properties desribed at
https://kafka.apache.org/0100/documentation.html#newconsumerconfigs are supported.
        -->
        <config name="org.opennms.core.ipc.sink.kafka.consumer">
            group.id = OpenNMS
```

```
bootstrap.servers = localhost:9092
        </config>
        <!--
            Configure as Kafka Producer for sending Events from Sentinel.
            All properties desribed at
https://kafka.apache.org/0100/documentation.html#producerconfigs are supported.
        -->
        <config name="org.opennms.core.ipc.sink.kafka">
            bootstrap.servers = localhost:9092
        </config>
        <!-- Install Kafka related features -->
        <feature>sentinel-kafka</feature>
        <!-- Install flow related features -->
        <feature>sentinel-flows</feature>
    </feature>
</features>
```

23.6. Persisting Collection Sets to Newts

In the previous chapter it is described on how to setup *OpenNMS Meridian, Minion* and *Sentinel* in order to distribute the processing of flows. However, it only covered flow processing adapters, but there are more, e.g. the NxosGpbAdapter, which can also be run on a *Sentinel*.

23.6.1. Adapters

This chapter describes the various adapters which may contain sample data which may be stored to a Persistence Storage and can also run on a *Sentinel*. At the moment only *Newts* is supported as a Persistence Storage. See chapter Configure Newts on how to configure *Newts*.

In order to get it to work properly, please note, that an apropriate listener on the *Minion* must also be configured. The name of the listener should share the same name on *Sentinel*.

SFlowTelemetryAdapter

In order to use this adapter, the feature sentinel-flows and sentinel-newts must be installed. In addition either sentinel-jms or sentinel-kafka should be installed and configured properly. See the previous *Flow Processing* chapter for more details.

If only sample data should be persisted, the following commands can be run on the *Sentinel*'s Karaf Shell

\$ ssh -p 8301 admin@localhost

```
admin@sentinel> config:edit --alias sflow --factory
org.opennms.features.telemetry.adapters
admin@sentinel> config:property-set name SFlow-Telemetry
admin@sentinel> config:property-set class-name
org.opennms.netmgt.telemetry.adapters.netflow.sflow.SFlowTelemetryAdapter
admin@sentinel> config:property-set parameters.script /opt/sentinel/etc/sflow-
host.groovy
admin@sentinel> config:update
```

If SFlow flows and the sample data should be processed, multiple adapters can be configured:

```
config:edit --alias sflow-telemetry --factory org.opennms.features.telemetry.adapters
config:property-set name SFlow
config:property-set adapters.1.name SFlow-Adapter
config:property-set adapters.1.class-name
org.opennms.netmgt.telemetry.adapters.netflow.sflow.SFlowAdapter
config:property-set adapters.2.name SFlow-Telemetry
config:property-set adapters.2.class-name
org.opennms.netmgt.telemetry.adapters.netflow.sflow.SFlowTelemetryAdapter
config:property-set adapters.2.class-name
org.opennms.netmgt.telemetry.adapters.netflow.sflow.SFlowTelemetryAdapter
config:property-set adapters.2.parameters.script /opt/sentinel/etc/sflow-host.groovy
config:update
```

Please note, that in both cases the file /opt/sentinel/etc/sflow-host.groovy must be provided manually, e.g. by manually copying it over from *OpenNMS Meridian*.

NxosGpbAdapter

In order to use this adapter, the feature sentinel-telemetry-nxos and sentinel-newts must be installed. In addition either sentinel-jms or sentinel-kafka should be installed and configured properly. See the previous *Flow Processing* chapter for more details.

Besides this, configuration files from *OpenNMS Meridian* must be copied to *Sentinel* to /opt/sentinel/etc. The following files and directories are required:

- \${OPENNMS_HOME}/etc/datacollection
- \${OPENNMS_HOME}/etc/datacollection-config.xml
- \${OPENNMS_HOME}/etc/resource-types.d

Afterwards the adapter can be set up:

\$ ssh -p 8301 admin@localhost

admin@sentinel> config:edit --alias nxos --factory
org.opennms.features.telemetry.adapters
admin@sentinel> config:property-set name NXOS
admin@sentinel> config:property-set class-name
org.opennms.netmgt.telemetry.protocols.nxos.adapter.NxosGpbAdapter
admin@sentinel> config:property-set parameters.script /opt/sentinel/etc/cisco-nxostelemetry-interface.groovy
admin@sentinel> config:update

Please note, that the file /opt/sentinel/etc/cisco-nxos-telemetry-interface.groovy must also be provided manually, e.g. by manually copying it over from *OpenNMS Meridian*.

JtiGpbAdapter

In order to use this adapter, the feature sentinel-telemetry-jti and sentinel-newts must be installed. In addition either sentinel-jms or sentinel-kafka should be installed and be configured properly. See the previous *Flow Processing* chapter for more details.

Besides this, configuration files from *OpenNMS Meridian* must be copied to *Sentinel* to /opt/sentinel/etc. The following files and directories are required:

- \${OPENNMS_HOME}/etc/datacollection
- \${OPENNMS_HOME}/etc/datacollection-config.xml
- \${OPENNMS_HOME}/etc/resource-types.d

Afterwards the adapter can be set up:

\$ ssh -p 8301 admin@localhost

```
admin@sentinel> config:edit --alias jti --factory
org.opennms.features.telemetry.adapters
admin@sentinel> config:property-set name JTI
admin@sentinel> config:property-set class-name
org.opennms.netmgt.telemetry.protocols.jti.adapter.JtiGpbAdapter
admin@sentinel> config:property-set parameters.script /opt/sentinel/etc/junos-
telemetry-interface.groovy
admin@sentinel> config:update
```

Please note, that the file /opt/sentinel/etc/junos-telemetry-interface.groovy must also be provided manually, e.g. by manually copying it over from *OpenNMS Meridian*.

23.6.2. Configure Newts

The configuration of *Newts* for *Sentinel* uses the same properties as for *OpenNMS Meridian*. The only difference is, that the properties for *Sentinel* are stored in /opt/sentinel/etc/org.opennms.newts.config.cfg instead of *.properties files. The name of each

property is the same as for *OpenNMS Meridian* without the org.opennms.newts.config prefix. The following example shows a custom *Newts* configuration using the *Sentinel's Karaf Shell*.

\$ ssh -p 8301 admin@localhost

admin@sentinel> config:edit org.opennms.newts.config admin@sentinel> config:property-set hostname localhost admin@sentinel> config:property-set port 9042 admin@sentinel> config:property-set cache.strategy org.opennms.netmgt.newts.support.GuavaSearchableResourceMetadataCache admin@sentinel> config:update

Chapter 24. Special Cases and Workarounds

24.1. Overriding SNMP Client Behavior

By default, the SNMP subsystem in OpenNMS Meridian does not treat *any* RFC 3416 error-status as fatal. Instead, it will attempt to continue the request, if possible. However, only a subset of errors will cause OpenNMS Meridian's SNMP client to attempt retries. The default SNMP error-status handling behavior is as follows:

Table 130. Default SNMP Error Status Behavior

error-status	Fatal ?	Retry ?
noError(0)	false	false
tooBig(1)	false	true
noSuchName(2)	false	true
badValue(3)	false	false
readOnly(4)	false	false
genErr(5)	false	true
noAccess(6)	false	true
wrongType(7)	false	false
wrongLength(8)	false	false
wrongEncoding(9)	false	false
wrongValue(10)	false	false
noCreation(11)	false	false
inconsistentValue(12)	false	false
resourceUnavailable(13)	false	false
commitFailed(14)	false	false
undoFailed(15)	false	false
authorizationError(16)	false	true
notWritable(17)	false	false
inconsistentName(18)	false	false

You can override this behavior by setting a property inside ${OPENNMS_HOME}/etc/opennms.properties$ in the form:

org.opennms.netmgt.snmp.errorStatus.[statusCode].[type]

For example, to make authorizationError(16) abort and not retry, you would set:

org.opennms.netmgt.snmp.errorStatus.16.fatal=true
org.opennms.netmgt.snmp.errorStatus.16.retry=false

Chapter 25. IFTTT Integration

The free web-based service *IFTTT* allows to combine web applications using simple conditional instructions. Each supported service has several triggers that can be used to trigger actions of other services. This allows for example to change brightness and color of a smart bulb, send messages or date to IoT devices.

The *OpenNMS Meridian* integration makes uses of the so-called "Webhooks" service, that allows to trigger actions when a specific web-request was received. The basic operation is as follows: *OpenNMS Meridian* polls for alarms and matches the alarm reduction key against a given filter and the alarm's associated nodes against a given category filter. For the resulting alarm set the maximum severity and total count is computed. If one of these values changed compared to the last poll one or more events specified for the computed maximum severity will be sent to *IFTTT*.

25.1. IFTTT Configuration

In order to use the *IFTTT* integration in *OpenNMS Meridian* you need an *IFTTT* account. With this account you are able to create so-called applets that combine a trigger with an action. In our case we use the "Webhooks" service as the trigger and define the event name OpenNMS. After this step you can combine this trigger with any of the possible supported services and their actions.

Webhooks service trigger definition

Make an Applet - IFTTT × +		
(+) (i) A https://ifttt.com/create/if-receive-a-web-request?sid=5	୯ ସ	, Suchen ☆ 🖨 🗸 🗧 🗮
FTTT ⓒ Discover Q Search 🖹 I	My Applets ≡ Activity	exampleuser Y
< Back		
	🖧 Complete trigger fie	lds
	Step 2 of 6	
	Receive a web request	
	This trigger fires every time the Maker service receives a web request to notify it of an event. For information on triggering events, go to your Maker service settings and then the listed URL (web) or tap your username (mobile)	
	Event Name	
	OpenNMS	
	The name of the event, like "button_pressed" or "front_door_opened"	
	Create trigger	
		,
About	Platform Blog Community Jobs Terms	Privacy

In your account service settings for the "Webhooks" service you find your key in the given service URL. In the following example this key is X71dfUZsH4Wkl6cjsLjdV.

Webhooks service settings

• • • • Webhooks settings - IFTTT × -			
(oks/settings	C Q Suchen	☆ 自 ♣ ♠ ♥ ☰
IFTTT © Discover Q S	earch 🖹 My Applets 🚍 Activity		exampleuser 🗸
My Applets > Webhooks	Webhooks set View activity lo Account Info Connected as: exampleuser URL: https://maker.ifttt.com/use/X71dfU Status: active Edit connection	a	
	Disconnect Webh	ooks	
	About Platform Blog Community	Jobs Terms Privacy	

On the side of *OpenNMS Meridian* you need a configuration that defines which event names to send on an alarm count or severity change. The configuration file ifttt-config.xml contains so called trigger packages.

The operation is as follows: *OpenNMS Meridian* retrieves all alarms that have a node associated. Each trigger package defines whether only acknowledged alarms should be taken into account. It then computes the maximum severity and alarm count for each trigger package's category filter and reduction key filter. After that it triggers all events defined in the corresponding trigger sets for the computed maximum severity. The category and reduction key filter accepts Java regular expressions. Using an empty category filter will use all unacknowledged alarms regardless of whether these alarms have nodes assigned or not.

Each trigger inside a trigger set defines the event name to be triggered and three additional values. These values can be used to set additional attributes for the corresponding *IFTTT* applet action. The following trigger sets can be defined:

Name	Execution
ON	on start of the <i>IFTTT</i> alarm polling daemon to switch on a device
OFF	on stop of the <i>IFTTT</i> alarm polling daemon to switch off a device
NORMAL	if severity is NORMAL

Name	Execution
WARNING	if severity is WARNING
MINOR	if severity is MINOR
MAJOR	if severity is MAJOR
CRITICAL	if severity is CRITICAL

There are also ON and OFF available for the trigger set definition. The ON event will be sent when the polling daemon is started and the OFF when it is stopped. These events can be used to powering up/down and initializing devices.

25.2. OpenNMS Configuration

IFTTT alarm polling will be enabled by setting the attribute enabled to true in the ifttt-config.xml file. It is also possible to configure the polling interval. The following trigger package defined the trigger sets which itself define a sequence of events to be triggered at *IFTTT*. Each trigger defines the eventName and an additional delay. This allows to defer the execution of the next trigger in a trigger set.

25.3. Example

The following example shows the configuration file for a WiFi light bulb controlled via *IFTTT*. The defined applets use value1 for setting the color and value2 for setting the brightness. The third value demonstrate the use of placeholders. For the severity-based trigger sets the following placeholders can be used in the three value fields: <code>%os%/%oldSeverity</code> for old severity, <code>%ns%/%newSeverity%</code> for new severity, <code>%oc%/%oldCount</code> for old alarm count and <code>%nc%/``%newCount%</code> for new alarm count. This is useful for sending messages or operating LED displays via *IFTTT*.

```
<ifttt-config enabled="true" key="X71dfUZsH4Wkl6cjsLjdV" pollInterval="30">
    <trigger-package categoryFilter="Routers|Switches" reductionKeyFilter=".*"
onlyUnacknowledged="true">
        <trigger-set name="ON">
            <trigger eventName="on" delay="0">
                <value1></value1>
                <value2></value2>
                <value3></value3>
            </trigger>
        </trigger-set>
        <trigger-set name="OFF">
            <trigger eventName="off" delay="0">
                <value1></value1>
                <value2></value2>
                <value3></value3>
            </trigger>
        </trigger-set>
```

```
<trigger-set name="NORMAL">
            <trigger eventName="OpenNMS" delay="0">
                <value1>#336600</value1>
                <value2>0.40</value2>
                <value3>%os%,%ns%,%oc%,%nc%</value3>
            </trigger>
        </trigger-set>
        <trigger-set name="WARNING">
            <trigger eventName="OpenNMS" delay="0">
                <value1>#FFCC00</value1>
                <value2>0.50</value2>
                <value3>%os%,%ns%,%oc%,%nc%</value3>
            </trigger>
        </trigger-set>
        <trigger-set name="MINOR">
            <trigger eventName="OpenNMS" delay="0">
                <value1>#FF9900</value1>
                <value2>0.60</value2>
                <value3>%os%,%ns%,%oc%,%nc%</value3>
            </trigger>
        </trigger-set>
        <trigger-set name="MAJOR">
            <trigger eventName="OpenNMS" delay="0">
                <value1>#CC3300</value1>
                <value2>0.70</value2>
                <value3>%os%,%ns%,%oc%,%nc%</value3>
            </trigger>
        </trigger-set>
        <trigger-set name="CRITICAL">
            <trigger eventName="OpenNMS" delay="0">
                <value1>#FF0000</value1>
                <value2>0.80</value2>
                <value3>%os%,%ns%,%oc%,%nc%</value3>
            </trigger>
        </trigger-set>
    <trigger-package>
</ifttt-config>
```

Chapter 26. DNS Resolver

The DNS Resolver is used internally by OpenNMS modules and functions to provide lookup functionality as required.

26.1. Modules that use DNS Resolution

• TelemetryD

26.2. Configuring DNS Resolution

In order to customize the DNS servers that are queried, the following commands can be used:

```
$ ssh -p 8201 admin@localhost
...
admin@minion()> config:edit org.opennms.features.dnsresolver.netty
admin@minion()> property-set nameservers 8.8.8.8,4.2.2.2:53,[::1]:5353
admin@minion()> property-set query-timeout-millis 5000
admin@minion()> property-set max-cache-size 10000
admin@minion()> config:update
```

If no nameservers are set (or set to an empty string), the servers configured by the system running the JVM will be used.

The resolved host names are cached for their TTL as specified in the returned DNS records. TTL handling can be customized by setting the min-ttl-seconds, max-ttl-seconds and negative-ttl-seconds properties in the configuration above.

26.3. Configuring Circuit Breaker

Circuit Breaker functionality exist that helps prevent your DNS infrastructure from being flooded with requests when multiple failures occur. It is enabled by default but can be disabled by setting breaker-enabled to false.

Additional parameters can be modified to tune the functionality of the circuit breaker:

```
$ ssh -p 8201 admin@localhost
...
admin@minion()> config:edit org.opennms.features.dnsresolver.netty
admin@minion()> property-set breaker-enabled true
admin@minion()> property-set breaker-failure-rate-threshold 80
admin@minion()> property-set breaker-wait-duration-in-open-state 15
admin@minion()> property-set breaker-ring-buffer-size-in-half-open-state 10
admin@minion()> property-set breaker-ring-buffer-size-in-closed-state 100
admin@minion()> config:update
```



If the circuit breaker is disabled, the lookup statistics lookupsSuccessful and lookupsFailed are no longer tracked.

26.4. Configuring Bulkhead

A bulkhead is used to limit the number of concurrent DNS lookups that can be made.

Additional parameters can be modified to tune the functionality of the circuit breaker:

```
$ ssh -p 8201 admin@localhost
...
admin@minion()> config:edit org.opennms.features.dnsresolver.netty
admin@minion()> property-set bulkhead-max-concurrent-calls 1000
admin@minion()> property-set bulkhead-max-wait-duration-millis 5100
admin@minion()> config:update
```

Chapter 27. Telemetry Daemon

The telemetry daemon (telemetryd) provides an extensible framework you can use to handle sensor data pushed to *OpenNMS Meridian*. Use the framework to support applications that use different protocols to transfer metrics. With *telemetryd*, operators can define listeners supporting different protocols to receive the telemetry data and adapters transferring the received data into generic formats like flows or performance data.




Figure 41. Generic component overview of components in telemetryd

The configuration is split in two parts. *Listeners* and attached *Parsers* on one side, receive telemetry data transported over a specific protocol and parse the protocol according to its specification. On the other side, *Adapters* pick up the parsed data and enrich it before persisting it.

Queues transport the parsed telemetry data from *Parsers* to *Adapters* by binding a specific *Parser* to a specific *Adapter*.

27.1. Listeners and Parsers

Listeners receive sensor data from an external source and hand them off to *Parsers*, which handle the transport protocol format and extract the transported data.

A *Listener* does the transport protocol handling like opening a socket and accepting incoming connections. The received messages are then passed to the parser configured for the *Listener* which parses the concrete protocol implementation and extracts all available information out of the received message. For further processing, the extracted data is handed over to the configured queue.

For example: a *Listener* may open a UDP socket for receiving packets and an assigned *Parser* parses the incoming IPFIX packets.

Parsers and *Listeners* must work together closely. Therefore, they cannot be combined in any random way. Which *Parser* is supported by which *Listener* is described in the documentation of each respective *Parser*.

27.2. Adapters

Adapters enrich and process the data dispatched over a queue. They receive the data from queue and transform it into a format usable by *OpenNMS Meridian*. Adapters can also enrich the incoming data to attach node or interface information, depending on information already available.

For example: an *Adapter* may be used to transform telemetry data received via sFlow into performance data and persist it to the applicable node.

As an *Adapter* must handle data dependent to a transport protocol, not all *Adapters* can be used in combination with any possible *Parser*. Which *Parsers* are supported by which *Adapters* is described in the documentation of each respective *Adapter*.



If you have multiple *Adapters*, the execution order is the same as defined in the telemetryd-configuration.xml.

27.2.1. Working with Minions

Listeners and parsers run on Minion, but adapters do not. Adapters run on Sentinel, while the main OpenNMS Meridian instance can run listeners, parsers, and adapters. When using Minion as a listener, you must use adapters on OpenNMS Meridian or Sentinel to transform the data.

27.3. Queues

Queues transfer data between *Parsers* and *Adapters* and are represented by a channel in the messaging system.

27.3.1. Configuring Queues

The following options can help fine-tune queue behavior:

Queue attribute (OpenNMS)	Key (Minion/Sen tinel)	Description	Default value
threads	queue.thread s	Number of threads used for consuming & dispatching messages.	(2 * number of cores)
queue-size	queue.size	Maximum number of messages to keep in memory while waiting to be dispatched.	10000
use-routing-key	queue.use- routing-key	Whether to use the routing key when forwarding messages to the broker. This enforces ordering of the messages.	true
batch-size	batch.size	Messages are aggregated in batches before being dispatched. When the batch reaches this size, it will be dispatched.	1000
batch-interval	batch.interv al	Messages are aggregated in batches before being dispatched. When the batch has been created for longer than this interval (ms) it will be dispatched, regardless of the current size.	500



When using Kafka as a message broker, setting use-routing-key to false allows the messages to be balanced across all partitions. This can be done safely for flows, but is not supported for metrics when using thresholding (order is required).

When setting these options in OpenNMS they can be added as an attribute to the <queue> element. For example:

```
<queue name="IPFIX" use-routing-key="false">
...
</queue>
```

When setting these options on Minion you can add them as parser properties, and on Sentinel as adapter properties:

```
name=IPFIX-Listener
class-name=org.opennms.netmgt.telemetry.listeners.UdpListener
parameters.host=0.0.0.0
parameters.port=4738
parsers.0.name=IPFIX
parsers.0.class-
name=org.opennms.netmgt.telemetry.protocols.netflow.parser.IpfixUdpParser
parsers.0.queue.use-routing-key=false
```

27.4. Push Sensor Data through Minion

Listeners and their *Parsers* may run on either *OpenNMS Meridian* or *Minion*, whereas adapters run on *OpenNMS Meridian* or *Sentinel*. If a *Listener* and its *Parsers* are running on *Minion*, the received messages will be automatically dispatched to the associated *Adapters* running in *OpenNMS Meridian* or *Sentinel* via a *Queue*. Minions can listen (receive) data, but requires OpenNMS Meridian or Sentinel to process.




Figure 42. Running Listener on a Minion forwarding packets using the messaging system

27.5. Reverse hostname resolution

Some *Parsers* support reverse hostname resolution to annotate IP addresses with the actual hostname. The *Minion* performs the reverse name lookup while parsing the protocol data. The resolved hostname, if found, is attached to the address information and both are sent to the *Adapter* for further processing.

The following *Parsers* currently support reverse hostname resolution: Netflow v5, Netflow v9, IPFIX and sFlow.

27.6. Listener Reference

27.6.1. TCP Listener

The *TCP Listener* accepts incoming TCP connections and forwards the TCP stream to a single *Parser*.

Facts

Class Name	org.opennms.netmgt.telemetry.listeners.TcpListene	
Supported on Minion	Yes	

Parameters

Table 131. Listener-specific parameters for the TcpListener

Paramete r	Description	Require d	Default value
host	IP address on which to bind the TCP port	optional	0.0.0.0
port	TCP port number on which to listen	optional	50000

27.6.2. UDP Listener

The *UDP Listener* can be used to open a UDP socket and forward the received packets to a *Parser*.

The *UDP Listener* can support multiple *Parsers* if all of these *Parsers* support protocol detection. If this is the case, each *Parser* defined for the *Listener* will be asked if it can handle the incoming packet. The first *Parser* that accepts the packet is then used to parse the packet and dispatch it to its *Queue*.

If only a single *Parser* is defined in the *Listener*, the packet is directly handed over for parsing.

Facts

Class Name	org.opennms.netmgt.telemetry.listeners.UdpListener	
Supported on Minion	Yes	

Parameters

Table 132. Listener-specific parameters for the UdpListener


Parameter	Description	Require d	Default value
host	IP address on which to bind the UDP port	optional	0.0.0.0
port	UDP port number on which to listen	optional	50000
maxPacketSiz e	Maximum packet size in bytes (anything greater will be truncated)	optional	8096

27.7. Protocol Reference

27.7.1. BGP Monitoring Protocol

The *BGP Monitoring Protocol (BMP)* provides a convenient interface for obtaining route views. The integration in *OpenNMS Meridian* allows you to use these route views, status updates and statistics for monitoring and management.

BMP integration overview



BMP TCP Parser

The BMP Parser accepts BMP connections from router packets using a TCP Listener.

Facts

Class Name org.opennms.netmgt.telemetry.protocols.bmp.parser.BmpParser

Parameters

Table 133. Parameters for the BMP Parser

Parameter	Description	Requir ed	Default value
dnsLookupsEnabled	Enable or disable DNS resolution of router and peer hostnames.	no	true
bulkhead.maxConcurre ntCalls	Limits the number of parallel parsing operations.	no	1000
bulkhead.maxWaitDura tionMs	Limits the amount of time to wait for a saturated bulkhead (in milliseconds).	no	5 Minutes

Configure BMP Listener on a Minion

To enable and configure a *TCP Listener* for BMP on Minion, connect to the *Karaf Console* and set the following properties:

\$ ssh -p 8201 admin@localhost

```
admin@minion()> config:edit --alias tcp-5000 --factory
org.opennms.features.telemetry.listeners
admin@minion()> config:property-set name BMP
admin@minion()> config:property-set class-name
org.opennms.netmgt.telemetry.listeners.TcpListener
admin@minion()> config:property-set parameters.port 5000
admin@minion()> config:property-set parsers.0.name BMP
admin@minion()> config:property-set parsers.0.class-name
org.opennms.netmgt.telemetry.protocols.bmp.parser.BmpParser
admin@minion()> config:update
```

The protocol must also be enabled on *OpenNMS Meridian* for the messages to be processed. If you do not specify the queue name, the fallback is the name of the parser.

BMP Telemetry Adapter

i

The BMP Telemetry Adapter handles *BMP* statistics received and parsed by the <u>BMP</u> Parser. Statistics received from the router are associated as performance data with that router. The router must exist as a regular node in *OpenNMS Meridian*.

OpenNMS Meridian uses the IP address exporting BMP messages to associate a router with the particular *OpenNMS Meridian* node. In addition, the node's metadata can specify a BGP ID, which will then be used to associate routers. If the parameter metaDataNodeLookup is not empty, it will be interpreted as a context:key metadata name, which will be used to lookup a node that has stored the queried BGP ID as a value in exactly this key.

Facts

Class Name org.opennms.netmgt.telemetry.protocols.bmp.adapter.BmpTelemetryAdapter

Parameters

Parameter	Description	Require d	Default value
metaDataNodeLookup	Enables lookup using BGP IDs.	no	

Table 134. Parameters for the BMP Telemetry Adapter

BMP Peer Status Adapter

The BMP Peer Status Adapter creates events for peer status changes. It handles *BMP* Peer Up and Down messages that the BMP Parser receives and parses, and converts to *OpenNMS Meridian* events. *OpenNMS Meridian* associates the created events with the router sending the messages. This router must exist as regular node in *OpenNMS Meridian*.

The events are called uei.opennms.org/bmp/peerUp and uei.opennms.org/bmp/peerDown.

OpenNMS Meridian uses the IP address exporting BMP messages to associate a router with the particular *OpenNMS Meridian* node. In addition, the node's metadata can specify a BGP ID, which will then be used to associate routers. If the parameter metaDataNodeLookup is not empty, it will be interpreted as a context:key metadata name, which will be used to lookup a node that has stored the queried BGP ID as a value in exactly this key.

Facts

Class Name org.opennms.netmgt.telemetry.protocols.bmp.adapter.BmpPeerStatusAdapter

Parameters

Table 135. Parameters for the BMP Telemetry Adapter

Parameter	Description	Require d	Default value
metaDataNodeLookup	Enables lookup using BGP IDs.	no	

OpenBMP Integration Adapter

The OpenBMP Integration Adapter integrates with an existing OpenBMP installation. It handles *BMP* messages the BMP Parser receives and parses, and creates *OpenBMP*-compatible messages, which are then passed to the *OpenBMP* Kafka cluster.

This setup replaces the *Collector* component of *OpenBMP*.

Facts

Class Name org.opennms.netmgt.telemetry.protocols.bmp.adapter.openbmp.BmpIntegrationAdapter

Parameters

Parame ter	Description	Requi red	Default value
kafka.*	Uses options to create OpenBMP Kafka producer. Allows all known Kafka settings, but prefixed with <mark>kafka</mark>	no	
topicPre fix	Prefix used before each Kafka topic.	no	

Table 136. Parameters for the OpenBMP Integration Adapter

27.7.2. IPFIX

The *IP Flow Information Export (IPFIX)* protocol is a vendor-neutral standard for transmitting traffic flow information. See Flow Support for details on flow support in *OpenNMS Meridian*.

IPFIX UDP Parser

The IPFIX UDP Parser accepts packets received by a UDP Listener and must forward them to an IPFIX Adapter.

The IPFIX UDP Parser supports protocol detection.

Facts

Class Name org.opennms.netmgt.telemetry.protocols.netflow.parser.IpfixUdpParser

Parameters

Table 137. Parameters for the IPFIX UDP Parser

Parameter	Description	Requir ed	Default value
templateTimeou t	Templates must be redeclared in the given duration or they will be dropped.	no	30 minutes
maxClockSkew	The maximum delta in seconds between exporter and Minion timestamps.	no	0
clockSkewEvent Rate	Used to rate-limit clock skew events in seconds.	no	3600
dnsLookupsEnab led	Used to enable or disable DNS resolution for flows.	no	true

IPFIX TCP Parser

The IPFIX TCP Parser accepts packets received by a TCP Listener and must forward them to a IPFIX Adapter.

Class Name org.opennms.netmgt.telemetry.protocols.netflow.parser.IpfixTcpParser

Parameters

This parser does not currently have any configurable parameters.

Configure IPFIX Listener on a Minion

To enable and configure a *TCP Listener* for IPFIX on Minion, connect to the *Karaf Console* and set the following properties:

```
$ ssh -p 8201 admin@localhost
...
admin@minion()> config:edit --alias tcp-50000 --factory
org.opennms.features.telemetry.listeners
admin@minion()> config:property-set name IPFIX
admin@minion()> config:property-set class-name
org.opennms.netmgt.telemetry.listeners.TcpListener
admin@minion()> config:property-set parameters.port 50000
admin@minion()> config:property-set parsers.0.name IPFIX
admin@minion()> config:property-set parsers.0.class-name
org.opennms.netmgt.telemetry.protocols.netflow.parser.IpfixParser
admin@minion()> config:update
```



The protocol must also be enabled on *OpenNMS Meridian* for the messages to be processed. If you do not specify the queue name, the fallback is the name of the parser.

IPFIX Adapter

The IPFIX Adapter handles *IPFIX* telemetry data received and parsed by either of the IPFIX UDP Parser or IPFIX TCP Parser. Received flows are decoded from the messages into the canonical flow format and published to the *flow repository*.

Facts

Class Name org.opennms.netmgt.telemetry.protocols.netflow.adapter.ipfix.IpfixAdapter

Parameters

Table 138. Parameters for the IPFIX TCP Parser

Parameter	Description	Requir ed	Default value
templateTimeou t	Templates must be redeclared in the given duration or they will be dropped.	no	30 minutes

Parameter	Description	Requir ed	Default value
maxClockSkew	The maximum delta in seconds between exporter and Minion time stamps.	no	0
clockSkewEvent Rate	Used to rate-limit clock skew events in seconds.	no	3600
dnsLookupsEnab led	Used to enable or disable DNS resolution for flows.	no	true

The parameter maxClockSkew in your parser definition enables clock skew detection for exporters. It specifies the maximum delta in seconds between exporter and Minion timestamps. If exceeded, an alarm will be generated for the exporting device. The default value is 0, so clock skew detection is disabled. Furthermore, a parameter clockSkewEventRate can be used to rate-limit clock skew events. The default is 3600 seconds, so every hour an event will be sent.

27.7.3. Junos Telemetry Interface

 \bigcirc

The *Junos Telemetry Interface (JTI)* allows users to push operational statistics asynchronously to *OpenNMS Meridian. OpenNMS Meridian* sends a request to stream periodic updates once to the device. Data is generated as Google protocol buffers (gpb) structured messages over *UDP*. For detailed information about *JTI*, see the Juniper Documentation.

To enable support for JTI, edit \${OPENNMS_HOME}/etc/telemetryd-configuration.xml set enabled=true for JTI protocol.

Enable JTI protocol in telemetryd-configuration.xml

```
<listener name="JTI-UDP-50000" class-name=</pre>
"org.opennms.netmgt.telemetry.listeners.simple.Udp" enabled="false">
    <parameter key="port" value="50000"/>
    <parser name="JTI-Parser" class-name=</pre>
"org.opennms.netmgt.telemetry.protocols.common.parser.ForwardParser" queue="JTI" />
</listener>
<queue name="JTI">
    <adapter name="JTI-GPB" class-name=
"org.opennms.netmgt.telemetry.protocols.jti.adapter.JtiGpbAdapter" enabled="false">
        <parameter key="script" value="${install.dir}/etc/telemetryd-adapters/junos-</pre>
telemetry-interface.groovy"/>
        <package name="JTI-Default">
            <rrd step="300">
                <rra>RRA:AVERAGE:0.5:1:2016</rra>
                <rra>RRA: AVERAGE: 0.5:12:1488</rra>
                <rra>RRA:AVERAGE:0.5:288:366</rra>
                <rra>RRA:MAX:0.5:288:366</rra>
                <rra>RRA:MIN:0.5:288:366</rra>
            </rrd>
        </package>
    </adapter>
</queue>
```

Apply the changes without restarting by sending a reloadDaemonConfig event in the CLI or the Web UI:

Send a reloadDaemonConfig event through CLI

\${OPENNMS_HOME}bin/send-event.pl -p 'daemonName Telemetryd'
uei.opennms.org/internal/reloadDaemonConfig

By default, this will open a UDP socket bound to 0.0.0.0:50000 to which *JTI* messages can be forwarded.

Configure JTI Listener on a Minion

To enable and configure a *UDP Listener* for JTI on Minion, connect to the *Karaf Console* and set the following properties:

```
$ ssh -p 8201 admin@localhost
...
admin@minion()> config:edit --alias udp-50000 --factory
org.opennms.features.telemetry.listeners
admin@minion()> config:property-set name JTI
admin@minion()> config:property-set class-name
org.opennms.netmgt.telemetry.listeners.UdpListener
admin@minion()> config:property-set parameters.port 50000
admin@minion()> config:property-set parsers.0.name JTI
admin@minion()> config:property-set parsers.0.class-name
org.opennms.netmgt.telemetry.protocols.common.parser.ForwardParser
admin@minion()> config:update
```



The protocol must also be enabled on *OpenNMS Meridian* for the messages to be processed.

JTI Adapter

The JTI adapter handles *Junos Telemetry Interface* payloads. Messages are decoded using the published protobuf specifications and forwarded to a JSR-223-compatible script (i.e., Beanshell or Groovy) for further processing. Use the script extension to extract the desired metrics from the JTI messages and persist the results as time series data.

Facts

Class Name org.opennms.netmgt.telemetry.protocols.jti.adapter.JtiGpbAdapter

Parameters

Table 139. Adapter specific parameters for the JtiGpbAdapter

]	Paramete r	Description	Require d	Default value
	script	Full path to the script used to handle the JTI messages	required	(none)

Scripting

The script will be invoked for every JTI message that is received and succesfully decoded.

The following globals will be passed to the script:

Table 140. Globals passed to the scri

Param eter	Description	Туре
agent	The agent (node) against which the metrics will be associated.	org.opennms.netmgt.collection.api.Collectio nAgent

Param eter	Description	Туре
builder	Builder in which to add the resources and metrics.	org.opennms.netmgt.collection.support.build er.CollectionSetBuilder
msg	Decoded JTI message from which the metrics should be extracted.	org.opennms.netmgt.telemetry.adapters.jti.p roto.TelemetryTop

27.7.4. NetFlow v5

See Flow Support for details on flow support in OpenNMS Meridian.

Netflow v5 UDP Parser

The Netflow v5 UDP Parser accepts packets received by a UDP Listener and must forward them to a Netflow v5 Adapter.

The Netflow v5 UDP Parser supports protocol detection.

Facts

Class Name org.opennms.netmgt.telemetry.protocols.netflow.parser.Netflow5UdpParser

Parameters

Table 141. Parameters for the Netflow v5 UDP Parser

Parameter	Description	Requir ed	Default value
maxClockSkew	The maximum delta in seconds between exporter and Minion timestamps.	no	0
clockSkewEventR ate	Used to rate-limit clock skew events in seconds.	no	3600
dnsLookupsEnabl ed	Used to enable or disable DNS resolution for flows.	no	true

Netflow v5 Adapter

The Netflow v5 Adapter is used to handle *Netflow v5* payloads received and parsed by by the Netflow v5 UDP Parser. Flows are decoded from the messages into the canonical flow format and are published to the *flow repository*

Facts

Class Name org.opennms.netmgt.telemetry.protocols.netflow.adapter.netflow5.Netflow5Adapter

Parameters

This adapter does not currently have any configurable parameters.

27.7.5. NetFlow v9

See Flow Support for details on flow support in *OpenNMS Meridian*.

Netflow v9 UDP Parser

The Netflow v9 UDP Parser accepts packets received by a UDP Listener and must forward them to a Netflow v9 Adapter.

The Netflow v9 UDP Parser supports protocol detection.

Facts

Class Name org.opennms.netmgt.telemetry.protocols.netflow.parser.Netflow9UdpParser

Parameters

Table 142. Parameters for the Netflow v9 UDP Parser

Parameter	Description	Requir ed	Default value
templateTimeou t	Templates must be re-declared in the given duration or they will be dropped.	no	30 minutes
maxClockSkew	The maximum delta in seconds between exporter and Minion timestamps.	no	0
clockSkewEvent Rate	Used to rate-limit clock skew events in seconds.	no	3600
dnsLookupsEnab led	Used to enable or disable DNS resolution for flows.	no	true

Netflow v9 Adapter

The Netflow v9 Adapter is used to handle *Netflow v9* payloads received and parsed by by the Netflow v9 UDP Parser. Flows are decoded from the messages into the canonical flow format and are published to the *flow repository*

Facts

Class Name org.opennms.netmgt.telemetry.protocols.netflow.adapter.netflow9.Netflow9Adapter

Parameters

This adapter does not currently have any configurable parameters.

 \bigcirc

The parameter maxClockSkew in your parser definition enables clock skew detection for exporters. It specifies the maximum delta in seconds between exporter and Minion time stamps. If exceeded, an alarm will be generated for the exporting device. The default value is 0, so clock skew detection is disabled. Furthermore, a parameter clockSkewEventRate can be used to rate-limit clock skew events. The default is 3600 seconds, so every hour an event will be sent.

27.7.6. Cisco NX-OS Telemetry

The *Cisco NX-OS Telemetry* allows to push operational statistics asynchronously to *OpenNMS Meridian*. *OpenNMS Meridian* sends a request to stream periodic updates once to the device. Data is generated as Google protocol buffers (gpb) structured messages over *UDP*. Detailed information about *NX-OS* can be found in NXOS Documentation.

To enable support for NX-OS Telemetry, edit \${OPENNMS_HOME}/etc/telemetryd-configuration.xml set enabled=true for NXOS protocol.

Enable NX-OS protocol in telemetryd-configuration.xml

```
listener name="NXOS-UDP-50001" class-name=
"org.opennms.netmgt.telemetry.listeners.simple.Udp" enabled="false">
    <parameter key="port" value="50001"/>
    <parser name="NXOS-GPB" class-name=</pre>
"org.opennms.netmgt.telemetry.protocols.common.parser.ForwardParser" queue="NXOS" />
</listener>
<queue name="NXOS">
    <adapter name="NXOS-GPB" class-name=
"org.opennms.netmgt.telemetry.protocols.nxos.adapter.NxosGpbAdapter" enabled="false">
        <parameter key="script" value="${install.dir}/etc/telemetryd-adapters/cisco-</pre>
nxos-telemetry-interface.groovy"/>
        <package name="NXOS-Default">
            <rrd step="300">
                <rra>RRA:AVERAGE:0.5:1:2016</rra>
                <rra>RRA:AVERAGE:0.5:12:1488</rra>
                <rra>RRA:AVERAGE:0.5:288:366</rra>
                <rra>RRA:MAX:0.5:288:366</rra>
                <rra>RRA:MIN:0.5:288:366</rra>
            </rrd>
        </package>
    </adapter>
</queue>
```

Apply the changes without restarting by sending a reloadDaemonConfig event in the CLI or the WebUI:

\${OPENNMS_HOME}bin/send-event.pl -p 'daemonName Telemetryd'
uei.opennms.org/internal/reloadDaemonConfig

By default, this will open a UDP socket bound to 0.0.0.0:50001 to which *NXOS* messages can be forwarded.

Configure NX-OS Listener on a Minion

To enable and configure an *UDP Listener* for NX-OS on Minion, connect to the *Karaf Console* and set the following properties:

```
$ ssh -p 8201 admin@localhost
...
admin@minion()> config:edit --alias udp-50001-nxos --factory
org.opennms.features.telemetry.listeners
admin@minion()> config:property-set name NXOS
admin@minion()> config:property-set class-name
org.opennms.netmgt.telemetry.listeners.UdpListener
admin@minion()> config:property-set parameters.port 50001
admin@minion()> config:property-set parsers.0.name NXOS
admin@minion()> config:property-set parsers.0.name NXOS
admin@minion()> config:property-set parsers.0.class-name
org.opennms.netmgt.telemetry.protocols.common.parser.ForwardParser
admin@minion()> config:update
```



The protocol must also be enabled on *OpenNMS Meridian* for the messages to be processed.

Cisco NX-OS Adapter

The NX-OS adapter is used to handle *Cisco NX-OS Telemetry* payloads. Messages are decoded using the published protobuf (proto3) specifications and forwarded to a JSR-223 compatible script (i.e. Beanshell or Groovy) for further processing. Using the script extension you can extract the desired metrics from the NX-OS messages and persist the results as time series data.

Facts

Class Name org.opennms.netmgt.telemetry.protocols.nxos.adapter.NxosGpbAdapter

Parameters

Paramete	Description	Require	Default
r		d	value
script	Full path to the script used to handle the NXOS messages	required	(none)

Scripting

The script will be invoked for every NX-OS message that is received and succesfully decoded.

The following globals will be passed to the script:

<i>Table 144.</i>	Globals	passed to	the script	-
100001111	01000000	<i>p c c c c c c c c c c</i>	<i>cite oei cp c</i>	

Param eter	Description	Туре
agent	The agent (node) against which the metrics will be associated	org.opennms.netmgt.collection.api.Collecti onAgent
builder	Builder in which the resources and metrics should be added	org.opennms.netmgt.collection.support.buil der.CollectionSetBuilder
msg	Decoded NX-OS message from which the metrics should be extracted	org.opennms.netmgt.telemetry.adapters.nxos .proto.TelemetryBis

27.7.7. sFlow

sFlow is capable of transporting both, telemetry data and flow information. *OpenNMS Meridian* can utilize both data types and extract and persist accordingly.

See Flow Support for details on flow support in OpenNMS Meridian.

sFlow UDP Parser

The sFlow UDP Parser accepts packets received by a UDP Listener and must forward them to a sFlow Adapter.

The sFlow UDP Parser supports protocol detection.

Facts

Class Name org.opennms.netmgt.telemetry.protocols.sflow.parser.SFlowUdpParser

Parameters

Table 145. Parameters for the Netflow v5 UDP Parser

Parai	meter	Description	Require d	Default value
dnsLo	okupsEnabled	Used to enable or disable DNS resolution for flows.	no	true

sFlow Adapter

The sFlow Adapter is used to handle *sFlow* data received and parsed by the sFlow Parser. Flows are decoded from the messages into the canonical flow format and are published to the *flow repository*.

Class Name org.opennms.netmgt.telemetry.protocols.sflow.adapter.SFlowAdapter

Parameters

This adapter does not currently have any configurable parameters.

sFlow Telemetry Adapter

The sFlow Telemetry Adapter is used to handle *sFlow* telemetry data received and parsed by the sFlow UDP Parser. The telemetry data is forwarded to a JSR-223 compatible script (i.e. Beanshell or Groovy) for further processing. Using the script extension you can extract the desired metrics from the sFlow messages and persist the results as time series data.

Facts

Class Name org.opennms.netmgt.telemetry.protocols.sflow.adapter.SFlowTelemetryAdapter

Parameters

Table 146. Adapter specific parameters

Parameto	e Description	Require	Default
r		d	value
script	Full path to the script used to handle the sFlow messages	required	(none)

Scripting

The script will be invoked for every sFlow (extended) counter sample that is received.

The following globals will be passed to the script:

Table 147. Globals passed to the script	Table 147.	Globals	passed to	the	script
---	------------	---------	-----------	-----	--------

Param eter	Description	Туре
agent	The agent (node) against which the metrics will be associated	org.opennms.netmgt.collection.api.Collection Agent
builder	Builder in which the resources and metrics should be added	org.opennms.netmgt.collection.support.builde r.CollectionSetBuilder
msg	sFlow (extended) counter sample	dynamic Map

See sFlow Specification for the contained fields and their meaning.

27.7.8. Graphite Telemetry

The Graphite telemetry adapter allows you to push telemetry data over UDP to OpenNMS Meridian

using the *plaintext* protocol.

To enable support for plaintext Graphite over UDP, edit \${OPENNMS_HOME}/etc/telemetrydconfiguration.xml set enabled=true for the Graphite protocol.

```
Enable Graphite protocol in telemetryd-configuration.xml
```

```
"org.opennms.netmgt.telemetry.listeners.UdpListener" enabled="true">
       <parameter key="port" value="2003"/>
       <parser name="Graphite-Parser" class-name=</pre>
"org.opennms.netmgt.telemetry.protocols.common.parser.ForwardParser" queue="Graphite"
/>
   </listener>
   <queue name="Graphite">
       <adapter name="Graphite" class-name=
"org.opennms.netmgt.telemetry.protocols.graphite.adapter.GraphiteAdapter" enabled=
"true">
           <parameter key="script" value="/Users/ranger/git/opennms-</pre>
work/target/opennms-2020.1.22/etc/telemetryd-adapters/graphite-telemetry-
interface.groovy"/>
            <package name="Graphite-Default">
               <rrd step="300">
                   <rra>RRA:AVERAGE:0.5:1:2016</rra>
                   <rra>RRA:AVERAGE:0.5:12:1488</rra>
                   <rra>RRA:AVERAGE:0.5:288:366</rra>
                   <rra>RRA:MAX:0.5:288:366</rra>
                   <rra>RRA:MIN:0.5:288:366</rra>
               </rrd>
           </package>
       </adapter>
   </queue>
```

Apply the changes without restarting by sending a reloadDaemonConfig event in the CLI or the WebUI:

Send a reloadDaemonConfig event through CLI

```
${OPENNMS_HOME}bin/send-event.pl -p 'daemonName Telemetryd'
uei.opennms.org/internal/reloadDaemonConfig
```

By default, this will open a UDP socket bound to 0.0.0.0:2003 to which *Graphite* messages can be forwarded.

Configure Graphite Listener on a Minion

To enable and configure a *UDP Listener* for Graphite on Minion, connect to the *Karaf Console* and set the following properties:

```
$ ssh -p 8201 admin@localhost
...
admin@minion()> config:edit --alias udp-2003 --factory
org.opennms.features.telemetry.listeners
admin@minion()> config:property-set name Graphite
admin@minion()> config:property-set class-name
org.opennms.netmgt.telemetry.listeners.UdpListener
admin@minion()> config:property-set parameters.port 2003
admin@minion()> config:property-set parsers.0.name Graphite
admin@minion()> config:property-set parsers.0.class-name
org.opennms.netmgt.telemetry.protocols.common.parser.ForwardParser
admin@minion()> config:update
```



The protocol must also be enabled on *OpenNMS Meridian* for the messages to be processed.

Graphite Adapter

The Graphite adapter is used to handle *Graphite* payloads. Messages are decoded and forwarded to a JSR-223 compatible script (i.e. Beanshell or Groovy) for further processing. Using the script extension you can extract the desired metrics from the Graphite messages and persist the results as time series data.

Facts

Class Name org.opennms.netmgt.telemetry.protocols.graphite.adapter.GraphiteAdapter

Parameters

Table 148. Adapter specific parameters for the GraphiteAdapter

Paramete r	Description	Require d	Default value
script	Full path to the script used to handle the Graphite messages	required	(none)

Scripting

The script will be invoked for every Graphite message that is received and succesfully decoded.

The following globals will be passed to the script:

Table 149. Globals passed to the script

Paran eter	Description	Туре
agent	The agent (node) against which the metrics will be associated	<pre>org.opennms.netmgt.collection.api.CollectionAg ent</pre>

Param eter	Description	Туре
builder	Builder in which the resources and metrics should be added	org.opennms.netmgt.collection.support.builder. CollectionSetBuilder
msg	Decoded message from which the metrics should be extracted	org.opennms.netmgt.telemetry.protocols.graphit e.adapter.GraphiteMetric

Chapter 28. Elasticsearch Integration

OpenNMS Meridian persists/forwards certain data to Elasticsearch.

The following chapters describe the configuration possibilities as well as the available features.

Internally all *Elasticsearch* integrations use the Jest library to access the *Elasticsearch* ReST interface.

28.1. Configuration

The location of the configuration file depends on the feature. For flows, it can be found in \${OPENNMS_HOME}/etc/org.opennms.features.flows.persistence.elastic.cfg.

The following properties can be set:

Property	Description	Requ ired	default
elasticUrl	URL(s) to Elasticsearch nodes. Can either point directly to ReST API or seed nodes. The format is: <host>:<port>. Comma separate multiple values.</port></host>	requi red	http://localhost: 9200
elasticIndexStrateg y	Index strategy for data, allowed values <i>yearly, monthly, daily, hourly</i>	optio nal	daily
globalElasticUser	Username to use for all nodes, when X-Pack Security is configured.	optio nal	-
globalElasticPassw ord	Password to use for all nodes, when <i>X-Pack Security</i> is configured.	optio nal	-
ignoreCertificates	Set this to ignore HTTPS/SSL/TLS certificates.	optio nal	false
defaultMaxTotalCo nnectionPerRoute	Sets the default max connections per route. If a negative value is given, the value is ignored.	optio nal	<available processors> * 2</available
maxTotalConnectio n	Sets the default max total connections. If a negative value is given, the value is ignored.	optio nal	<max connections<br="">per route> * 3</max>
nodeDiscovery	Enable/Disable node discovery. Valid values are true false.	optio nal	false
nodeDiscoveryFreq uency	Defines the frequency in seconds in which the nodes are re-discovered. Must be set, if discovery=true	optio nal	-
proxy	Allows defining a HTTP proxy. Only accepts valid URLs.	optio nal	-

Property	Description	Requ ired	default
httpCompression	Allows the use of HTTP compression.	optio nal	-
retries	Defines how many times an operation is retried before considered failed.	optio nal	0
retryCooldown	Defines the cooldown in ms to wait before retrying. Value of 0 means no cooldown. Value must be >= 0.	optio nal	500
connTimeout	Defines the connection timeout in ms.	optio nal	5000
readTimeout	Defines the read timeout in ms.	optio nal	30000
bulkRetryCount	Defines the number of retries performed before a bulk operation is considered as failed. When bulk operations fail, only the failed items are retried.	optio nal	5
settings.index.numb er_of_shards	The number of primary shards that an index should have. Refer to Elasticsearch Reference → Index Modules for more details.	optio nal	-
settings.index.numb er_of_replicas	The number of replicas each primary shard has. Refer to Elasticsearch Reference → Index Modules for more details.	optio nal	-
settings.index.refres h_interval	How often to perform a refresh operation, which makes recent changes to the index visible to search. Refer to Elasticsearch Reference \rightarrow Index Modules for more details.	optio nal	-
settings.index.routi ng_partition_size	The number of shards a custom routing valuce can go to. Refer to Elasticsearch Reference → Index Modules for more details.	optio nal	-
indexPrefix	Prefix is prepended to the index and template names. Can be used in cases where you want to share the same Elasticsearch cluster with many <i>OpenNMS Meridian</i> instances.	optio nal	-



If a configuration management tool is used, the properties file can be created and is used as startup configuration



If credentials are provided preemptive auth is used for all defined Elasticsearch nodes.

```
elasticUrl=http://elastic:9200
elasticIndexStrategy=daily
globalElasticUser=elastic
globalElasticPassword=changeme
```

28.2. Credentials

It is possible to define credentials for each Elasticsearch node individually. Credentials for each node must be stored in $OPENNMS_HOME/etc/elastic-credentials.xml$.

Custom credentials

```
<?xml version="1.0" encoding="UTF-8" standalone="yes"?>
<elastic-credentials>
<credentials url="http://localhost:9200" username="ulf" password="ulf" />
<credentials url="https://10.10.0.1:9333" username="ulf" password="flu" />
</elastic-credentials>
```

6

Credentials are globally defined and will be used by each feature.

28.3. Features

28.3.1. Feature Matrix

The following features leverage *Elasticsearch* and are compatible with version 7.x.x.

Name	Enabled by default	Feature
Event and Alarm Forwarder	no	opennms-es-rest
Flow Support	yes	opennms-flows
Situation Feedback (ALEC)	no	opennms-situation-feedback
Alarm History	yes	opennms-alarm-history-elastic

28.3.2. Event Forwarder

The *Event Forwarder* (formerly known as the *Elasticsearch ReST plugin*) forwards events to Elasticsearch.

The events in *Elasticsearch* can then be used for indexing, long time archival, plotting with *Grafana* and browsing with *Kibana*.

6

This feature uses the *Elasticsearch* ReST interface and can interact with cloud-hosted *Elasticsearch* instances.



Configuration

Theconfigurationisheldin\${OPENNMS_HOME}/etc/org.opennms.plugin.elasticsearch.rest.forwarder.cfg.Please refer to sectionConfiguring Elasticsearch in order to configure *Elasticsearch* connection settings.

Besides the general *Elasticsearch* connection settings, the following properties are supported to configure the *Event Forwarder*:

Parameter	Default Value	Requi red	Description
logEventDescr iption	true	option al	Whether to forward the event description field to <i>Elasticsearch</i> . It can be disabled because it contains a long text field that can be redundant with the rest of the metadata included in the event.
archiveAssetD ata	true	option al	If true The following attributes representing useful node asset fields from the node asset table are included in archived events and alarms. These are included only where the values are not null or empty strings in the table.
			(asset-latitude,asset-longitude,asset-region,asset-building,asset- floor,asset-room,asset-rack,asset-slot,asset-port,asset- category,asset-displaycategory,asset-notifycategory,asset- pollercategory,asset-thresholdcategory,asset- managedobjecttype,asset-managedobjectinstance,asset- manufacturer,asset-vendor,asset-modelnumber,parent- nodelabel,parent-nodeid,parent-foreignsource,parent-foreignid)
groupOidParam eters	false	option al	If true all oid from the event parameters are stored in a single array p_oids instead of a flattened structue.
logAllEvents	false	option al	If changed to true, then archive all events even if they have not been persisted in the <i>OpenNMS Meridian</i> database.
batchSize	200	option al	Increase this value to enable batch inserts into <i>Elasticsearch</i> . This is the maximum size of a batch of events that is sent to <i>Elasticsearch</i> in a single connection.
batchInterval	500	option al	The maximum time interval in milliseconds between batch events (recommended: 500ms) when a batchSize value greater than 1 is being used.

Once you are sure everything is correctly configured, you can activate the *Event Forwarder* by logging into the *OSGi* console and installing the feature: opennms-es-rest.

ssh admin@localhost -p 8101 feature:install opennms-es-rest

Loading Historical Events

It is possible to load historical *OpenNMS Meridian* events into *Elasticsearch* from the *OpenNMS Meridian* database using a *karaf* console command. The command uses the *OpenNMS Meridian* Events ReST interface to retrieve a set number of historical events and forward them to *Elasticsearch*. Because we are using the ReST interface it is also possible to contact a remote *OpenNMS Meridian* and download its events into *Elasticsearch* by using the correct remote URL and credentials.

The following example sends historic events to *Elasticsearch* using the *karaf* console:

```
# open karaf command prompt using
# ssh -p 8101 admin@localhost
karaf> opennms:send-events-to-elasticsearch --username admin --password admin --url
http://localhost:8980 --limit 10 --offset 0
```



For more details, consolidate the --help option of the command.

Index Definition

The index names used to store the events uses the following form: opennms-raw-events-<index-strategy>/type/id

For example (assuming an index strategy of monthly):

```
opennms-events-raw-2017-01/eventdata/11549
```

Viewing events using Kibana Sense

Kibana Sense is a *Kibana* app which allows you to run queries directly against *Elasticsearch*. (https://www.elastic.co/guide/en/sense/current/installing.html)

If you install *Kibana Sense* you can use the following commands to view the events sent to *Elasticsearch* You should review the *Elasticsearch* ReST API documentation to understand how searches are specified. (See https://www.elastic.co/guide/en/elasticsearch/reference/current/search.html)

Example searches to use in *Kibana Sense* (you can copy the whole contents of this panel into *Kibana Sense* as a set of examples)

```
# Search all the events indexes
GET /opennms-events-*/_search
# Search all the raw events indexes
GET /opennms-events-raw*/_search
# Delete all the events indexes
DELETE /opennms-events-*/
# Get all the raw events indexes
GET /opennms-events-raw*/
```

Mapping of Events to Elasticsearch

Overview of index mapping

In *OpenNMS Meridian*, Event table entries contain references to associated node, asset, service and journal message tables. In *Elasticsearch*, we must flatten these entries into a single index entry for each insertion. Thus each index entry contains more context information than would be found in the actual *OpenNMS Meridian* event. This context information includes the associated node and asset table information which was current when (but may have changed since) the event was archived.

In the *Table of Index Mappings* below we have example event JSON entries retrieved using a sense command. The table helps illustrate how *OpenNMS Meridian* saves data in *Elasticsearch*.

Internal *Elasticsearch* fields always begin with an underscore character. The internal fields id, _index and _type are combined to give the unique identifier for an entry as described above under Index Definitions. All of the fields under _source represent the stored event (_Elasticsearch documentation refers to source entries as indexed documents). The ID of each event is included in the _source id field and also duplicated in the internal _id.

Events in the *OpenNMS Meridian* events table (i.e. those corresponding to logs or traps) are copied directly to the opennms-events-raw- indexes. In *OpenNMS Meridian* events can contain parameters which are key-value pairs referencing additional data stored when the event is created. In *Elasticsearch* these parameters are always stored in separate fields in the index with names beginning with p_{-}

Events have severity fields defined as integers (long) and also corresponding severity_text fields which give the text equivalent (Critical, Major, Minor, Normal, Cleared).

Table of Index Mapping

The following table describes the mapping of simple *OpenNMS Meridian* events to the Raw Events Index. Note that fields that begin with an underscore (_) are internal to Elasticsearch.

Event Index Fields		Description		
Event Field	Example Event JSON	Ty pe	Description	
"_index":	"_index": "opennms-raw-events- 2017.03",	stri ng	_index is the index in which this event is stored.	
"_type":	"_type": "eventdata",	stri ng	_type either alarmdata or eventdata	
"_id":	"_id": "1110",	stri ng	_id field matches the event or alarm ID, if present.	
"_score":	"_score": 1,	lon g	Internal Elasticsearch ranking of the search result.	
"_source":	"_source": {	stri ng	_source contains the data of the index entry.	
"@timesta mp":	"@timestamp": "2017-03- 02T15:20:56.861Z",	dat e	<pre>event time from event.getTime().</pre>	
"dom":	"dom": "2",	lon g	Day of month from <code>@timestamp</code> .	
"dow":	"dow": "5",	lon g	Day of week from @timestamp.	
"hour":	"hour": "15",	lon g	Hour of day from @timestamp.	
"eventdes cr":	"eventdescr": "Alarm 30 Cleared",</a 	stri ng	Event description.	
"eventsev erity":	"eventseverity": "3",	lon g	Event severity.	
"eventsev erity_text ":	"eventseverity_text": "Normal",	stri ng	Text representation of severity value.	
"eventsou rce":	"eventsource": "AlarmChangeNotifier",	stri ng	OpenNMS event source.	
"eventuei ":	"eventuei": "uei.opennms.org/plugin/AlarmChange NotificationEvent/AlarmCleared",	stri ng	OpenNMS universal event identifier (UEI) of the event.	
"id":	"id": "1110",	stri ng	Event ID.	

Event Index Fields		Description		
"interface ":	"interface": "127.0.0.1",	stri ng	IP address of the event.	
"ipaddr":	"ipaddr": "/127.0.0.1",	stri ng	IP address of the event.	
"logmsg":	"logmsg": "Alarm 30 Cleared",</a 	stri ng	Log message of the event.	
"logmsgd est":	"logmsgdest": "logndisplay",	stri ng	Log Destination of the Event.	
"asset- category":	"asset-category": "Power",	stri ng	All asset_ entries correspond to fields in the Asset Table of the node referenced in the event. These fields are only present if populated in the asset table.	
"asset- building":	"asset-building": "55",	stri ng		
"asset- room":	"asset-room": "F201",	stri ng		
"asset- floor":	"asset-floor": "Gnd",	stri ng		
"asset- rack":	"asset-rack": "2101",	stri ng		
"categorie s":	"categories": "",	stri ng	categories corresponds to node categories table. This is a comma-separated list of categories associated with this node ID. This field is indexed so separate values can be searched.	
"foreignid ":	"foreignid": "1488375237814",	stri ng	Foreign ID of the node associated with the event.	
"foreigns ource":	"foreignsource": "LocalTest",	stri ng	Foreign source of the node associated with event.	
"nodeid":	"nodeid": "88",	stri ng	Node ID of the node associated with the alarm or event.	
"nodelabe l":	"nodelabel": "localhost",	stri ng	Node label of the node associated with the alarm or event.	
"nodesysl ocation":	"nodesyslocation": "Unknown (edit /etc/snmp/snmpd.conf)",	stri ng	SNMP syslocation of the node associated with the alarm or event.	

Event Index Fields		Description		
"nodesys name":	"nodesysname": "localhost.localdomain",	stri ng	SNMP sysname of the node associated with the alarm or event.	
"qosalar mstate": null,	"qosalarmstate":			

28.3.3. Flow Support

Flow Support is described in detail here.

When persisting flows into Elasticsearch, every flow is represented by a single document.

Field	Description
@timestamp	Timestamp in milliseconds at which the flow was sent by the exporter.
location	Monitoring location at which the flow was received. This will be Default unless you are using Minion.
netflow.bytes	Number of bytes transferred in the flow.
netflow.last_swit ched	Timestamp in milliseconds at which the last packet of the flow was transferred.
netflow.direction	ingress or egress
netflow.first_swi tched	Timestamp in milliseconds at which the first packet of the flow was transferred.
netflow.input_snm P	SNMP interface index on which packets related to this flow were received.
<pre>netflow.output_sn mp</pre>	SNMP interface index on which packets related to this flow were forwarded.

The following table describes a subset of the fields in the flow document:

28.3.4. Situation Feedback

6

Full documentation on *Situation Feedback* is available here.

When persisting Situation Feedback, feedback on each related alarm is represented by a document as follows:

Field	Description
@timestamp	Timestamp in milliseconds when the feedback was submitted.
situation_key	The reduction key of the situation.

Field	Description
alarm_key	The reduction key of the related alarm.
feedback_type	One of CORRECT, FALSE_POSITIVE or FALSE_NEGATIVE
situation_fingerprint	A hash calculated on the situation when the feedback was submitted.
reason	A text string provided with the feedback.
user	The user that submitted the feedback.

28.3.5. Alarm History

See Alarm History.

Chapter 29. Flow Support

29.1. Introduction

OpenNMS Meridian supports receiving, decoding and persisting flow information sent via *Netflow* v5, *Netflow* v9, *IPFIX* and *sFlow*. While flows offer a great breadth of information, the current focus of the support in *OpenNMS Meridian* is aimed at:

- Network diagnostic: Being able to view the top protocols and top talkers within the context of a particular network interface.
- Forensic analysis: Persisting the flows for long term storage.

29.1.1. How it works

At a high level:

- telemetryd is used to receive and decode flows on both OpenNMS Meridian and Minion.
- The *telemetryd* adapters convert the flows to a canonical flow model and dispatch these to the *flow repository*.
- The *flow repository* enriches the flows and persists them to Elasticsearch:
 - Flows are tagged with an application name via the Classification Engine.
 - Metadata related to associated nodes such as ids and categories are also added to the flows.
- The *REST API* supports generating both summaries and time series data from the flows stored in the *flow repository*.
- *OpenNMS Helm* is used to visualize the flow data using the *flow datasource* that interfaces with the *OpenNMS Meridian REST API*.

29.2. Setup

Here we assume that you already have:

- An Elasticsearch cluster setup with the elasticsearch-drift-plugin installed on every Elasticsearch node.
- An instance of Grafana OpenNMS Helm v2.0.0 or greater installed.

29.2.1. Configuration Elasticsearch persistence

From a Karaf shell on your *OpenNMS Meridian* instance, start by configuring the flow persistence to use your Elasticsearch cluster:

```
$ ssh -p 8101 admin@localhost
...
admin@opennms()> config:edit org.opennms.features.flows.persistence.elastic
admin@opennms()> config:property-set elasticUrl http://elastic:9200
admin@opennms()> config:update
```



Thisconfigurationisstoredin\${OPENNMS_HOME/etc/org.opennms.features.flows.persistence.elastic.cfg.SeeGeneral Elasticsearch Configuration for a complete set of options.See

29.2.2. Enabling a protocol

Next, enable one or more of the protocols you would like to handle in \${OPENNMS_HOME}/etc/telemetryd-configuration.xml.



In this example we enable the NetFlow v5 protocol, but the same process can be repeated for any of the other flow related protocols.

Enable NetFlow v5 in telemetryd-configuration.xml

Apply the changes without restarting by sending a reloadDaemonConfig event via the CLI:

Send a reloadDaemonConfig event through CLI

\${OPENNMS_HOME}bin/send-event.pl -p 'daemonName Telemetryd'
uei.opennms.org/internal/reloadDaemonConfig

This will open a UDP socket bound to 0.0.0.8877 to which *NetFlow v5* messages can be forwarded.

29.2.3. Linking to OpenNMS Helm in the Web UI

In order to access flow related graphs from the *OpenNMS Meridian* web interface, you must configure a link to your instance of *OpenNMS Helm*.

```
$ ssh -p 8101 admin@localhost
...
admin@opennms()> config:edit org.opennms.netmgt.flows.rest
admin@opennms()> config:property-set flowGraphUrl
'http://grafana:3000/dashboard/flows?node=$nodeId&interface=$ifIndex'
admin@opennms()> config:update
```

G

This URL can optionally point to other tools as well. It supports placeholders for \$nodeId, \$ifIndex, \$start and \$end.

Once configured, an icon will appear on the top right corner of a resource graph for an SNMP interface if there is flow data for that interface.

Configuring a listener on a Minion (Optional)

In this example we'll look at enabling a generic listener for the NetFlow v5 protocol on Minion.



NetFlow v5 uses the generic UDP listener, but other protocols require a specific listener. See the examples in ${OPENNMS_HOME}/{etc/telemetryd-configuration.xml}$, or Telemetryd Listener Reference for details.

To enable and configure a *Listener* for NetFlow v5 on Minion, connect to the *Karaf Console* and set the following properties:

```
$ ssh -p 8201 admin@localhost
...
admin@minion()> config:edit --alias udp-8877 --factory
org.opennms.features.telemetry.listeners
admin@minion()> config:property-set name Netflow-5
admin@minion()> config:property-set class-name
org.opennms.netmgt.telemetry.listeners.UdpListener
admin@minion()> config:property-set parameters.port 8877
admin@minion()> config:property-set parsers.0.name Netflow-5-Parser
admin@minion()> config:property-set parsers.0.class-name
org.opennms.netmgt.telemetry.protocols.netflow.parser.Netflow5UdpParser
admin@minion()> config:update
```



If a configuration management tool is used, the properties file can be created and is used as startup configuration in \${MINION_HOME}/etc/org.opennms.features.telemetry.listeners-udp-8877.cfg.

```
name = Netflow-5
class-name = org.opennms.netmgt.telemetry.listeners.UdpListener
parameters.port = 8877
parsers.0.name Netflow-5-Parser
parsers.0.class-name
org.opennms.netmgt.telemetry.protocols.netflow.parser.Netflow5UdpParser
```



The associated protocol, in this case Netflow-5 must also be enabled on *OpenNMS Meridian* for the messages to be processed.

In some scenarios the exporters address is altered due to network address translation. In this case you can use node meta-data to identify the exporter. Use the metaDataNodeLookup parameter to specify a context-key pair in the form of context:key for the lookup.

This value used for the lookup corresponds to the following fields from the various protocols:

Property	Description
NetFlow v5	engineId
NetFlow v9	sourceId
IPFix	observationDomainId
SFlow	agent_address:sub_agent_id
BMP	bgpId

29.2.4. Node cache configuration (Optional)

By default each *Flow Document* is - if known by *OpenNMS Meridian* - enriched with node information. To reduce the number of queries to the database, the data is cached.

The following cache properties are available to be set in \${OPENNMS_HOME/etc/org.opennms.features.flows.persistence.elastic.cfg:

Property	Description	Requi red	defa ult
<pre>nodeCache.maximumS ize</pre>	The maximum size of the cache	false	1000
nodeCache.expireAf terWrite	Number of seconds until an entry in the node cache is evicted. Set to 0 to disable eviction.	false	300
<pre>nodeCache.recordSt ats</pre>	Defines if cache statistics are exposed via JMX. Set to false to disable statistic recording.	false	true

29.2.5. Classification Exporter Filter cache configuration (Optional)

A rule in the *Classification Engine* may define an exporterFilter. In order to resolve if the filter

criteria matches the address of an exporter a database query is executed. A cache can be configured to cache the result to improve performance.

The following cache properties are available to be set in \${OPENNMS_HOME/etc/org.opennms.features.flows.classification.cfg:

Property	Description	Requi red	defa ult
cache.classificationFilte r.enabled	Enables or disables the cache.	false	fals e
cache.classificationFilte r.maxSize	The maximum size of the cache	false	5000
<pre>cache.classificationFilte r.expireAfterRead</pre>	Number of seconds until an entry in the node cache is evicted. Set to 0 to disable eviction. The timer is reset every time an entry is read.	false	300
nodeCache.recordStats	Defines if cache statistics are exposed via JMX. Set to false to disable statistic recording.	false	true

29.2.6. Configure Kafka forwarder

Enriched flows (with OpenNMS Node data) can also be forwarded to kafka.

Enriched flows are stored in flowDocuments topic and the payloads are encoded using Google Protocol Buffers (GPB). See flowdocument.proto in the corresponding source distribution for the model definitions.

Enable kafka forwarding:

```
$ ssh -p 8101 admin@localhost
...
admin@opennms()> config:edit org.opennms.features.flows.persistence.elastic
admin@opennms()> config:property-set enableForwarding true
admin@opennms()> config:update
```

Configure Kafka server for flows:

```
$ ssh -p 8101 admin@localhost
...
admin@opennms()> config:edit org.opennms.features.flows.persistence.kafka
admin@opennms()> config:property-set bootstrap.servers 127.0.0.1:9092
admin@opennms()> config:update
```

29.3. Classification Engine

The *Classification Engine* applies a set of user- and/or system-defined rules to each flow to classify it.

This allows users to group flows by applications, e.g. if all flows to port 80 are marked as http.

In order to classify a flow, a rule must be defined. A rule defines at least a name, which the flow is classified with, and additional parameters which must match for a successful classification.

29.3.1. Rule definition

A rule has the following fields:

Name	Mandatory	Description
group	mandatory	The group in which this rule was placed, e.g. system-defined, see also Rule Groups
position	mandatory	The position at which it is placed within its group, relevant for the Order of evaluation.
name	mandatory	The name the flow is classified with, e.g. http
dstPort	optional	The dstPort of the flow must match this port. May be a range or list of ports, e.g. 80,8080,8980, or 8000-9000.
dstAddress	optional	The dstAddress of the flow must match this address. May contain wildcards.
srcPort	optional	The srcPort of the flow must match this port. See dstPort for more details.
srcAddress	optional	The srcAddress of the flow must match this address. See dstAddress for more details.
exporterFilter	optional	The exporter of the flow must match this criteria. It supports all capabilities of the <i>OpenNMS</i> <i>Meridian Filters API</i> .
protocol	optional	The ip protocol of the flow must match this criteria.

Even if all fields (besides group, position and name) are optional, at least one of them must be defined to be considered a valid rule.

A list of pre-defined rules already exist in the group pre-defined. The pre-defined rules are inspired

by the IANA Service Name and Transport Protocol Port Number Registry. New rules can be defined using the *Classification UI* which can be found in the Admin Menu: Admin \rightarrow Configure OpenNMS \rightarrow Manage Flow Classification

29.3.2. Omnidirectional Rules

Rules can be marked as omnidirectional which additionally evaluates the rules with interchanged endpoint addresses and ports. This is helpful if traffic related to a matching classification should be classified the same way.

29.3.3. Rule Groups

Rules live within a rule group. New groups can be added, edited and deleted via the *Classification UI*. The pre-defined group is read only. It (and it's rules) can not be altered.

29.3.4. Order of evaluation

Rules and groups have a position. Lower positions are evaluated first. The position of a rules group is more important than the rules position within its group. The system defined group is always evaluated last.

Group Position	Group	Rule Position	Rule
1	group 1	1	rule 1.1
1	group 1	2	rule 1.2
1	group 1	3	rule 1.3
1	group 1	4	rule 1.4
2	group 2	1	rule 2.1
2	group 2	2	rule 2.2
2	group 2	3	rule 2.3
2	group 2	4	rule 2.4
3	group 3	1	rule 3.1
3	group 3	2	rule 3.2

An example of an evaluation:

The positions of rules and groups can be changed by drag and drop or by editing the position field in the edit dialogs.

29.3.5. Verification

With a more complex set of rules it is not always easy to verify if everything is configured correctly. To make things a bit easier, the *Classification UI* allows to test/verify a classification. To do so, please navigate to the *Classification UI*: Admin \rightarrow Configure OpenNMS \rightarrow Manage Flow Classification and select the *Test Classification* action in the top right. This allows to simulate a flow being send to

the *Classification Engine* with certain fields.

29.3.6. Example

Let's assume the following rules are defined:

name	srcAddress	srcPort	dstAddress	dstPort	protocol	exporterFilt er
OpenNMS			10.0.0.1	8980	tcp,udp	
http				80,8980,8080 ,9000	udp,tcp	
https				443		
Exporters						categoryNa me == 'Exporters'

The following flows are send to *OpenNMS Meridian* and with the rules defined above classified accordingly.

Flow	Classification
protocol: tcp,	http
srcAddress: 10.0.0.5, srcPort: 60123,	
dstAddress: 54.246.188.65, dstPort: 80,	
exporterAddress: 10.0.0.55	
protocol: tcp,	https
srcAddress: 10.0.0.5, srcPort: 60123,	
dstAddress: 54.246.188.65, dstPort: 443,	
exporterAddress: 10.0.0.55	
protocol: tcp,	OpenNMS
srcAddress: 10.0.0.5, srcPort: 60123,	
dstAddress: 10.0.0.1, dstPort: 8980,	
exporterAddress: 10.0.0.55	

29.4. Aggregation

The flow query engine supports rendering Top-N metrics from pre-aggregated documents stored in Elasticsearch. These can be used to help alleviate compute load on the Elasticsearch cluster, particularly for environments with large volumes of flows (>10,000 flows/sec).

In order to use this functionality you must enable the Kafka forwarder as described in [ga-flow-support-kafka-forwarder] and setup Nephron to process the flows.



Nephron currently requires an Apache Flink cluster to deploy the job.

Thefollowingpropertiescanbetsetin\${OPENNMS_HOME/etc/org.opennms.features.flows.persistence.elastic.cfgtocontrolthequeryengine to use aggregated flows:

Property	Description		default
alwaysUseRawForQuerie s	Set to true to use raw flow documents to respond to all queries and effectively disable the use of aggregated flows.		true
alwaysUseAggForQuerie s	Set to true to use raw aggregated flow documents to respond to all queries and effectively disable the use of raw flows.		false
timeRangeDurationAggr egateThresholdMs	Queries with time range filters that have a duration greater than this value will use aggregated flows when possible.	false	120000 (2 minutes)
timeRangeEndpointAggr egateThresholdMs	Queries with time range filters that have an endpoint that is older than this value will use aggregated flows when possible.	false	604800000 (7 days)

Chapter 30. Kafka Producer

30.1. Overview

The *Kafka Producer feature* allows events, alarms, nodes, topologies and metrics from *OpenNMS Meridian* to be forwarded to *Kafka*.

These objects are stored in different topics and the payloads are encoded using Google Protocol Buffers (GPB). See opennms-kafka-producer.proto and collectionset.proto in the corresponding source distribution for the model definitions.

30.1.1. Events

The *Kafka Producer* listens for all events on the event bus and forwards these to a *Kafka* topic. The records are keyed by event *Id* and contain a *GPB* encoded model of the event.

By default, all events are forwarded to a topic named events.

The name of the topic used can be configured, and an optional filtering expression can be set to help control which events are sent to the topic.

30.1.2. Alarms

The *Kafka Producer* listens for changes made to the current set of alarms and forwards the resulting alarms to a *Kafka* topic. The records are keyed by alarm reduction key and contain a *GPB* encoded model of the alarm. When an alarm is deleted, a *null* value is sent with the corresponding reduction key. Publishing records in this fashion allows the topic to be used as a *KTable*. The *Kafka Producer* will also perform periodic synchronization tasks to ensure that the contents of the Kafka topic reflect the current state of alarms in the *OpenNMS Meridian* database.

By default, all alarms (and subsequent updates) are forwarded to a topic named alarms.

The name of the topic used can be configured, and an optional filtering expression can be set to help control which alarms are sent to the topic.

30.1.3. Nodes

If an event or alarm being forwarded reference a node, then the corresponding node is also forwarded. The records are keyed by "node criteria" (see bellow) and contain a *GPB* encoded model of the alarm. A caching mechanism is in place to help avoid forwarding nodes that have been successfully forwarded, and have not changed since.

The name of the topic used can be configured.



The node topic is not intended to include all of the nodes in the system, it only includes records for nodes that relate to events or alarms that have been forwarded.

Node Criteria

The *node criteria* is a string representation of the unique identifier for a given node. If the node is associated with a *foreign source (fs)* and *foreign id (fid)*, the node criteria resulting node criteria will be the name of the *foreign source*, followed by a colon (:) and then the foreign id i.e. (fs:fid). If the node is not associated with both a *foreign source* and *foreign id*, then the node id (database id) will be used.

30.1.4. Topologies

The *Kafka Producer* listens for changes made to the current set of topologies (bridge, cdp, isis, lldp and ospf) and forwards the resulting messages to *Kafka* topics. A topic is defined either for Topology Vertex Update Message and another topic is defined for Topology Edge Update Message. The topologies are provided by the *enhanced linkd updaters* via the OnmsTopology API. An *Updater* send OnmsTopologyMessage to the subscribers. The records are keyed by *GPB* encoded key of protocol and TopologyRef and contain a *GPB* encoded model of the Vertex or Edge. When a Vertex or an Edge is deleted, a *null* value is sent with the corresponding encoded *GBP* key. Publishing records in this fashion allows the topic to be used as a KTable.



The topologies topic are not intended to include all of the vertices in the system, it only includes records for vertex that relate to topology messages that have been forwarded.

30.1.5. Metrics

The *Kafka Producer* can be used to write metrics to *Kafka* either exclusively, or in addition to an existing persistence strategy i.e. RRD or Newts. The metrics are written in the form of "collection sets" which correspond to the internal representation used by the existing collectors and persistence strategies. The records are keyed by Node ID or by IP Address if no Node ID is available and contain a *GPB* encoded version of the collection sets. The records are keyed in this fashion to help ensure that collection sets related to the same resources are written to the same partitions.

When enabled (this functionality is disabled by default), the metrics are written to a topic named metrics.



When exclusively writing to *Kafka*, no metrics or resource graphs will be available on the *OpenNMS Meridian* instance.

30.2. Enabling the Kafka Producer

The Kafka Producer is disabled by default and can be enabled as follows.

First, login to the *Karaf* shell of your *OpenNMS Meridian* instance and configure the *Kafka* client settings to point to your *Kafka* broker. See Producer Configs for a complete list of available options.

```
$ ssh -p 8101 admin@localhost
...
admin@opennms()> config:edit org.opennms.features.kafka.producer.client
admin@opennms()> config:property-set bootstrap.servers 127.0.0.1:9092
admin@opennms()> config:update
```

Next, install the opennms-kafka-producer feature from that same shell using:

```
admin@opennms()> feature:install opennms-kafka-producer
```

In order to ensure that the feature continues to be installed as subsequent restarts, add opennmskafka-producer to the featuresBoot property in the \${OPENNMS_HOME}/etc/org.apache.karaf.features.cfg.

30.3. Configuring the Kafka Producer

The *Kafka Producer* exposes the following options to help fine tune its behavior.

Name	Default Value	Description
eventTopic	events	Name of the topic used for events. Set this to an empty string to disable forwarding events.
alarmTopic	alarms	Name of the topic used for alarms. Set this to an empty string to disable forwarding alarms.
alarmFeedbackTopic	alarmFeedba ck	Name of the topic used for alarm feedback. Set this to an empty string to disable forwarding alarm feedback.
nodeTopic	nodes	Name of the topic used for nodes. Set this to an empty string to disable forwarding nodes. Set this to an empty string to disable forwarding topologies.
topologyVertexTopi c	vertices	Name of the topic used for topology vertices.
topologyEdgeTopic	edges	Name of the topic used for topology edges.
metricTopic	metrics	Name of the topic used for metrics.
eventFilter	-	A <i>Spring SpEL expression</i> (see bellow) used to filter events. Set this to an empty string to disable filtering, and forward all events.
alarmFilter	-	A <i>Spring SpEL expression</i> (see bellow) used to filter alarms. Set this to an empty string to disable filtering, and forward all alarms.
forward.metrics	false	Set this value to true to enable forwarding of metrics.

Name	Default Value	Description
nodeRefreshTimeout Ms	300000 (5 minutes)	Number of milliseconds to wait before looking up a node in the database again. Decrease this value to improve accuracy at the cost of additional database look ups.
suppressIncrementa lAlarms	true	Suppresses forwarding alarms that differ only by count or last event time. Set this to false to prevent suppressing these alarms.
kafkaSendQueueCapa city	1000	The capacity for the queue of Kafka messages that is used when a Kafka message is pushed but Kafka is unavailable.
startAlarmSyncWith CleanState	false	Set this to true to force the Kafka Streams client to start with a clean state on every boot.

30.3.1. Configuring Filtering

Filtering can be used to selectively forward events and/or alarms to the Kafka topics.

Filtering is performed using a Spring SpEL expression which is evaluated against each object to determine if it should be forwarded. The expression must return a boolean value i.e. true or false.

Enabling Event Filtering

To enable event filtering, set the value of the eventFilter property to a valid SpEL expression.

```
$ ssh -p 8101 admin@localhost
...
admin@opennms()> config:edit org.opennms.features.kafka.producer
admin@opennms()> config:property-set eventFilter
'getUei().equals("uei.opennms.org/internal/discovery/newSuspect")'
admin@opennms()> config:update
```

In the example above, the filter is configured such that only events with the given *UEI* are forwarded. Consult the source code of the org.opennms.netmgt.xml.event.OnmsEvent class in your distribution for a complete list of available properties.

Enabling Alarm Filtering

To enable alarm filtering, set the value of the alarmFilter property to a valid SpEL expression.

```
$ ssh -p 8101 admin@localhost
...
admin@opennms()> config:edit org.opennms.features.kafka.producer
admin@opennms()> config:property-set alarmFilter 'getTTicketId() != null'
admin@opennms()> config:update
```

In the example above, the filter is configured such that only alarms that are associated with a *ticket*

id are forwarded. Consult the source code of the org.opennms.netmgt.model.OnmsAlarm class in your distribution for a complete list of available properties.

30.3.2. Enabling Metric Forwarding

To enable metric forward, set the value of the forward.metrics property to true.

```
$ ssh -p 8101 admin@localhost
...
admin@opennms()> config:edit org.opennms.features.kafka.producer
admin@opennms()> config:property-set forward.metrics true
admin@opennms()> config:update
```

Enabling Exclusive Metric Forwarding

Once metric forwarding is enabled, you can use this as the exclusive persistence strategy as follows by setting the following system property:

```
echo 'org.opennms.timeseries.strategy=osgi' >
"$OPENNMS_HOME/etc/opennms.properties.d/kafka-for-metrics.properties"
```

30.3.3. Configuring Topic Names

By default five topics are created i.e. events, alarms, nodes, vertices, and edges. To change these, you can use:

```
$ ssh -p 8101 admin@localhost
...
admin@opennms()> config:edit org.opennms.features.kafka.producer
admin@opennms()> config:property-set eventTopic ""
admin@opennms()> config:property-set nodeTopic "opennms-nodes"
admin@opennms()> config:update
```

In the example above, we disable event forwarding by setting an empty topic name and change the node topic name to opennms-nodes.

```
$ ssh -p 8101 admin@localhost
...
admin@opennms()> config:edit org.opennms.features.kafka.producer
admin@opennms()> config:property-set topologyVertexTopic "opennms-bridge-vertex"
admin@opennms()> config:property-set topologyEdgeTopic "opennms-edge-vertex"
admin@opennms()> config:update
```

In the example above, we set the vertex and edge topics to be different to default.

30.4. Shell Commands

The *Kafka Producer* also provides a series of shell commands to help administering and debugging the service.

30.4.1. opennms:kafka-list-alarms

The list-alarms command can be used to enumerate the reduction keys and show the associated event labels for the alarms that are present in the topic. This command leverages functionality used by the alarm synchronization process, and as a result this must be enabled in for this command to function.

30.4.2. kafka-producer:sync-alarms

The sync-alarms command can be used to manually trigger the alarm synchronization process.

30.4.3. opennms:kafka-evaluate-filter

The evaluate-filter command can be used to test arbitrary *SpEL* filtering expressions against alarms or events.

Evaluating filters against alarms

To test a filter against an alarm, specify the database id of the alarm and the expression to test:

admin@opennms> opennms:kafka-evaluate-filter --alarm-id 57
"getReductionKey().contains('n33')"
SPEL Expression: getReductionKey().contains('n33')
Alarm with ID 57 has reduction key:
uei.opennms.org/alarms/trigger:n33:0.0.0.0:HTTPS_POOLs
Result: true

Evaluating filters against events

To test a filter against an event, specify the *UEI* of the event and the expression to test:

```
admin@opennms> opennms:kafka-evaluate-filter --event-uei
uei.opennms.org/alarms/trigger "getUei().contains('alarm')"
SPEL Expression: getUei().contains('alarm')
Event has UEI: uei.opennms.org/alarms/trigger
Result: true
```

In this case, a new event will be created with the given *UEI*, and the filter will be evaluated against this new event object. At this time, existing events cannot be referenced by this tool, so this functionality only serves to help make sure the expressions are syntactically valid.

Chapter 31. Alarm Correlation

31.1. Situation Feedback

31.1.1. Introduction

Situation Feedback allows operators to provide real time feedback on Alarm Correlation.

31.1.2. Installation

Situation Feedback needs to be enabled by installing the feature from the Karaf shell:

feature:install opennms-situation-feedback

In order to ensure that the feature continues to be installed as subsequent restarts, add opennmssituation-feedback to the featuresBoot property in the \${OPENNMS_HOME}/etc/org.apache.karaf.features.cfg.

31.1.3. Requirements

The feature requires Elasticsearch to persist the feeback records.

Configuration Elasticsearch persistence

From a Karaf shell on your *OpenNMS Meridian* instance, start by configuring the Situation Feedback persistence to use your Elasticsearch cluster:

```
$ ssh -p 8101 admin@localhost
...
admin@opennms()> config:edit org.opennms.features.situation-
feedback.persistence.elastic
admin@opennms()> config:property-set elasticUrl http://elastic:9200
admin@opennms()> config:update
```



This configuration is stored in \${OPENNMS_HOME/etc/org.opennms.features.situation-feedback.persistence.elastic.cfg. See Elasticsearch Integration for more information.

Installing the feature exposes a ReST endpoint that *OpenNMS Helm* uses to display and submit feedback.

Further information on the ReST API can be found in the Developer Guide

Chapter 32. Meta-Data

OpenNMS Meridian supports the assignment of arbitrary metadata to nodes, interfaces and services. You can then use this metadata to dynamically configure service monitoring, performance data collection, service detection, and expression-based thresholds.

The metadata is a simple triad of strings containing a context, a key and the associated value. Each node, each interface and each service can have an arbitrary number of metadata elements assigned to it. The only restriction is that the tuple of context and key must be unique in the element with which it is associated.

The association of metadata with nodes, interfaces and services happens during provisioning. Users can add, query, modify, or delete metadata through the requisition editor in the web UI, or through the ReST endpoints.

A simple domain-specific language (DSL) allows users to access the metadata associated with the elements they are working on, and use it as a variable in parameters and expressions. There is no limitation in defining metadata: users can decide how to define it and use it in expressions.

View metadata currently assigned to nodes, interfaces and services, on the details page associated with that entity in the web UI:

[metadata view]

32.1. Contexts

A context distinguishes different kinds of metadata use. OpenNMS Meridian uses several default contexts: pattern (used with polling), requisition, node, interface, and service.

Three special contexts provide details about nodes, interfaces and services objects. Each context has keys associated with it that you can use in a metadata expression.

You can create user-defined contexts in the ReST API by prefixing the context name with X-. Using an X- prefix can help to avoid future OpenNMS Meridian contexts interfering with a user-defined context, since OpenNMS Meridian contexts are not prefixed in this way.

32.1.1. Node context

The node context provides details about the node currently processed. The following keys are available under this context:

Context:Key	Description
node:label	The node's label
node:foreign-source	The node's foreign source name
node:foreign-id	The node's foreign ID
node:netbios-domain	The NetBIOS domain as provided by SNMP

Context:Key	Description
node:netbios-name	The NetBIOS name as provided by SNMP
node:os	The node's operating system
node:sys-name	The system name of the node
node:sys-location	The system location of the node
node:sys-contact	The system contact specified for the node
node:sys-description	The system description of the node
node:location	The node's monitoring location name
node:area	The node's monitoring location area

32.1.2. Interface context

The interface context provides details about the interface currently processed. The following keys are available under this context:

Context:Key	Description
interface:hostname	The hostname associated with the IP address of the interface
interface:address	The IP address of the interface
interface:netmask	The netmask of the interface
interface:if-index	The SNMP interface index
interface:if-alias	The SNMP interface alias
interface:if-description	The SNMP interface description
interface:phy-addr	The physical address of the interface

32.1.3. Service context

The service context provides details about the service currently processed. The following key is available under this context:

Context:Ke	Description
У	
service:name	The full name of the service

32.2. Adding Metadata through the Web UI

You can edit the requisition context in the web UI:

- 1. Under the admin menu, select Configure OpenNMS.
- 2. Select Manage Provisioning Requisitions.
- 3. Click the edit icon beside the requisition you want to work with.
- 4. Click edit beside the node you want to work with.
- 5. In the **Meta-Data** area, click **Add Meta-Data**.

[metadata add]

- 6. Specify node or interface as the **scope** of where the metadata will apply.
- 7. Specify the key and a value and click **Save**.

32.3. The Metadata DSL

The metadata DSL allows interpolation of metadata into a parameter. The syntax allows the use of patterns like $context_fallback:key_fallback|\cdots|default$ in an expression.

Each expression can contain multiple references to metadata that will be replaced with the corresponding value during evaluation. Placeholders start with \${ and end with } containing a reference to a context-key pair. You may choose to define multiple fallback context-key pairs and and an optional trailing default value. Separate context and key by a :. Use a | to separate optional fallback context-key pairs and default value. If the first context:key item is not available (not on a service, interface, node or any other of the special contexts) the next one after the | is used. The last one, the default value, is not interpreted as a context:key but is used as a literal and will always succeed.

Examples

\${requisition:username}

Will resolve to the username as defined in the requisitioning UI or an empty value, if there is no such username defined.

A placeholder can contain an optional default value which is separated by a |.

\${requisition:username|admin}

Will resolve to the username as defined in the requisitioning UI or to the value admin, if there is no such username defined.

Use fallback context-key pairs in a placeholder after the primary context-key pair to specify other values if the primary context-key pair is not defined. Separate each fallback context-key-pair by a |.

\${requisition:username|requisition:account|admin}

Will resolve to the username as defined in the requisitioning UI. If there is no such username defined, the fallback account will be used. If neither exist, the fallback value admin will be used.

To resolve the value associated with context-key pair, the DSL uses scopes that determine the resolution order. The last scope will be queried first and if a scope does not contain the queried context-key tuple, the next one will be queried. For example, the resolution of a query on a service

entity would be service metadata \rightarrow interface metatdata \rightarrow node metadata. On an interface, it is metadata \rightarrow interface metatdata \rightarrow node metadata. On the node level, only the node is queried.

Which scopes are available depends on the environment for which an expression is evaluated and is documented in the corresponding places elsewhere in this guide. Some environments also provide additional scopes that are not backed by the persisted metadata but provide additional metadata related to the current evaluation.

32.3.1. Testing an expression

To test an expression, there is a karaf shell command which interpolates a string containing a pattern to the final result:

```
admin@opennms> opennms:metadata-test -n 1 -i 192.168.0.100 -s ICMP
'${fruits:apple|fruits:banana|vegetables:tomato|blue}'
_ _ _
Meta-Data for node (id=1)
fruits:
  apple='green'
  banana='yellow'
vegetables:
  tomato='red'
Meta-Data for interface (ipAddress=192.168.0.100):
fruits:
  apple='brown'
_ _ _
Meta-Data for service (name=ICMP):
fruits:
  apple='red'
Input: '${fruits:apple|fruits:banana|vegetables:tomato|blue}'
Output: 'red'
admin@opennms>
```

32.3.2. Uses

The following places allow the use the Metadata DSL:

- Provisioning Detectors
- Service Assurance
- Performance Management
- TTLs with Minion
- Expression-Based Thresholds

Chapter **OpenNMS** Meridian 33. Administration


This section describes administrative tasks, such as shutdown and restart, you may need to perform with your OpenNMS Meridian instance.

This chapter provides an example of the order to follow when shutting down and restarting a sample OpenNMS Meridian system: OpenNMS Meridian core layer, persistence and messaging layer, and database layer.

Grafana

Kibana

OpenNMS Restart Process Restart Shutdown 1. Persistence and Messaging laver (in any order) 2. OpenNMS layer (in any order) 2. OpenNMS layer (in any order) 3. Persistence and Messaging layer (in any order) Note: You can restart dashboard applications at any time, but they will not show any useful until all components in the persistence and OpenNMS layers are started.



Note that restarting the whole stack is rare. Usually, restarting the OpenNMS Meridian core happens for reconfiguration or to run upgrades. A core restart takes between 2-5 minutes depending on memory configuration. Minion and Sentinel restart faster.

Keep in mind that when shutting down the OpenNMS Meridian core, there will be no notifications, alarms, outage detection, performance data collection, thresholding, or flows. After restarting there will be gaps in your performance graphs for the shutdown time.

Restarting components in the persistence and messaging layer normally happens only for upgrades or catastrophic failures. Exercise caution with restarting components in this layer, since there is the risk of data loss.



The steps below are illustrative for a sample Linux setup. Your OpenNMS Meridian may be different. Documenting procedures for each setup is beyond the scope of this document. You must be root to run the commands listed below.


33.1. Shutdown

Shutdown components in the following order:

1. Dashboard applications such as Grafana and Kibana.

```
systemctl stop grafana-server
systemctl stop kibana
```

- 2. OpenNMS Meridian Core application (Core, Sentinel, Minion), in any order.
 - a. Turn off notifications first.
 - i. Login to the OpenNMS Meridian UI.
 - ii. In the top right corner choose **User name Configure OpenNMS**:



iii. Under Event Management, turn off Notification Status and click Update.



- b. Access the OpenNMS Meridian system via CLI (putty, SecureCRT, etc.).
- c. Become a root user via the following command: sudo su -
- d. Type the following commands:

```
systemctl stop opennms
systemctl stop minion
systemctl stop sentinel
```

3. Persistence and messaging components such as PostgreSQL, Cassandra, Kafka, etc., in any order:

```
systemctl stop postgresql-12
systemctl stop cassandra
systemctl stop elasticsearch
```



Neither Kafka nor Zookeeper have systemd definitions. The way to control the processes depends on how they were installed, and is beyond the scope of this documentation.

33.2. Restart

Restart components in the following order:

1. Persistence and messaging components such as PostgreSQL, Cassandra, Kafka, etc., in any order:

```
systemctl start postgresql-12
systemctl start cassandra
systemctl start elasticsearch
```

2. OpenNMS Meridian Core application second, in any order.

systemctl start opennms systemctl start minion systemctl start sentinel

a. In the UI, turn the Notification Status to **On** and click **Update**.

3. Dashboard applications like Grafana and Kibana last so they function properly.

systemctl start grafana-server systemctl start kibana



You can restart dashboard applications at any time, but they will not show any useful information until all components in the persistence and OpenNMS Meridian layers have started.